

Dashboard Guide

Operations Center 5.0

March 21, 2014

Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page](#) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2008-2014 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc.
1800 South Novell Place
Provo, UT 84606
U.S.A.
www.novell.com

Online Documentation

To access the latest online documentation for this and other Novell products, see the [Operations Center 5.0 documentation Web site](#).

Novell Trademarks

For Novell trademarks, see [the Novell Trademark and Service Mark list](#).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	9
1 About the Operations Center Dashboard	11
1.1 Getting Started with the Dashboard	11
2 Dashboard Installation	13
2.1 Performance Considerations	13
2.2 Installing the Dashboard	13
2.2.1 Verifying Your Operations Center Server's Default Accounts and Configuration Settings	14
2.2.2 Installing the Dashboard	16
2.2.3 Configuring the Dashboard Database	18
2.2.4 Verifying the Dashboard Default Time Zone for User Accounts	20
2.2.5 Configuring the Dashboard and Operations Center	20
2.2.6 Starting the Dashboard for the First Time and Verifying the Installation	24
2.2.7 Update Dashboard Configuration Settings	25
2.3 Starting and Stopping the Dashboard	26
2.3.1 Starting the Dashboard	27
2.3.2 Stopping the Dashboard	27
2.4 Enterprise-Wide Trusted Sites	27
3 Dashboard Configuration	29
3.1 About the Dashboard Control Panel	30
3.2 Updating Dashboard Administrative Configurations	31
3.2.1 Updating Dashboard Administrative Configurations	32
3.2.2 Updating the Dashboard Site Name & Logo	33
3.3 Configuring Auto-Login for Single Sign On (SSO)	33
3.3.1 Implementing Auto-Login with Your Web Server	34
3.3.2 Disabling Direct Client Login	35
3.4 Setting Session Timeout	36
3.4.1 Setting Operations Center Server Timeout	36
3.4.2 Setting Dashboard Timeout	36
3.4.3 Disabling Dashboard Session Timeout	37
3.4.4 Configuring the "Remember Me" Feature and Setting Browser Cookie Lifespan	37
3.5 Changing the Dashboard Account for Persistent Connection	38
3.6 Configuring the Mail Server	39
3.7 Configuring the Proxy Server	40
3.8 Creating Operations Center Server Profiles	41
3.9 Understanding Portal Properties Files	43
3.10 Deploying Portlets to the Dashboard	44
3.10.1 Deploying a Portlet	44
3.10.2 Deploying a Portlet using Hot Deploy	44
3.11 Default Portlet Settings	45
3.12 Granting or Denying Access to Portlets	47

4	User Accounts	49
4.1	Operations Center and Dashboard Interaction	49
4.1.1	Understanding User and Group Synchronization	50
4.1.2	Updating Access Control Synchronizer Settings	51
4.1.3	Understanding the Use of the Default Admin Account	51
4.1.4	Understanding Access and Permissions for User Accounts	51
4.2	Understanding User Account Requirements	52
4.2.1	Understanding User Name Restriction	52
4.2.2	Understanding Unique E-Mails	52
4.2.3	Understanding Password Policy	53
4.3	Configuring Dashboard User Account Structure	53
4.3.1	Understanding the Dashboard Portal Architecture	54
4.3.2	Configuring Corporate Hierarchy via Organizations and Locations	56
4.3.3	Configuring Groups	59
4.4	Managing User Accounts	60
4.4.1	Self-Service User Account Creation, Authentication and Notification Settings	61
4.4.2	Default Associations for User Accounts	62
4.4.3	Creating User Accounts	62
4.4.4	Activating, Deactivating, and Deleting Accounts	64
4.5	Understanding User Sign On	64
4.6	User Maintained Account Settings	65
5	Personal Pages, Page Configurations, and Communities	67
5.1	Customizing Default Personal Pages	67
5.2	Creating and Maintaining Communities	68
5.2.1	Creating a New Community	70
5.2.2	Performing Actions on a Community	70
5.2.3	Updating Community Settings	71
5.3	Adding Pages	72
5.3.1	Adding Child Pages	72
5.3.2	Editing an Existing Page	74
5.4	Community Provisioning	74
5.5	Assign Users to a Community	76
5.5.1	Assign Users Directly to a Community	76
5.5.2	Assign Groups, Organizations, or Locations to a Community	77
5.5.3	Remove Users	78
5.6	Changing Page Layout	78
5.7	Changing the Look and Feel	79
5.7.1	The Default Themes Library	79
5.7.2	Selecting the Look and Feel	85
5.7.3	Installing Additional Themes	85
5.8	Configuring Default Home for User Groups, Communities and Organizations	86
5.9	Importing and Exporting Data and Configurations from User Groups, Communities, or Organizations	88
6	Adding Content to a Page Using Portlets	91
6.1	Understanding Available Content via Portlets	91
6.2	Adding Portlets	94
6.2.1	Adding a Portlet	95
6.2.2	Moving Portlets on a Page	96
6.2.3	Configuring Portlet "Look and Feel"	96
6.3	Understanding Sharing Portlets	97
6.4	Adding a Site Map, Breadcrumbs, or Navigation to a Page	97
6.5	Adding a Refresh Feature to Pages	99

6.6	Integrating Reports from External Reporting Tools Using iFrames	99
-----	---	----

7 Exposing Operations Center Content **103**

7.1	Understanding the Operations Center Portlets	103
7.1.1	Understanding Data Types in Operations Center	104
7.1.2	Understanding Custom Colors in Portlets	106
7.1.3	Setting Options for a Portlet	107
7.2	Configuring Portlet View Links	107
7.3	Configuring Home and Starting Elements	108
7.3.1	Changing the User's Default Home Element	109
7.3.2	Configuring Starting Elements for Portlets	110
7.4	Using Navigation Mode to Drive Multiple Portlets	110
7.4.1	Understanding Drive Configuration	110
7.4.2	Tagging Portlets to Drive Specific Portlets	111
7.5	Creating Custom Right-Click Menus	112
7.5.1	Adding Right-Click Context Menus	112
7.5.2	Accessing URLs from Right-Click Menus	115
7.5.3	Issuing JavaScript Commands from Right-Click Menus	117
7.5.4	Adding Portlet View Links to Right-Click Menus	118
7.5.5	Performing Operations Center Server-Side Operations from Right-Click Menus	119
7.6	Configuring URL Linking for the Layout Portlet	121
7.7	Viewing Source Data for Charts	122
7.8	Setting Technical Configurations for Operations Center Portlets	123
7.8.1	Configuring Default Alarms Limits Returned from the Operations Center Server	124
7.8.2	Configuring Performance Data Point Retrieval from the Operations Center Server	124
7.8.3	Configuring Regular Expression Look Up for the Performance Portlet	125
7.8.4	Selecting an Alternate Operations Center Server Connection	126
7.8.5	Scheduling Portlets	126
7.8.6	Automatic Data Updates with Push Technology	131
7.9	Installing Third-Party Software	131
7.9.1	SVG Viewer	132
7.9.2	Flash Player	132
7.10	Troubleshooting Operations Center Portlets	132
7.10.1	Operations Center server Unavailable	132

8 Configuring Operations Center Portlets **133**

8.1	Configuring the Alarms Portlet	134
8.1.1	Viewing Alarms	135
8.1.2	Performing Alarms General Configuration	137
8.1.3	Applying and Creating Alarm Filters	138
8.1.4	Performing Alarm Operations	144
8.2	Configuring the Charting Portlet	144
8.3	Configuring the Element Properties Portlet	147
8.4	Configuring the Information Portlet	147
8.4.1	Viewing Element Information	148
8.4.2	Configuring the Information Portlet	150
8.5	Configuring the Layout Portlet	153
8.5.1	Navigating in the Layout Portlet	153
8.5.2	Configuring the Layout Portlet	154
8.6	Configuring the Navigation Portlet	156
8.7	Configuring a Performance Portlet	157
8.7.1	Viewing a Performance Chart	159
8.7.2	Configuring the Performance Portlet	159
8.8	Configuring the Properties Table Portlet	165
8.8.1	Viewing the Properties Table Listing	166

8.8.2	Configuring the Portlet Properties Table	166
8.9	Configuring the Public End User View Portlet	169
8.10	Configuring the Root Cause Portlet	170
8.11	Search Portlet	171
8.11.1	Configuring Search Parameters	172
8.11.2	Configuring Properties for Found Elements	173
8.12	Configuring the Show Impacted Portlet	175
8.13	Configuring the Starter Portlet	176
8.14	Configuring the Status Portlet	178
8.14.1	Viewing the Status Portlet	178
8.14.2	Configuring the Status Portlet	179
8.15	Understanding the Summary Portlet	180
8.16	Configuring the Tree Map Portlet	181
8.16.1	Changing the Tree Map Portlet Display	181
8.16.2	Configuring the Tree Map	182

9 SLA Reporting Portlets 183

9.1	Understanding the SLA Reporting Portlets	183
9.1.1	Generating SLA Report Portlets	183
9.1.2	SLA Report Portlet Options	184
9.2	Configuring the SLA Compliance Portlet	185
9.2.1	Setting Up the SLA Compliance Portlet	187
9.2.2	Using the SLA Compliance Portlet	190
9.2.3	Regenerating the Report with Ad-Hoc Options	191
9.3	Configuring the SLA Status Portlet	192
9.3.1	Setting Up the SLA Status Portlet	193
9.3.2	Using the SLA Status Portlet	196
9.3.3	Setting Up User Navigation to Drive an SLA Status Portlet	196

10 Chart Builder Portlet 199

10.1	Predefined Templates	199
10.1.1	Chart Display Examples	200
10.1.2	Deploying Charts	203
10.1.3	Setting Up the SLA Status Dashboard	204
10.2	Custom Templates	205
10.2.1	Creating the Template File	206
10.2.2	Integrating Operations Center Data	209
10.2.3	Creating Drill-Down URLs for a Chart	211
10.2.4	An Example: Modifying a PCXML File with JSP Tags	211
10.2.5	Uploading New Templates	213
10.2.6	Deleting Templates	213

11 Portal and Community Permissions 215

11.1	Assigning Permissions Using Roles	215
11.1.1	Community Roles	216
11.1.2	Portal Administration Roles	219
11.1.3	Configuring Roles	221
11.1.4	Understanding the Power Users Role	222
11.1.5	Granting Role Permissions for Other Roles	222
11.2	Setting Individual Permissions	223
11.2.1	Assigning Individual Permissions to Pages	223
11.2.2	Assigning Individual Permissions to a Portlet	224
11.3	Delegating Tasks with Roles	225
11.4	Verifying User Permissions	225

12 Advanced Administrative Topics	227
12.1 Encrypting the Dashboard Database Password	227
12.2 Configuring Dashboard Ports for RMI Callbacks	228
12.3 Enabling the Dashboard for Section 508 Accessibility	228
12.4 Moving a Dashboard Configuration	229
12.4.1 Preparing to Move a Dashboard Configuration	229
12.4.2 Moving a Dashboard Configuration	230
12.5 Upgrading the Dashboard	230
12.5.1 About Patches	231
12.5.2 Installing Patches	231
12.5.3 Rolling Back a Patch Installation	233
12.5.4 Upgrading myMO/the Dashboard	233
12.5.5 Upgrading from the Dashboard Embedded Database to Oracle or SQL Server	235
12.6 Performing System Recovery	236
A System Properties File	237
A.1 Overriding System Settings in the Systems Properties File	237
A.2 Viewing the Default System Properties	238
B Running a Console or Unattended Installation	243
B.1 Console Installation	243
B.2 Unattended Installation	244
B.2.1 Running an Unattended Installation	244
B.2.2 Using a Response File	246
B.2.3 Sample Response File	246
C JSP Tag Library Reference	249
C.1 Understanding JSP Tag Libraries in Operations Center	249
C.2 Query Tag Library	250
C.2.1 createQuery	250
C.2.2 performQuery	251
C.3 Constrain Tag Library	251
C.3.1 category	251
C.3.2 element	252
C.3.3 excludeManual	252
C.3.4 local	252
C.3.5 offering	252
C.3.6 objective	252
C.3.7 time	252
C.3.8 timeZone	253
C.4 Expand Tag Library	253
C.4.1 time	253
C.5 Request Tag Library	253
C.5.1 summaryState	254
C.5.2 compliance	254
C.5.3 availability	255
C.5.4 outageCount	255
C.5.5 breachCount	255
C.5.6 outageDuration	256
C.5.7 objectiveInstance	256
C.6 Element Tag Library	256
C.6.1 exists	256
C.7 Result Tag Library	257

C.7.1	iterator	258
C.7.2	ResultTagSupport Class	258

D Troubleshooting Trace Logs 261

D.1	Errors	261
D.1.1	User ID Exception – Unable to Synchronize User	261
D.1.2	Data Dispatcher Exception – Broken Pipe	262
D.2	Warnings	264
D.2.1	No Such LayoutSet Exception	264

E Documentation Updates 265

E.1	March 2014 Patch Release	265
E.2	November 2013 Patch Release	265
E.3	September 2013 Patch Release	266
E.4	April 2013 Patch Release	266
E.5	December 2012 Patch Release	267
E.6	June 2012 Patch Release	269
E.7	February 2012 Patch Release	269
E.8	September 2011 Patch Release	270

About This Guide

The Novell® Operations Center *Dashboard Guide* provides information on how to use the Web-based application that provides Operations Center users with a personalized and portable view into the Operations Center server.

Audience

This guide is intended for dashboard administrators and users.

Guide Sections

The following table shows which sections might be most helpful to you:

If your role is ...	Then you might be interested in ...
General Information	<ul style="list-style-type: none">◆ Chapter 1, "About the Operations Center Dashboard," on page 11
Installer and Administrator	<ul style="list-style-type: none">◆ Chapter 2, "Dashboard Installation," on page 13◆ Chapter 3, "Dashboard Configuration," on page 29◆ Chapter 4, "User Accounts," on page 49◆ Chapter 11, "Portal and Community Permissions," on page 215◆ Chapter 12, "Advanced Administrative Topics," on page 227◆ Appendix A, "System Properties File," on page 237◆ Appendix B, "Running a Console or Unattended Installation," on page 243◆ Appendix D, "Troubleshooting Trace Logs," on page 261
Dashboard Users and Community Page Owners	<ul style="list-style-type: none">◆ Chapter 5, "Personal Pages, Page Configurations, and Communities," on page 67◆ Chapter 6, "Adding Content to a Page Using Portlets," on page 91◆ Chapter 7, "Exposing Operations Center Content," on page 103◆ Chapter 8, "Configuring Operations Center Portlets," on page 133◆ Chapter 10, "Chart Builder Portlet," on page 199

Documentation Updates

In general, Operations Center provides two main sources of information to help you configure and use Operations Center products:

- ◆ **Online help:** The help is part of each product and available from multiple locations depending upon the product; look for help in the upper right of a window or dialog box as a drop-down menu option, a help button, or a question mark symbol (?).
- ◆ **Guides:** Available as PDF files on the installation CD, as well as both PDF and HTML on the documentation Web site, the guides provide an overview of how to solve a problem, complete a task, or use a specific Operations Center product.

For the most recent version of the *Dashboard Guide*, visit the [Operations Center 5.0 documentation Web site](#).

Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path. The > symbol is also used to connect consecutive links in an element tree structure where you can either click a plus symbol (+) or double-click the elements to expand them.

A trademark symbol (®, ™, etc.) denotes a Novell trademark. An asterisk (*) denotes a third-party trademark.

When a single path name can be written with a backslash for some platforms or a forward slash for other platforms, the path name is presented with a forward slash to preserve case considerations in the UNIX* or Linux* operating systems.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to www.novell.com/documentation/feedback.html and enter your comments there.

1 About the Operations Center Dashboard

The Dashboard is a Web-based application that provides Operations Center users with a personalized and portable view into the Operations Center server. It allows for single sign-on, personalization, and integration of data from both Operations Center and other sources.

The Dashboard utilizes portlets to provide functionality and selected content from various sources. Dashboard portlets are JSR-168 compliant and any portlet that uses this standard could be deployed in the Dashboard. Portlets from third-party sources including Liferay v.5.2 are leveraged by the Dashboard.

A portlet is a Web-based application built for integration into a portal; it serves as a frame or container for content. Content, including content alarms from the Operations Center server, can be updated in real time.

For users, the Dashboard provides a personal Web desktop. They can personalize the Dashboard display, customize the content, and save changes between sessions. Not only can private, personal pages be created, but users can join communities that have shared pages. Content can be distributed among communities and the responsibility of moderating content can be delegated to various users.

- ♦ [Section 1.1, “Getting Started with the Dashboard,” on page 11](#)

1.1 Getting Started with the Dashboard

As with any Web site or portal, there are two main phases to using the Dashboard:

1. Install and configure the Dashboard.
2. Build and maintain the Dashboard portal.

When building a dashboard portal, the two primary considerations are users and content:

- ♦ **Users:** The Dashboard uses the same user accounts as the Operations Center server and users must have permissions in Operations Center to access that information in the Dashboard.
- ♦ **Content:** Content is distributed to users through personal pages or shared pages. Personal pages belong to a single user only. Shared pages can be accessed by members of a community.

2 Dashboard Installation

The Dashboard is a separate product with its own installation CD or media download, and is not installed as part of the Operations Center server. For more information about installing Operations Center, see the [Novell Operations Center 5.0 Server Installation Guide](#).

The Dashboard is a Web-based application that requires access to the Operations Center server. While it can be installed on the same server as Operations Center, it doesn't need to be on the same host machine.

For hardware and deployment requirements, see "[Supported Versions and Hardware Requirements](#)" in the [Novell Operations Center 5.0 Getting Started Guide](#).

During installation, various configuration values must be set for the Dashboard. After installation, you must start the Dashboard service. After the installation is verified, deploy additional portlets or make property changes to portlets.

- ♦ [Section 2.1, "Performance Considerations," on page 13](#)
- ♦ [Section 2.2, "Installing the Dashboard," on page 13](#)
- ♦ [Section 2.3, "Starting and Stopping the Dashboard," on page 26](#)
- ♦ [Section 2.4, "Enterprise-Wide Trusted Sites," on page 27](#)

2.1 Performance Considerations

Because the Operations Center Dashboard offers the flexibility to design your own dashboards, you might be required to upgrade hardware, increase memory allocations, alter page designs (including number of charts or expressions on a chart), or limit the amount of users to achieve optimal performance.

Performance can vary based on the number of users, complexity of installation, and amount of data in your dashboard pages. For example, a page might be loading slowly because of the amount of data being charted, the management system involved, or other variables. We suggest you contact Novell Consulting for help in implementing a high performing solution.

2.2 Installing the Dashboard

Do the following in the order listed:

1. [Section 2.2.1, "Verifying Your Operations Center Server's Default Accounts and Configuration Settings," on page 14](#)
2. [Section 2.2.2, "Installing the Dashboard," on page 16](#)
3. [Section 2.2.3, "Configuring the Dashboard Database," on page 18](#)

4. [Section 2.2.5, “Configuring the Dashboard and Operations Center,” on page 20](#)
5. [Section 2.2.6, “Starting the Dashboard for the First Time and Verifying the Installation,” on page 24](#)

2.2.1 Verifying Your Operations Center Server’s Default Accounts and Configuration Settings

Review the following topics for information about the connections and communications with the Operations Center server:

- ♦ [“Confirming Default Server Accounts” on page 14](#)
- ♦ [“Verifying Configuration Settings” on page 14](#)

Confirming Default Server Accounts

By default, the Operations Center’s default admin account is used to maintain a [persistent connection](#) between the Dashboard and the Operations Center server. While this can be changed later, verify the following default accounts still exist on the Operations Center server before installing the Dashboard:

- ♦ admin
- ♦ guest

If either of these accounts no longer exists, they need to be re-created. If re-creating the admin account, be sure to give it manage, define, access, and view permissions for the *Users* branch of the element hierarchy. This enables the account to create, delete, and update user accounts. The account does not need to be a member of the admins group.

Continue with [“Verifying Configuration Settings” on page 14](#).

Verifying Configuration Settings

Because the Dashboard must communicate with the Operations Center server, we recommend verifying Operations Center server configuration settings before you start to install. For more information about the Configuration Manager and communication ports, see the [Novell Operations Center 5.0 Server Configuration Guide](#).


The Operations Center server to which the Dashboard establishes a connection is considered the default Operations Center server and the Dashboard obtains all its Operations Center content from this server. However, the Dashboard does allow additional connections to other Operations Center servers so that users can view and use content from multiple servers while viewing Web pages in the Dashboard. For more information, see [Section 3.8, “Creating Operations Center Server Profiles,” on page 41](#).

To verify and update Operations Center Configuration Settings:

- 1 Open the Operations Center Configuration Manager.
- 2 Switch to the *Tasks* tab (*Networking* section) to verify the following settings for the Operations Center server that are important for maintaining open communication between Operations Center and the Dashboard:
 - ♦ Host Name
 - ♦ Client/Server Communication Mode

- ◆ Web Server Ports
- ◆ Image Server Comm Port
- ◆ Remote Services Port (RMI)
- ◆ Dashboard Communications Security (for RMI communications security)

The *Tasks* tab on the Operations Center Configuration Manager allows you to view all Networking settings in a single list, as shown in the following illustration:



3 Because the RMI communications security can be set in Operations Center only, and is automatically detected by the Dashboard, do one of the following:

- ◆ If *Remote Services Security (RMI)* is set to *Secured communication using SSL*, or *Secured communication using SSL and Client Certificates*, then:
 - ◆ Set Operations Center server’s RMI communications to secure.
 - ◆ Configure the Operations Center Web server for secure communications.
- ◆ If *Remote Services Security (RMI)* is set to *Unsecured communication*, then:
 - ◆ Set Operations Center server’s RMI communications to unsecure.
 - ◆ Configure the Operations Center Web server for unsecure communications.

Use the *Secured communication using SSL and Client Certificates* option when running the Dashboard with a reverse-proxy scenario where the connecting client is always the Apache Web server. For more information about configuring the Dashboard with a reverse-proxy scenario or configuring Apache to deliver client certificates, contact Novell Support as a Technical Information Document (TID) has been written on this subject.

For more information about securing communications between servers and setting up certificates, see “[Communications Security](#)” in *Novell Operations Center 5.0 Security Management Guide*.

- 4 (Unix Only) Configure the *X11 Display Name* for the display of images. Specify the display name where the server listens for connection with the virtual framebuffer.
For example, for a display name of 1 and screen name of 0, set to :1 or :1.0.
For more information, see [Configuring Display for Images on UNIX](#) in the *Novell Operations Center 5.0 Server Installation Guide*.
- 5 Continue with [Section 2.2.2, “Installing the Dashboard,”](#) on page 16.

2.2.2 Installing the Dashboard

Typically, the Dashboard is installed by using the Installation Wizard. It might also be installed using a console installation or an unattended (or silent) installation as detailed in [Appendix B, “Running a Console or Unattended Installation,”](#) on page 243. For more information about any of these installation methods, see the *Novell Operations Center 5.0 Server Installation Guide*.

To install the Dashboard:

- 1 To obtain access to the installation files, do one of the following:
 - ♦ Insert the Operations Center Dashboard CD into the CD drive of the server where the software is to be installed.
 - ♦ Locate the Dashboard files that were downloaded on the server where the software is to be installed.
- 2 Do one of the following:
 - ♦ **Windows:** If the Installation Wizard does not launch automatically, run `install.bat` from a command prompt.
If User Access Control (UAC) is enabled, you must run the installation as the Administrator.
 - ♦ **UNIX:** Set the variable path to where the Java executable is, mount the CD, then run `install.sh` from the root.
- 3 On the *Introduction* page, do the following:
 - 3a (Recommended) Stop all programs before continuing especially those any programs that might interfere with the dashboard installation.
 - 3b Click *Next* to continue.
- 4 On the *License Agreement* page, do the following as applicable:
 - 4a Review the contents of the license agreement.
 - 4b Select the *I accept the terms of the License Agreement* radio button if you agree with the terms.
 - 4c Click *Next* to continue.
- 5 On the *Choose JVM* page, do the following:
 - 5a To select the Java VM, do one of the following:
 - ♦ (Windows 32-bit) Select the *Install a Java VM specifically for this application* radio button to install the Java VM.
 - ♦ (Windows 32-bit) Select the *Choose a Java VM already installed on this application* radio button and select the desired Java VM from the list.
 - ♦ Select *Search For Others* to list additional installed VMs.
 - ♦ Select *Choose Another* to navigate to the location of the Java VM you want to use.

IMPORTANT: If installing on a Windows 32-bit platform, select a 32-bit JVM. If installing on a Windows 64-bit platform, select a 64-bit JVM. Dashboard cannot run if the wrong JVM is selected.

If installing on Solaris x64, be sure to modify the Apache `Setclasspath.sh` file to reference the Java path in your AMD64 installation in order for the Dashboard to start successfully. For example,

```
_RUNJAVA="/usr/jdk1.6.0_21/jre/bin/amd64/java"
```

- 5b Click *Next* to continue.
- 6 On the *Choose Install Folder* page, do the following:
 - 6a Specify the install path on the server.

We recommend that you do not install the Dashboard in the same directory as the Operations Center server.

If necessary, click *Choose* to browse for a different location.
 - 6b Click *Next* to continue.
- 7 On the *Dashboard Server Configuration* page, do the following:
 - 7a Specify the Dashboard communications mode by selecting one of the following *Dashboard Communications Mode* radio buttons:
 - ♦ **http only** to only use unsecure communications.
 - ♦ **https only** to only use secure communications.
 - ♦ **both** to allow both unsecure and secure communications.
 - 7b Specify the http port the Dashboard is to use for http communications in the *Dashboard Web Server Port (HTTP)* field.
 - 7c Specify the http port the Dashboard is to use for https communications in the *Dashboard Web Server Port (HTTPS)* field.
 - 7d Click *Next*.
 - 7e Specify the communications mode that the Dashboard uses to communicate with the Operations Center server by selecting one of the following *Operations Center Communications Mode* radio buttons:
 - ♦ **http** to use unsecure communication with Operations Center.
 - ♦ **https** to use secure communications with Operations Center.
 - 7f Click *Next*.
 - 7g Select the *Run Configuration Manager* after install option to launch the Configuration Manager during installation.
 - 7h Click *Next*.

- 8 On the *Pre-Installation Summary* page, do the following:
 - 8a Review the installation details.
 - 8b To change any settings, click *Previous* as necessary.
 - 8c To install, click *Install*.
- 9 While the Dashboard installs, note the following that occurs:
 - ♦ The status display updates as the Dashboard installs.
 - ♦ The Configuration Manager launches to configure settings for the installation if selected in [Step 7g](#).
Details on these settings are documented in [Section 2.2.5, “Configuring the Dashboard and Operations Center,”](#) on page 20.
- 10 On the *Install Complete* page, click *Done* to close the Installation Wizard.
- 11 Continue with [Section 2.2.3, “Configuring the Dashboard Database,”](#) on page 18.

2.2.3 Configuring the Dashboard Database

While the Dashboard installs by default with an embedded Hypersonic SQL database, the Dashboard must be configured to use an Oracle or SQL Server database.

The following instructions provide instructions for configuring the Dashboard database:

- ♦ [“Configuring Windows Servers for Database Single Sign On \(SSO\)”](#) on page 18
- ♦ [“Configuring the Dashboard Database”](#) on page 18

Configuring Windows Servers for Database Single Sign On (SSO)

The Dashboard can be configured to use Server Domain Authentication for single sign on with Microsoft SQL databases. Windows servers require additional configuration for SSO functionality.

To configure Windows servers for Single Sign On with Dashboard MSSQL databases:

- 1 Stop the Dashboard.
- 2 Copy one of the following files into the directory containing the `java.exe` used by the Dashboard server:
 - ♦ **On a 32-bit JVM:** `OperationsCenter_Dashboard_install_path/mssql/win32/ntlmauth.dll`
 - ♦ **On a 64-bit JVM:** `OperationsCenter_Dashboard_install_path/mssql/win64/ntlmauth.dll`
- 3 Specify the domain, username and password when configuring the Dashboard `portal-ext.custom.properties` file.
For information on configuring the Dashboard database and properties file for SSO, continue to [Configuring the Dashboard Database](#).
- 4 Restart the Dashboard.

Configuring the Dashboard Database

The following prepackaged JDBC drivers are installed with the Dashboard installation in the `OperationsCenter_Dashboard_install_path/server/lib/ext/` directory:

- ♦ **Oracle:** `ojdbc6.jar`

- ♦ **SQL Server:** jtids-1.2.5.jar

To configure the Dashboard to use an Oracle or SQL Server database:

- 1 Do one of the following to create the schema for the new database:

- ♦ **Oracle:** Use the Oracle SQL*Plus Client to run the following scripts against your Oracle database.

```
/OperationsCenter_Dashboard_install_path/data/scripts/create-oracle.sql
```

```
/OperationsCenter_Dashboard_install_path/data/scripts/init-oracle.sql
```

Note that the schema creation script contains some PL/SQL code which other jdbc based clients cannot execute.

- ♦ **SQL Server:** Run the following scripts against your SQL Server database.

```
/OperationsCenter_Dashboard_install_path/data/scripts/create-sql-server.sql
```

```
/OperationsCenter_Dashboard_install_path/data/scripts/init-sql-server.sql
```

- 2 Open the */OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.properties* file, and locate and copy the properties for your database type in the *Database Support* section.
- 3 Paste these database properties into the */OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties* file, then uncomment the lines.

For example,

```
jdbc.default.driverClassName=net.sourceforge.jtids.jdbc.Driver
jdbc.default.url=jdbc:jtids:sqlserver://localhost:1433/myDB;instance=inst
jdbc.default.username=sa
jdbc.default.password=abc.123
```

Where,

Where, *localhost* is IP address or server name of SQL server, *1433* is the port that SQL database uses, *myDB* is the database name, and *inst* is the name of the instance of SQL.

Optionally, you can encrypt the password. For more information about encrypting the database password, see [Section 12.1, “Encrypting the Dashboard Database Password,”](#) on page 227.

For more information about the *portal-ext.properties* and *portal-ext.custom.properties* files, refer to [Section 3.9, “Understanding Portal Properties Files,”](#) on page 43.

- 4 (Optional) Specify the following if configuring the domain authentication with Microsoft SQL databases:
 - ♦ Append the database URL property with *;domain=domain_value*
 - ♦ On Windows servers, leave the username and password properties blank to attempt to connect using the current Windows user account.

- ♦ If running Operations Center Dashboard as a Windows service, the service must use the same domain user account as the database.
 - ♦ On Linux/UNIX servers, define the `jdbc.default.username` and `jdbc.default.password` properties with the username and password of the desired Windows account.
- 5 If the database installs without any errors, continue to [Section 2.2.4, “Verifying the Dashboard Default Time Zone for User Accounts,”](#) on page 20 and [Section 2.2.5, “Configuring the Dashboard and Operations Center,”](#) on page 20.

2.2.4 Verifying the Dashboard Default Time Zone for User Accounts

The default time zone for the portal is set to UTC for Dashboard users. It is important that its value be updated to an appropriate time zone if this is not the correct time zone for your users prior to the initial automatic synchronization with the Operations Center server.

Note that data in the Layout portlet and the Layout tab in the Information portlet displays based on the time zone of the Operations Center server, and not the time zone configured for the Dashboard.

To change the default time zone:

- 1 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.properties` file, and locate the list of time zones.
- 2 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file. Add the `user.timezone` property, and define it using a time zone from the list in Step 1.

For more information about the `portal-ext.properties` and `portal-ext.custom.properties` files, refer to [Section 3.9, “Understanding Portal Properties Files,”](#) on page 43

WARNING: When Dashboard users are created via the automatic synchronization with Operations Center server, their time zone is assigned based on the `user.timezone` property in the `system-ext.properties` file. If this property isn't updated for the desired default time zone in the `system-ext.custom.properties` file prior to synchronization, each user must update their time zone individually via their Dashboard control panel. For more information about user synchronization, see [Section 4.1, “Operations Center and Dashboard Interaction,”](#) on page 49.

2.2.5 Configuring the Dashboard and Operations Center


The Operations Center Dashboard's Configuration Manager and the Operations Center's Configuration Manager are two different configuration managers. You need to use both managers to configure the Dashboard.

Configurations must be made for general Dashboard operation and communications with the Operations Center server. In order for the Dashboard to communicate with the Operations Center server, some configuration settings must match the settings of the Operations Center server's configuration. These settings are found in the Operations Center Dashboard Configuration Manager and must match the same settings in the Operations Center Configuration Manager.

WARNING: Changing the settings in either Configuration Manager replaces existing configuration files and any manual changes are lost.

To configure the Dashboard:

- 1 To access the Operations Center Dashboard Configuration Manager, do one of the following:
 - ♦ **Windows:** You have two options:
 - ♦ Click *Start > All Programs > Novell Operations Center > Novell Operations Center Dashboard > Configure Novell Operations Center Dashboard*.
 - ♦ At the DOS prompt, run *customizer* from the `\OperationsCenter_Dashboard_install_path\bin` directory.
 - ♦ **UNIX:** At a command prompt, run *Customizer* from the `/OperationsCenter_Dashboard_install_path/bin` directory.
- 2 Click *Novell Operations Server* in the *Components* tab.



- 3 Configure the following settings:

Novell Operations Center Server Host Name: The host name for the Operations Center server.

Novell Operations Center Server Communication Mode: The method of communication for the Operations Center server. Select between *Unsecured communication* or *Secured communication using SSL*.

Novell Operations Center Server Web Server Port: The Web server port for the Operations Center server. If using unsecured communication, specify the Web Server Port number for HTTP from the Operations Center server. Or, if using Secured communication using SSL, specify the Web Server Port number for HTTPS from the Operations Center server.

Novell Operations Center Server SQL Views port: The port used by SQL Views for access to the Operations Center server. For more information, see the [Novell Operations Center 5.0 SQL Views Guide](#).

Novell Operations Center Server RMI Server Port: The RMI server port for the Operations Center server. The default RMI port is 1099. Value must match the RMI server port specified in the Operations Center configuration manager. If the port is changed in the Dashboard Configuration Manager, then the port value must be updated in the Operations Center Configuration Manager, and vice versa.

Novell Operations Center Server Image Server Comm Port: The Image Server's Communication Port for the Operations Center server. If using a portlet that accesses the Operations Center server's Image server, value must match the Image server communications

port that is specified in the Operations Center configuration manager. The Operations Center server's Image server can be accessed from the Dashboard IP Address. For more information on this, see the *Novell Operations Center 5.0 Server Configuration Guide*.


Novell Operations Center Server System User Id: The user name of the Operations Center admin account that is used for handling the persistent connection for user synchronization between the Dashboard and Operations Center.

For more information about user and group synchronization and the default admin account, see [Section 4.1, "Operations Center and Dashboard Interaction,"](#) on page 49.

For more information about changing the default admin account, see [Section 3.5, "Changing the Dashboard Account for Persistent Connection,"](#) on page 38

Novell Operations Center Server System User Password: The corresponding password of the Operations Center admin account specified in the *Operations Center server's System User Id* field.

- 4 To access the Dashboard configuration options, in the *Dashboard* section, click the *Components* tab.



- 5 Configure the following Dashboard settings:

Dashboard Communication Mode: The method of communication for the Dashboard. Select *Unsecured communication*, *Secured communication using SSL*, or *Support both unsecured and secured communication*.

Dashboard Web Server Port (HTTP): The port to access the Dashboard if using an unsecured communication protocol.

IMPORTANT: For all ports, verify that the port does not conflict with a port already in use.

Dashboard Web Server Port (HTTPS): The port to access the Dashboard if using a secure communication protocol.

Dashboard Web Server Shutdown Port: The TCP/IP port number to which the Dashboard listens for a shutdown command.

Dashboard Data Caching: The RMI connection between the Dashboard and Operations Center uses a memory sensitive cache to retain data for a predetermined amount of time. This cache resides on the Dashboard application and reduces the amount of calls to the Operations Center server. By default, the caching mechanism is enabled. Note that because this is a memory sensitive cache, it is purged if memory demands are exceeded by the Dashboard application.

Cache timeout value in seconds: The amount of time the data caching mechanism holds onto data. Defaults to 45 seconds.

Dashboard Trace Level: Controls how much information is passed to the server trace logs. Defaults to INFO, which is recommended. The trace levels are:

- ◆ **ERROR:** Logs error messages only.
- ◆ **WARN:** Logs error and warning messages.
- ◆ **INFO:** Logs informational, error, and warning messages.
- ◆ **DEBUG:** Logs all information and as the most detailed setting should be used only to track down problems.

Dashboard Trace Destination: Specifies the location of trace log output file. By default, all logging is saved to `/OperationsCenter_Dashboard_install_path/server/logs/dashboard.trc`.

On application startup, the current version of the Dashboard and a listing of all environment variables are written to the trace file. For more information, see [Appendix D, “Troubleshooting Trace Logs,”](#) on page 261.

Dashboard Server Push: Push technology allows data from the Operations Center server to be received as new data appears. If disabled, data is only sent when the user refreshes or loads a page. By default, this option is enabled and applies to all Operations Center portlets that support push technology. However, push settings can be overridden for each individual portlet taking precedence over this setting in the Operations Center Dashboard Configuration Manager. For more information, see [Section 7.8.6, “Automatic Data Updates with Push Technology,”](#) on page 131.

Dashboard Server Alarm Options: Enables alarm operations similar to those on the Operations Center console. By default, this option is enabled and applies to alarms components for all Operations Center portlets. However, alarm options can also be overridden for each individual portlet taking precedence over this setting in the Operations Center Dashboard Configuration Manager. For more information, see [Section 8.1.3, “Applying and Creating Alarm Filters,”](#) on page 138.

6 Specify Java configuration options:

Java Development Kit Directory: The location of the JDK used by the Dashboard. Click *Browse* to select a new location.

Java Initial Memory Pool: (Windows Only) Initial and minimum Java heap size in megabytes.

Java Max Memory Pool: (Windows Only) Maximum Java heap size in megabytes.

Java Runtime Options: List of command line options in the form of `-D` or `-X` that are passed to the JDK. For Windows, separate entries with a semicolon. For UNIX, separate entries with a space.

For more information about JRE requirements, see [“Requirements for the Dashboard and CMS”](#) in the *Novell Operations Center 5.0 Getting Started Guide*.

7 To restart the Dashboard, continue with [Section 2.2.6, “Starting the Dashboard for the First Time and Verifying the Installation,”](#) on page 24.

After making changes in the Configuration Manager, it is necessary to restart the Dashboard for any changes to take affect.

2.2.6 Starting the Dashboard for the First Time and Verifying the Installation

The last step to installing the Dashboard is to start the Dashboard and log in to verify a successful connection.

IMPORTANT: At the initial start up of the Dashboard server, a user synchronization process imports all users and groups from the Operations Center server into the Dashboard. For more information about the user synchronization process, see [Section 4.1, “Operations Center and Dashboard Interaction,”](#) on page 49.

When user accounts are created, a default time zone is assigned based on a property setting in the `portal-ext.properties` file. Be sure to validate, and override this setting if necessary in the `portal-ext.custom.properties` file, before starting the Dashboard server for the first time. For more information about time zone settings, see [Section 2.2.4, “Verifying the Dashboard Default Time Zone for User Accounts,”](#) on page 20.

For more information about the `portal-ext.properties` and `portal-ext.custom.properties` files, refer to [Section 3.9, “Understanding Portal Properties Files,”](#) on page 43

For more information on starting the Dashboard, see [Section 2.3.1, “Starting the Dashboard,”](#) on page 27.

To log in to the Dashboard:


- 1 From your Web browser, access the URL of the Dashboard server:

`http://server:dashboard_port`

For example, the Dashboard is installed on your current machine and the HTTP port (Operations Center Dashboard Configuration Manager) set to 8080, then point your browser to:

`http://localhost:8080`

When successful, the guest home page for the Dashboard displays:



- 2 To verify RMI communication settings between the Dashboard and the Operations Center server, log in to the Dashboard.

Use the Operations Center default admin account credentials.

If successful, the Dashboard establishes a persistent administration connection to the Operations Center server. This connection is then used to verify the credentials provided by users in the login portlet. If the credentials are correct, the [Access Control Synchronizer](#) starts and users from Operations Center are imported.

After logged into the Dashboard, you can add and update content from your personal home page.

Next, configure the URL settings. For more information, see [Section 3.2, “Updating Dashboard Administrative Configurations,”](#) on page 31.

- 3 If the connection or authentication fails, do the following as necessary:

- ◆ Confirm your administrator default account credentials.
- ◆ Verify that you are using the correct HTTP or HTTPS port.
- ◆ For all port configurations, verify that the port does not conflict with a port already in use.
- ◆ Confirm that the RMI connections specified in the Operations Center Dashboard Configuration Manager and the Operations Center Configuration Manager match.
If settings are changed in the Configuration Manager, restart the associated server.
- ◆ Review the `dashboard.trc` file for error messages.
- ◆ Add the Dashboard server as a trusted site.

For IE 7+ in Windows Vista or Windows Server 2008 and running in Protected Mode, the Dashboard server must be added as a trusted site before the Dashboard can function normally.

To add the Dashboard to the list of trusted sites, click *Tools* and select *Internet Options*. Select the *Security* tab and click *Trusted Sites*. Click *Sites* and specify the Dashboard host as a trusted site.

2.2.7 Update Dashboard Configuration Settings

For the Dashboard to function properly, the Virtual Host and Mail Domain settings need to be updated. Else, the Dashboard users might encounter redirect issues when navigating to the Dashboard or when the Dashboard is unable to send e-mail notifications.

For more information about other the Dashboard portal configuration settings, see [Section 3.2, “Updating Dashboard Administrative Configurations,”](#) on page 31.

To update the Virtual Host and Mail Domain for the Dashboard:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Settings*.

The screenshot displays the 'Settings' page for the 'Portal' in the Novell Operations Center. The page is divided into several sections:

- Main Configuration:** Fields for Name (Novell), Virtual Host (localhost), Home URL, and Mail Domain (novell.com).
- Additional Information:** Fields for Legal Name (Novell, Inc.), SIC Code, Legal ID, Ticker Symbol, Legal Type, Industry, and Type.

A sidebar on the left lists navigation options under 'Portal', with 'Settings' highlighted. A right sidebar shows a configuration menu with 'General (Modified)' selected, and buttons for 'Save' and 'Cancel' at the bottom.

- 3 Specify the fully qualified host name for the server where the Dashboard is running in the *Virtual Host* field.
- 4 Specify the domain name for the mail host for this instance in the *Mail Domain* field.
- 5 Click *Save* to save all updated settings.
- 6 Click *Back* to exit the Control Panel.

2.3 Starting and Stopping the Dashboard

The user account starting and stopping the Dashboard must have the proper permissions to create, update, and delete contents in the Dashboard directory on the Dashboard server. The user must also have the Environment variable `%JAVA_HOME%` in Windows or `$JAVA_HOME` in Linux/Unix set to point to the JDK directory.

- ♦ [Section 2.3.1, "Starting the Dashboard," on page 27](#)
- ♦ [Section 2.3.2, "Stopping the Dashboard," on page 27](#)

2.3.1 Starting the Dashboard

For important notes about starting the Dashboard for the first time, see [Section 2.2.6, “Starting the Dashboard for the First Time and Verifying the Installation,”](#) on page 24.

To start the Dashboard:

- 1 Do one of the following:
 - ♦ **Windows:** Do one:
 - ♦ Run the `/OperationsCenter_Dashboard_install_path/bin/startup.bat` script file.
 - ♦ Start the *Operations Center Dashboard Windows* service.
In the *Windows Start Menu*, select *Novell Operations Center > Novell Operations Center Dashboard > Start Novell Operations Center Dashboard*.
 - ♦ **UNIX:** Issue the `startup.sh` command.

2.3.2 Stopping the Dashboard

To stop the Dashboard, do one of the following:

- ♦ **Windows:** Do one:
 - ♦ Run the `/OperationsCenter_Dashboard_install_path/bin/shutdown.bat` script file.
 - ♦ Stop the *Operations Center Dashboard Windows* service.
In the *Windows Start Menu*, select *Novell Operations Center > Novell Operations Center Dashboard > Stop Novell Operations Center Dashboard*.
- ♦ **UNIX:** Issue the `shutdown.sh` command.
If the Dashboard does not terminate normally after invoking the `shutdown.sh` command, issue the `shutdown.sh` command again using the `-force` option to perform a hard shutdown of the Dashboard.

2.4 Enterprise-Wide Trusted Sites

Because of Protected Mode functionality, the Dashboard server must be added as a trusted site before the Dashboard can be run successfully using IE 7+ in Windows Vista or Windows Server 2008 in Protected Mode.

Unfortunately, if Protected Mode is enabled for the entire enterprise, having each user modify the Trusted Sites list is difficult to maintain. Therefore, we recommend adding the Dashboard server to the list of Trusted Sites by the enterprise administrator through domain policy and pushed out to all clients.

3 Dashboard Configuration


Because the Operations Center Dashboard is built on top of Liferay 5.2, see <http://www.liferay.com/documentation/liferay-portal/5.2/> for documentation on server configuration, portal administration, and Liferay content management functionality.

In addition, this section covers various administrator configurations required for the Dashboard, or for the proper functioning of various portlets.

- ♦ [Section 3.1, “About the Dashboard Control Panel,” on page 30](#)
- ♦ [Section 3.2, “Updating Dashboard Administrative Configurations,” on page 31](#)
- ♦ [Section 3.3, “Configuring Auto-Login for Single Sign On \(SSO\),” on page 33](#)
- ♦ [Section 3.4, “Setting Session Timeout,” on page 36](#)
- ♦ [Section 3.5, “Changing the Dashboard Account for Persistent Connection,” on page 38](#)
- ♦ [Section 3.6, “Configuring the Mail Server,” on page 39](#)
- ♦ [Section 3.7, “Configuring the Proxy Server,” on page 40](#)
- ♦ [Section 3.8, “Creating Operations Center Server Profiles,” on page 41](#)
- ♦ [Section 3.9, “Understanding Portal Properties Files,” on page 43](#)
- ♦ [Section 3.10, “Deploying Portlets to the Dashboard,” on page 44](#)
- ♦ [Section 3.11, “Default Portlet Settings,” on page 45](#)
- ♦ [Section 3.12, “Granting or Denying Access to Portlets,” on page 47](#)

3.1 About the Dashboard Control Panel

All of the administrative functions that you will need to maintain the portal or its content can be found in the control panel. Additionally, developers can write portlets which can also be added to the control panel. Access the Control Panel through the options from the Welcome button.



Administrative functions are listed in a logical order under main headings.

- ♦ **User:** The first section is always the logged in user's personal space. Here, you can change your account information and manage your own personal pages.
- ♦ **Content:** The Content section contains links to all Liferay content management functions. You can maintain web content, documents, images, bookmarks, a calendar, administer a message board, configure a wiki, and more.
- ♦ **Portal:** The Portal section allows portal administrators to set up and maintain the portal. This is where you can add and edit users, organizations, communities, roles, and configure various settings for the portal. Also change the portal site name and logo.
- ♦ **Server:** The Server section contains administrative functions for configuring portal instances, plug-ins, and more.

The *Portal* section of the Control Panel is used for most administrative tasks, such as for the creation and maintenance of:

- ♦ Users
- ♦ Organizations
- ♦ Communities
- ♦ User Groups
- ♦ Roles

Additionally, it allows you to configure many server settings, including:

- ◆ Password Policies

Note that Liferay Password Policies functionality for password expiration and password lockout are unsupported by the Dashboard.

- ◆ Authentication options, including Single Sign-On and LDAP integration
- ◆ Default User Associations
- ◆ Reserved Screen Names
- ◆ Mail Host Names
- ◆ E-mail Notifications

You will use the *Portal* section of the Control Panel to create your portal structure, implement security, and administer your users. Note that only users with the Administrator role—a portal scoped role—have permission to view this section of the Control Panel.

3.2 Updating Dashboard Administrative Configurations

Main Dashboard administrative configurations are handled through the *Control Panel* under *Settings*, and include:

- ◆ **General:** Update the portal site name to your company name. Also if necessary, change the virtual host and mail domain.
- ◆ **Authentication:** Settings for general authentication, LDAP, CAS, NTLM, OpenID, Open SSO, and SiteMinder. Because users are loaded from the Operations Center server, do NOT change the default authentication method.
- ◆ **Default User Associations:** Default assignments to communities, user roles and user groups.
- ◆ **Reserved Credentials:** Reserved screen names and e-mail addresses.
- ◆ **Mail Host Names:** Additional domains used to send e-mail messages related to certain portlets. For example, the login portlet allows users to request an account.
- ◆ **Email Notifications:** System settings for e-mail notifications including password change notification.
- ◆ **Display Settings:** Verify the language and time zone settings are correct for your implementation. By default, these are set to English (United States) and GMT respectively. Also, change the site logo to your company logo.

The following sections describe how to configure the Dashboard using the Control Panel:

- ◆ [Section 3.2.1, “Updating Dashboard Administrative Configurations,” on page 32](#)
- ◆ [Section 3.2.2, “Updating the Dashboard Site Name & Logo,” on page 33](#)

3.2.1 Updating Dashboard Administrative Configurations

To update main dashboard configurations:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Settings*.

The screenshot shows the 'Portal Settings' interface. On the left is a navigation menu with 'Settings' selected. The main content area is titled 'Portal' and contains a 'Settings' section. Under 'Main Configuration', there are input fields for Name (Novell), Virtual Host (localhost), Home URL, Mail Domain (novell.com), Legal Name (Novell, Inc.), SIC Code, Legal ID, Ticker Symbol, Legal Type, Industry, and Type. A right-hand sidebar contains a 'Configuration' menu with links for Authentication, Default User Associations, Reserved Credentials, Mail Host Names, Email Notifications, Identification (Addresses, Phone Numbers, Additional Email Addresses, Websites), and Miscellaneous (Display Settings). Save and Cancel buttons are at the bottom of the sidebar.

- 3 Update settings as required. Use the following links under Configuration, Identification and Miscellaneous to access the settings:

General: Main configuration settings including portal name, virtual host, and mail domain. Also includes additional information about your business or organization.

IMPORTANT: Setting the Portal URL or Home URL can cause warnings to appear in the trace logs. For more information, see [Section D.2.1, “No Such LayoutSet Exception,” on page 264](#).

Authentication: Settings for general authentication, LDAP, CAS, NTLM, OpenID, Open SSO, and SiteMinder. Because users are loaded from the Operations Center server, do NOT change the default authentication method.

Default User Associations: Default assignments to communities, user roles and user groups.

Reserved Credentials: Reserved screen names and e-mail addresses.

Mail Host Names: Additional domains used to send e-mail messages related to certain portlets. For example, the login portlet allows users to request an account.

Email Notifications: System settings for e-mail notifications including password change notification.

Display Settings: Verify the language and time zone settings are correct for your implementation. By default, these are set to English (United States) and GMT respectively. Also, update the main site logo.

For more information about updating the dashboard’s logo, see [Section 3.2.2, “Updating the Dashboard Site Name & Logo,” on page 33](#).

- 4 Click *Save* to save all updated settings.
- 5 Click *Back* to exit the Control Panel.

3.2.2 Updating the Dashboard Site Name & Logo

The Dashboard site name, that displays in browser window and tab titles, can be changed in *Settings > General* in the *Control Panel*. Changing the portal name also requires you to define the Virtual Host and Mail Domain settings. For instructions, refer to [Section 3.1, “About the Dashboard Control Panel,”](#) on page 30.

The logo used for the main site of the Dashboard can be changed in *Display Settings* from the *Control Panel*. For instructions, refer to [Section 3.2, “Updating Dashboard Administrative Configurations,”](#) on page 31.

To restore the original Novell Operations Center logo to the Dashboard, go to *Control Panel > Display Settings > Logo* and upload the logo file available in the `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/image_gallery/` directory. Access to this image directory is also available at `http://server:port/ManagedObjectsPortlets/image_gallery`.

Logos can also be customized for different communities. For information on assigning logos for communities, refer to [Section 5.2.3, “Updating Community Settings,”](#) on page 71.

3.3 Configuring Auto-Login for Single Sign On (SSO)

The Dashboard supports Single Sign On (SSO) capability through its auto-login function. SSO allows users to gain access to multiple systems (that support SSO) with a single login. For more information on user access to the Dashboard, see [Chapter 4, “User Accounts,”](#) on page 49.


In situations where it is necessary to disable direct access to the Dashboard server or operations client, authentication can be verified against the SSO implementation before users are allowed to access the Dashboard or the operations client. For more information, see [Section 3.3.2, “Disabling Direct Client Login,”](#) on page 35.

- ♦ [Section 3.3.1, “Implementing Auto-Login with Your Web Server,”](#) on page 34
- ♦ [Section 3.3.2, “Disabling Direct Client Login,”](#) on page 35

3.3.1 Implementing Auto-Login with Your Web Server

The Dashboard's auto-login can be used with any mechanism that can include in HTTP requests an HTTP header containing the user name to be auto-logged in. It is most commonly used with the Apache Web server set up as a reverse proxy.

When using a Web server reverse proxy, the security plug-in can authenticate incoming HTTP requests based on a certificate for a user name. The Web server can then be configured to pass an HTTP header to the Dashboard containing the user name of the authenticated user. If the Dashboard server has been configured to allow auto-login, the user is automatically logged in by bypassing the need for the user to provide user name and password.



In the above illustration, a Web Server is configured as a reverse proxy. The appropriate auto-login header (such as `remote-user`) is embedded into HTTP requests and the Dashboard server is configured to allow auto-login. Valid Operations Center users (a user that has already been created and exists in Operations Center) are authenticated if the specified HTTP header exists and the Dashboard is configured for auto-login, and the users are automatically logged into the Operations Center server.

To configure auto-login using the Web server reverse proxy:

- 1** Configure the Dashboard for auto-login by updating the Dashboard configuration file.

- 1a** Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file in a text editor.

For more information about the `portal-ext.custom.properties` file, refer to [Section 3.9, "Understanding Portal Properties Files,"](#) on page 43.

- 1b** Add the following line, but do not change the value of the property:

```
auto.login.hooks=com.mosol.liferay.authenticator.MOAuth
```

- 1c** Add the following line to specify the Web Server Request URIs that allow auto-login:

```
mo.autologin.request.uris=.*
```

The value defaults to `.*` for all pages as shown in the code sample above.

This property can be configured to a specific page such as `/c/portal/login` and if a user has not yet established a portal login and accesses the `http://dashboard_host:dashboard_port/c/portal/login` page, the auto-login is attempted. However, if any other page is accessed without a previous a portal login established, then auto-login isn't attempted because the page is not a match for the property's regular expression.

To specify more than one specific page, use a pipe character (vertical line) to separate the values. For example, `/c/portal/login|/c/portal/layout` sets the auto-login to the login page and general layout page. If the general layout page is specified (`/c/portal/layout,.*`, and so on), then logging out of the portal triggers an immediate attempt to auto-login. If successful, the user is automatically logged in and does not see a login portlet.

- 1d** Add the following line to request the header containing the principal to auto-login:

```
mo.autologin.header=remote-user
```

The value of `remote-user` is an http header only. In this configuration file you don't usually change the line itself nor declare specific users.

- 1e** After saving the file, restart the Dashboard Web server for the changes to take effect.

For more information, see [Section 2.3.1, "Starting the Dashboard," on page 27](#).

- 2** Configure the Web Server to set up the reverse proxy to forward requests from `/` to the Dashboard server URL.

For more information on configuring the Apache Server reverse proxy, contact Novell Support as a Technical Information Document (TID) has been written on this subject.

- 3** Configure a custom HTTP header by adding a `remote-user`, or the header specified above in [Step 1d on page 35](#), to contain the value of an existing Operations Center user.
- 4** We recommend using client certificates between the Web server and the Dashboard.

For more information about setting up a keystore and truststore, see ["Communications Security"](#) in the *Novell Operations Center 5.0 Security Management Guide*.

For more information about configuring Apache for client certificates, contact Novell Support as a Technical Information Document (TID) has been written on this subject.

3.3.2 Disabling Direct Client Login

When direct access should be disabled to the Dashboard server or operations client, user authentication against the auto-login implementation can be forced before access to the Dashboard or the operations client is granted. This approach provides a single authentication pipeline for all users against the target system.

To disable direct client login:

- 1** Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file in a text editor.

For more information about the `portal-ext.properties` and `portal-ext.custom.properties` files, refer to [Section 3.9, "Understanding Portal Properties Files," on page 43](#).

- 2** Add or update the following parameters as shown:

```
Client.DisableLogins=true  
Client.DisableLogins.AllowedAccounts=admin,guest
```

Setting the `Client.DisableLogins` parameter to `True` disables logins to the operations client.

The `Client.DisableLogins.AllowedAccounts` parameter defines a comma-separated list of accounts that are allowed to log in when the SSO provider is not available and administrators need access the system.

- 3 Save the file, then restart the Dashboard Web server.

3.4 Setting Session Timeout

Both the Dashboard and the Operations Center server to which the Dashboard has established a connection times out based on inactivity.

- ♦ [Section 3.4.1, “Setting Operations Center Server Timeout,” on page 36](#)
- ♦ [Section 3.4.2, “Setting Dashboard Timeout,” on page 36](#)
- ♦ [Section 3.4.3, “Disabling Dashboard Session Timeout,” on page 37](#)
- ♦ [Section 3.4.4, “Configuring the “Remember Me” Feature and Setting Browser Cookie Lifespan,” on page 37](#)

3.4.1 Setting Operations Center Server Timeout

The Dashboard portlets attempt to reconnect to a server that has timed out or gone down if the Dashboard application has not timed the user out of the Dashboard session.

To update the timeout value in the Operations Center server’s `Formula.custom.properties` file, add or update the `mo.remoteserver.context.keepAliveTime` property value (in minutes).

By default, a connection timeout occurs after 30 minutes of inactivity with the Operations Center server.

For information about creating or using the `Formula.custom.properties` file, see [“Making Custom Changes”](#) in the *Novell Operations Center 5.0 Server Configuration Guide*.

3.4.2 Setting Dashboard Timeout

By default, if a user does not perform any activity in the Dashboard for 30 minutes, the user is warned that the session will expire. The user can remain logged into the Dashboard for an additional 30 minutes by responding to the notification.

To change the Dashboard session timeout:

- 1 Update the following line in the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/web.xml` file for the number of minutes before timeout:

```
<session-config>
  <session-timeout>30</session-timeout>
</session-config>
```

3.4.3 Disabling Dashboard Session Timeout

By default, session timeout is enabled for the Dashboard. To extend sessions and keep them open as long as the user's browser is open and a portal page is loaded, update the `portal-ext.custom.properties` file. When extending sessions, a smaller `session.timeout` value, such as 5 minutes, must be set.

To halt session timeout:

- 1 Stop the Dashboard server.

For more information, see [Section 2.3.2, "Stopping the Dashboard," on page 27](#).

- 2 Update the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file to add the following line:

```
session.timeout.auto.extend=true
```

For more information about the `portal-ext.custom.properties` file, refer to [Section 3.9, "Understanding Portal Properties Files," on page 43](#).

- 3 Update the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/web.xml` file to set a smaller session timeout:

```
<session-config>  
  <session-timeout>5</session-timeout>
```

```
</session-config>
```

It is recommended to set the session timeout to 5 minutes.

- 4 Start the Dashboard server.

For more information, see [Section 2.3.1, "Starting the Dashboard," on page 27](#).

3.4.4 Configuring the "Remember Me" Feature and Setting Browser Cookie Lifespan

When using the Remember Me feature for auto-login, the cookie lifespan can be configured to expire after a specific length of time, or after each browser session.

By default, the Remember Me feature is enabled in the `portal-ext.properties` file using the `company.security.auto.login` setting.

To configure Remember Me and cookie lifespan:

- 1 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file.
- 2 To configure cookie lifespan, add the following line and set to the length of time (in seconds) to expire:

```
company.security.auto.login.max.age=31536000
```

31536000 sets a lifespan of one year. Set to -1 to expire after each browser session.

- 3 To disable the Remember Me auto login feature, add the following line:

```
company.security.auto.login=false
```

3.5 Changing the Dashboard Account for Persistent Connection

By default, the Operations Center *admin* user account is used by the Dashboard to establish a persistent connection to receive user account information and data from the Operations Center server. The Dashboard can be configured to use a different account for the persistent connection. For more information about this account, see [Section 2.2.1, “Verifying Your Operations Center Server’s Default Accounts and Configuration Settings,”](#) on page 14.

IMPORTANT: While you can deactivate the default admin account in the Dashboard, do not delete it. By deactivating the account, it cannot be used to log in to the Dashboard.

To change the persistent user account for the Dashboard:

- 1 On the Operations Center server console, create the new user account to use for the Dashboard persistent connection with the following properties/permissions:

- ♦ Is a member of the admins group
- ♦ Has both console and Web access

For more information, see the [Novell Operations Center 5.0 Security Management Guide](#).

- 2 Log in to the Dashboard using the default admin account.

- 3 To assign the new admin account as the Administrator role:

3a Click *Welcome* and select *Control Panel*.

3b Under *Portal*, select *Roles*.

3c Click *Actions* next to *Administrator*, and select *Assign Members*.

3d Click the *Users* tab, then click the *Available* tab.

3e Locate the name of the new persistent user account.

If the user is not available, synchronization has probably not occurred yet. Either wait for the users to be synchronized or log in as the new user to force the account to be synchronized.

For more information, see [Section 4.1.1, “Understanding User and Group Synchronization,”](#) on page 50.

3f Select the check box next to the account name.

3g Click *Update Associations*.

- 4 To deactivate the default admin account you no longer plan to use:
 - 4a Log out and log in using the new Administrator account.
 - 4b Click *Welcome* and select *Control Panel*.
 - 4c Under *Portal*, select *Users*.
 - 4d Click *Actions* next to the old admin account, and select *Deactivate*.
- 5 Update the Operations Center system account setting in the Operations Center Dashboard Configuration Manager:
 - 5a To access the Operations Center Dashboard Configuration Manager, do one of the following:
 - ♦ **Windows:** You have two options:
 - ♦ Click *Start > All Programs > Novell Operations Center > Novell Operations Center Dashboard > Configure Novell Operations Center Dashboard*.
 - ♦ At the DOS prompt, run *customizer* from the `\OperationsCenter_Dashboard_install_path\bin` directory.
 - ♦ **UNIX:** At a command prompt, run *Customizer* from the `/OperationsCenter_Dashboard_install_path/bin` directory.

The Operations Center Dashboard Configuration Manager is displayed.

- 5b Click *Novell Operations Center* in the *Components* tab.
- 5c Update the following settings:

Novell Operations Center Server System User Id: The user name of the Operations Center admin account that is used for handling the persistent connection for user synchronization between the Dashboard and Operations Center.

For more information about user and group synchronization and the default admin account, see [Section 4.1, “Operations Center and Dashboard Interaction,” on page 49](#).

Novell Operations Center Server System User Password: The corresponding password of the Operations Center admin account specified in the *Operations Center server’s System User Id* field.
- 5d Click *Apply*.
- 6 Restart the Dashboard server.

For more information, see [Section 2.3.1, “Starting the Dashboard,” on page 27](#).

3.6 Configuring the Mail Server

The Dashboard requires a mail server to perform the following functionality:

- ♦ Users request a new user account and receive an e-mail with account information. To send this e-mail message requires an SMTP host running on an SMTP server. For more information authentication settings and customizing e-mail notifications, see [Section 4.4.1, “Self-Service User Account Creation, Authentication and Notification Settings,” on page 61](#).
- ♦ Users request a forgotten password and receive an e-mail with the password. An IMAP host and POP 3 host need to be configured to send this e-mail. For more information about disabling this feature or customizing e-mail notifications, see [Section 4.4.1, “Self-Service User Account Creation, Authentication and Notification Settings,” on page 61](#)

By default, the Dashboard uses *localhost* for the mail server location.

To configure the mail server for the Dashboard e-mails:

- 1 Stop the Dashboard server.

For more information, see [Section 2.3.2, "Stopping the Dashboard," on page 27.](#)

- 2 Open the `/OperationsCenter_Dashboard_install_path/server/conf/Catalina/localhost/ROOT.xml` file in a text editor.

- 3 Update the `mail.smtp.host`, `mail.imap.host` and `pop3.host` values. In the following example, updates are made for `acme.com`:

```
<Resource
  name="mail/MailSession"
  auth="Container"
  type="javax.mail.Session"
  mail.imap.host="imap.acme.com"
  mail.pop3.host="pop3.acme.com"
  mail.smtp.host="webmachine.acme.com"
  mail.store.protocol="imap"
  mail.transport.protocol="smtp"
/>
```

- 4 Save the file, then restart the Dashboard server.

For more information, see [Section 2.3.1, "Starting the Dashboard," on page 27.](#)

3.7 Configuring the Proxy Server

Some of the portlets utilized by Dashboard users might have links to external Web sites. If using a proxy server, configure those Dashboard settings to allow users access to these external Web site references. Proxy server settings are set in the `system.properties` file:

```
## HTTP
# Set the location of the HTTP proxy that the portal will use to fetch
# external content.
#http.proxyHost=192.168.0.200
#http.proxyPort=4480

# These are read for backwards compatibility and only used if the
# "http.proxyHost" and "http.proxyPort" settings are not specified.
#com.liferay.util.Http.proxy.host=192.168.0.200
#com.liferay.util.Http.proxy.port=4480

# Set the proxy authentication type.
#com.liferay.util.Http.proxy.auth.type=username-password
#com.liferay.util.Http.proxy.auth.type=ntlm

# Set user name and password used for HTTP proxy authentication.
#com.liferay.util.Http.proxy.username=
#com.liferay.util.Http.proxy.password=

# Set additional properties for NTLM authentication.
#com.liferay.util.Http.proxy.ntlm.domain=
#com.liferay.util.Http.proxy.ntlm.host=

# Set the connection timeout when fetching HTTP content.
#com.liferay.util.Http.timeout=5000
```


To update the Dashboard proxy server settings:

- 1 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/system-ext.properties` file in a text editor.

The `system-ext.properties` file overrides any default settings from the `system.properties` file.

- 2 Add the HTTP proxy server settings as shown above. Uncomment and modify the appropriate lines for your environment.

Do not change any other properties in this file unless you are aware of the consequences.

For more information about the `system.properties` file, see [Appendix A, "System Properties File," on page 237](#).

- 3 Save the `system-ext.custom.properties` file when your changes are complete.
- 4 Edit the Web Server startup file to add `-Dsystem.properties.load=true` to the Java JM arguments line:

- ♦ **Windows:** Update the `/OperationsCenter_Dashboard_install_path/bin/catalina.bat` file:

```
set JAVA_OPTS=-Xmx768m -XX:MaxPermSize=128m -XX:+PrintHeapAtGC -
XX:+PrintGCDetails -Xloggc:%CATALINA_HOME%\logs\mymogc.log -
XX:+DisableExplicitGC -Dsystem.properties.load=true -Dfile.encoding=UTF8 -
Djava.security.auth.login.config=%CATALINA_HOME%/conf/jaas.config
```

- ♦ **UNIX:** Update the `/OperationsCenter_Dashboard_install_path/bin/catalina.sh` file:

```
JAVA_OPTS="-Xmx768m -XX:MaxPermSize=128m -XX:+PrintHeapAtGC -
XX:+PrintGCDetails -Xloggc:$CATALINA_HOME/logs/mymogc.log -
XX:+DisableExplicitGC -Dsystem.properties.load=true -Dfile.encoding=UTF8
-Djava.security.auth.login.config=$CATALINA_HOME/conf/jaas.config"
```

- 5 Restart the Dashboard server for the changes to take affect.

For more information, see [Section 2.3.1, "Starting the Dashboard," on page 27](#).

3.8 Creating Operations Center Server Profiles

By default, all portlets pull data from the default Operations Center server. This server was specified when the Dashboard was installed and configured. However, the Dashboard supports the selection of additional Operations Center servers to use as data sources. To establish communication between the Dashboard and another server, a server profile must be set up and selected in the portlet configuration.

Server profiles are used by all Operations Center portlets except for the Refresh portlet.


When the Dashboard communicates with a Operations Center server to retrieve data, the Dashboard uses one user license from that server. Each Operations Center server with which the Dashboard communicates should be running the same software version, including the same patch release.

Each server profile establishes a connection between the Dashboard and a specific Operations Center server. The Dashboard Default Profile, a server profile for the default Operations Center server is automatically created when the Dashboard is installed and configured using the [Configuration Manager](#). This default server profile cannot be edited as a server profile; any changes to the Dashboard connection with this Operations Center server must be made in the Configuration Manager.

Additional server profiles are created and edited using the *Operations Center Server Profiles* portlet. Note that Operations Center server Profiles portlets can be removed from the Web page without deleting the server profile from the Dashboard.

To create or edit a server profile:

- 1 If not already available, add the *Operations Center Server Profiles* portlet to a dashboard page.



For more information about adding portlets, see [Section 6.2, "Adding Portlets," on page 94](#).

- 2 Click (Options) on the Operations Center server Profile portlet, and select Preferences.
- 3 Click *Create New Profile*.

To edit a profile, select it from the drop-down list for *Select Profile Name*, then click *Edit This Profile*.

- 4 Complete the following settings for the new profile:

Settings	Definition
<i>Profile name</i>	Name that displays on the portlet for the option to select a Operations Center server.
<i>Icon name</i>	Only default icons for Operations Center are available.
<i>RMI host or IP</i>	Communication settings for the Operations Center server.
<i>RMI port</i>	
<i>Web host or IP</i>	
<i>Web server port</i>	
<i>Web server protocol</i>	
<i>Use logged in user credentials</i> or <i>User Name and Password</i>	Enter a user name and password or select the <i>Use logged in user credentials</i> check box. The <i>Use logged in user credentials</i> option provides access control because a user can only access data for which the user has permission in the Operations Center server.
<i>Default profile</i>	If selected, the Operations Center server defined in this profile is the default Operations Center server used by all portlets when they are added to a page in the Dashboard, unless another profile is specified within the portlet.

- 5 Click *Save* to save to create a profile or save changes to an existing profile.
The profile is available for use by any portlets that support selection of different Operations Center servers.
- 6 Click *Return to Full Page* to close portlet preferences.

3.9 Understanding Portal Properties Files

As with many systems, properties files are used to configure various default settings for the Dashboard. These are not limited to, but include:

- ◆ Database settings
For more information about configuring the database connection, refer to [Section 2.2.3, “Configuring the Dashboard Database,”](#) on page 18
- ◆ Portal Time Zone
For more information about setting the time zone, refer to [Section 2.2.4, “Verifying the Dashboard Default Time Zone for User Accounts,”](#) on page 20.
- ◆ Auto-Login
For information about configuring auto-login with your Web Server, refer to [Section 3.3.1, “Implementing Auto-Login with Your Web Server,”](#) on page 34.
- ◆ Session timeout
For information about setting and disabling session timeout, refer to [Section 3.4, “Setting Session Timeout,”](#) on page 36.
- ◆ Synchronization with Operations Center
For information about access control synchronizer settings, refer to [Section 4.1.2, “Updating Access Control Synchronizer Settings,”](#) on page 51.
- ◆ Disabling of Self-Service Use Account Creation, Authentication and Notification Settings
For information self-service features on account creation, refer to [Section 4.4.1, “Self-Service User Account Creation, Authentication and Notification Settings,”](#) on page 61.
- ◆ Setting of default home pages for user groups.
For information configuring a home page based on user groups, communities and organization memberships, refer to [Section 5.8, “Configuring Default Home for User Groups, Communities and Organizations,”](#) on page 86.
- ◆ Configuration settings for Liferay servlets, portlets, and standard functionality.
For example, set the `my.places.max.elements` property to set the number of items (communities and organizations) shown in the Welcome drop-down list under My Places.

Liferay portal settings are defined in the `portal.properties` file. Other settings necessary to integrate Operations Center and Operations Center portlets are defined in the `portal-ext.properties` file. Do not modify this file, as you might overwrite any update process that is already running. Instead, custom configurations should always be made in the `portal-ext.custom.properties` file.

Configurations in the `portal-ext.custom.properties` file always take precedence over settings in the `portal-ext.properties` file, which in turn always take precedence over settings in the `portal.properties` file.

For information about configurations that can be made to the Dashboard, through the `portal-ext.custom.properties`, see <http://www.liferay.com/community/wiki/-/wiki/MainPortal+Properties+5.2.3>

3.10 Deploying Portlets to the Dashboard

Any portlet adhering to the JSR-168 standard can be deployed with Operations Center Dashboard. Portlets, including new versions of Operations Center portlets, can be deployed by saving the archive file in a specific the Dashboard directory or uploaded using Hot Deploy.

Portlets, layout templates, and themes are deployed by bundling the files into an archive file. A `.war` file is a standard practice based on Servlet 2.4 specification; refer to the JSR-168 specification for more information on Web application archives and portlets.

The following sections describe the two ways to deploy a portlet:

- ♦ [Section 3.10.1, “Deploying a Portlet,” on page 44](#)
- ♦ [Section 3.10.2, “Deploying a Portlet using Hot Deploy,” on page 44](#)

3.10.1 Deploying a Portlet

To deploy a portlet:

- 1 Bundle the new or modified portlet into a `.war` file and save it to the `OperationsCenter_Dashboard_install_path/deploy` directory.

The directory to deploy new portlets is set in the *Control Panel* under *Plugins Installation* (Click *Install More Portlets* feature and select *Configuration*). If for some reason portlets are not deploying as expected, verify your settings.

The new portlet is automatically deployed based on the Interval setting. The default is every 10 seconds. However, the Dashboard server can be restarted in order to force an immediate update if necessary.

3.10.2 Deploying a Portlet using Hot Deploy

To deploy a portlet using hot deploy:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Server*, select *Plugins Installation*.
- 3 Click *Install More Portlets*.
- 4 Click *Upload File*.
- 5 Click *Browse* to locate the `.war` file to deploy.
- 6 Optionally, specify the context for the deployment.
- 7 Click *Install* to upload the archive file and deploy the portlet.

3.11 Default Portlet Settings

Global default settings for Operations Center portlets can be modified by editing the `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEB-INF/data/globals.xml` file.

Default settings can be made per user basis by making a copy of `globals.xml` file and renaming it as `username_globals.xml`, and saving it in the same directory. `Username_globals.xml` file settings apply only to portlets added to a page by the specified user.

In the XML declarations, each portlet is made up of a set of portlet components where each value has an explanation and in brackets shows the accepted values. For example, in the `globals.xml` file, the following code snippet shows default height and width declarations for *Alarm* listings.

```
<component>
  <name>alarms</name>
  <preferences>
    <entry>
      <string>width</string>
      <string>400</string>
    </entry>
    <entry>
      <string>height</string>
      <string>300</string>
    </entry>
  </preferences>
</component>
```

[Table 3-1](#) shows default properties that can be set for portlets in the `globals.xml` file.

Table 3-1 Default Preferences for Portlets

XML Component Name	Description
layout	Defaults for layout diagrams. Preference declarations include: <ul style="list-style-type: none">♦ width: The width of the layout diagram.♦ height: The height of the layout diagram.♦ output: The output of the layout diagram (such as SVG or FLASH).♦ relationships: The diagram should display the relationships browser (True or False).
alarms	Defaults for all alarms listings. Preference declarations include: <ul style="list-style-type: none">♦ width: The width of the embedded alarms control.♦ height: The height of the embedded alarms control.
elementselector	Default element for single element portlets. Preference declarations include: <ul style="list-style-type: none">♦ identity: The DName of the element to be used as the starting element for all portlets that have an initial element as a starting point. If this option is not set, then the portlet selects the first home element of a user. If a home element has not been specified, then the <i>Services</i> element is used (<code>root=Organizations</code>).

XML Component Name	Description
elementsselector	<p>Default elements for multi-element portlets.</p> <p>If this option is not active, then the list of elements is populated with all of the home elements for the logged in user. If the user does not have a home element, than an empty list is displayed. Preference declarations include:</p> <ul style="list-style-type: none"> ◆ total: The total number of elements shown. ◆ identity0: The DName of the first element to be used. ◆ identityX: Specify additional DNames defining name as <i>identitynumber</i> where <i>number</i> continues until 1, minus the specified value of total.
navigation	<p>Default element for all portlets displaying an element navigation tree.</p> <p>There are no preference declarations made by default.</p>
performance	<p>Defaults for all performance chart portlets.</p> <p>Preference declarations include:</p> <ul style="list-style-type: none"> ◆ width: The width of the performance chart. ◆ height: The height of the performance chart. ◆ chartWidth: The width of the charts. ◆ chartHeight: The height of the charts.
propertietable	<p>Defaults for all element properties tables.</p> <p>Preference declarations include:</p> <ul style="list-style-type: none"> ◆ propertyList: A list of properties that displays for the current element and its direct descendants. <p>For each item declaration contained in <code>propertyList</code>, specify <code>propertyListItem</code> structures with the following definitions:</p> <ul style="list-style-type: none"> ◆ columnHeader: The column name displayed at the top of the table. ◆ property: The property to display. ◆ logicSign: The logic operator to apply to the value (such as equals, more, less). ◆ conditionalValue: The value that the property is evaluated against (any number). ◆ condition: The condition for setting the background color of the cell when the <i>property [logicSign] conditionalValue = conditional</i> For example, if set to "24 < 25 = True", the background to CRITICAL "[CRITICAL,MAJOR,MINOR, INFORMATIONAL,OK,UNKNOWN]. ◆ textBefore: Any text to display immediately before the property value (\$). ◆ textAfter: Any text to display immediately after the property value (%). ◆ conditional: When the evaluation results equals this value, then the background of the cell is set accordingly (True or False). ◆ order: Not used. ◆ identity: Unique key for this property, all properties must have a unique key.

3.12 Granting or Denying Access to Portlets

The Dashboard adheres to a JSP standard and is designed to be personalized. It offers many portlet options, including those that leverage Operations Center data as well as other third-party portlets offering various types of functionality. As an administrator, you can grant or restrict access to each portlet.

To restrict the use of a portlet based on user roles:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Plugins Configuration*.
- 3 By default, all portlets have the role *Users* listed, which allows all users access to the portlet. Restrict or grant access on a limited basis to the portlet by performing one of the following steps:
 - ♦ Click the link for the desired portlet.
 - ♦ To make the portlet unavailable to all users, deselect the *Active* check box.
 - ♦ To grant access based on specific roles, specify the role names in the area provided. Users assigned to the roles listed can add the portlet to their Web pages.
 - ♦ Click *Save*.
- 4 Click the *Back* link to exit the Control Panel.

While not a best practice, permissions can be configured for a specific instance of a portlet. For instructions, see [Section 11.2.2, "Assigning Individual Permissions to a Portlet,"](#) on page 224.

4 User Accounts

User and group accounts from the Operations Center server are leveraged by the Dashboard so it is important to understand how these accounts are synchronized and configured. The following sections provide important details regarding the interaction between Operations Center and the Dashboard as well as account permissions and user account structure:

- ♦ [Section 4.1, “Operations Center and Dashboard Interaction,” on page 49](#)
- ♦ [Section 4.2, “Understanding User Account Requirements,” on page 52](#)
- ♦ [Section 4.3, “Configuring Dashboard User Account Structure,” on page 53](#)
- ♦ [Section 4.4, “Managing User Accounts,” on page 60](#)
- ♦ [Section 4.5, “Understanding User Sign On,” on page 64](#)
- ♦ [Section 4.6, “User Maintained Account Settings,” on page 65](#)

4.1 Operations Center and Dashboard Interaction

User and group accounts from the Operations Center server are leveraged by the Dashboard to give users access to the Dashboard portal pages and Operations Center data via the Dashboard portlets. Limited status information on specific elements can be seen using the [Public User End View portlet](#) without logging into the Dashboard.

Operations Center and the Dashboard use the same user and group accounts. User accounts are organized into groups that exist both in Operations Center and in the Dashboard.

Because the same user accounts are used by both Operations Center and the Dashboard, actions performed on a user account in the Dashboard impact the account in Operations Center and vice versa.

While actions performed on user groups in Operations Center impact the groups in the Dashboard, the reverse is not true. Because of this, groups in the Dashboard can be organized into a different structure designed to follow your corporate hierarchy.

User accounts can be managed (created and edited) by administrators and by users themselves.

User accounts have different permissions in the Dashboard and Operations Center. The permissions in Operations Center determine the Operations Center content that the user can access in the Dashboard. Permissions to administer the dashboard, must be set in the Dashboard control panel.

- ♦ [Section 4.1.1, “Understanding User and Group Synchronization,” on page 50](#)
- ♦ [Section 4.1.2, “Updating Access Control Synchronizer Settings,” on page 51](#)
- ♦ [Section 4.1.3, “Understanding the Use of the Default Admin Account,” on page 51](#)
- ♦ [Section 4.1.4, “Understanding Access and Permissions for User Accounts,” on page 51](#)

4.1.1 Understanding User and Group Synchronization

Both user accounts and groups are synchronized between the Operations Center server and the Dashboard. There are two accounts in the Operations Center server that have a special use in the Dashboard: *admin* and *guest*.

During the first synchronization (on initial Dashboard server start up), all users and groups from the Operations Center server are imported into the Dashboard, setting up the same user/group associations in the Dashboard. Subsequent synchronizations vary based on whether the action is on a user account or group and where the action is taken.

Any Admin accounts imported from Operations Center, must be given Dashboard administrative permissions from the Dashboard control panel. For example, after the initial synchronization of accounts, give the Admin group administrative permissions in the Dashboard.

[Table 4-1](#) details the action or location of a user or group and the resulting synchronization:

Table 4-1 *User/Group Synchronizations*

Action/Location	Result
User account actions in Operations Center	Users updated/deleted in Operations Center are updated/deleted in the Dashboard during the next synchronization.
User account actions in the Dashboard	<p>The following actions taken in the Dashboard immediately have the same effect on the Operations Center server:</p> <ul style="list-style-type: none">◆ Add, edit, or delete user accounts <p>New users accounts are automatically added to the users group in the Operations Center server.</p> <ul style="list-style-type: none">◆ Change user account settings <p>For important information about passwords, see Section 4.2.3, "Understanding Password Policy," on page 53.</p> <p>The following actions in the Dashboard have no corresponding effect in the Operations Center server:</p> <ul style="list-style-type: none">◆ Deactivate users◆ Restore users
Group actions in Operations Center	Users removed from groups in the Operations Center server are removed from groups in the Dashboard during the next synchronization. Groups deleted in the Operations Center server are removed from the Dashboard during the next synchronization. This default behavior can be changed in Updating Access Control Synchronizer Settings (page 51) .
Group actions in the Dashboard	Groups that are deleted in the Dashboard are not deleted in Operations Center. Changes made to group membership in the Dashboard are not made to groups in Operations Center. Any groups created in the Dashboard are not maintained and are automatically deleted by the Dashboard.

Dashboard user profiles are assigned a default time zone based upon a global setting in the `system-ext.properties` file. For more about the time zone setting, see [Section 2.2.4, "Verifying the Dashboard Default Time Zone for User Accounts,"](#) on page 20. Users can later update this selection manually in their control panel.

4.1.2 Updating Access Control Synchronizer Settings

The first time that the Access Control Synchronizer runs (on initial Dashboard server start up), all the user accounts and groups from the Operations Center server are downloaded to the Dashboard, except those user accounts that have Web access restricted.

The Access Control Synchronizer continues to synchronize with the Operations Center server at specified intervals to maintain all users and groups. When each user logs into the Dashboard, their user account is automatically synchronized.

To update synchronization settings:

- 1 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file in a text editor.

For more information about the `portal-ext.custom.properties` file, refer to [Section 3.9, “Understanding Portal Properties Files,”](#) on page 43.

- 2 Add and update synchronizer properties as required:

mo.acl.synchronizer.enabled: Enables the synchronization of users and groups between Operations Center and the Dashboard. Default is `True`.

mo.acl.synchronizer.interval: The time, in milliseconds, between each synchronization. Default is `300000`, which equates to every 5 minutes.

Because the synchronizer synchronizes all accounts, consider the number of Operations Center users and groups as well as how often user and group information changes when setting this property.

mo.acl.synchronizer.on.login.enabled: Enables the synchronization of all user accounts whenever any user logs in. If enabled, the login process could take longer depending on the number of Operations Center users. If set to `False`, only the user’s account is synchronized on login.

mo.acl.synchronizer.keepUserGroupSynchronized: If enabled, actions taken on groups in Operations Center are also taken on groups in the Dashboard the next time synchronization runs. If set to `False`, groups are update with changes from the Operations Center server.

- 3 Restart the Dashboard server for the changes to take affect. For more information, see [Section 2.3.1, “Starting the Dashboard,”](#) on page 27.

4.1.3 Understanding the Use of the Default Admin Account

The Dashboard uses the default `admin` account to communicate with the Operations Center server. This account must have full privileges in Operations Center. The guest account in Operations Center is also used. For more information, see [Section 3.5, “Changing the Dashboard Account for Persistent Connection,”](#) on page 38.

4.1.4 Understanding Access and Permissions for User Accounts

Because the Dashboard and Operations Center use the same user accounts, they are subject to two different sets of permissions in the Dashboard as follows:

- ♦ **Dashboard Permissions:** These are relevant to all functionality in the Dashboard.

When user accounts are created in the Dashboard and thus added to the Operations Center server, the user is automatically added to the users group in the Operations Center server and receives all permissions assigned to the users group. These accounts are automatically set to have restricted access to the Operations Center console. This means that the user can only log in

to the Dashboard or another Operations Center Web client; the user cannot log in to the Operations Center console. For more information on how access is restricted, see the [Novell Operations Center 5.0 Security Management Guide](#).

Any Admin accounts imported from Operations Center, must be given administrative accounts in the Dashboard, to administer the Dashboard. For example, after the initial synchronization of accounts, you can give the Admin group administrative permissions in the Dashboard.

- ♦ **Operations Center Permissions:** These are relevant for determining the data in the Operations Center server that the user can access.

Operations Center permissions cannot be changed in the Dashboard. To change permissions to Operations Center, you must access the permissions in the Operations Center console. For more information on permissions in Operations Center, see the [Novell Operations Center 5.0 Security Management Guide](#).

When user accounts are added in Operations Center and given access to the portal, these users are automatically assigned to the users group in the Dashboard and are assigned to two roles: User and Power User. For more information on these roles, see [Section 11.1, "Assigning Permissions Using Roles,"](#) on page 215.

4.2 Understanding User Account Requirements

You need to specify a user name, password, and unique e-mail address for the Dashboard user accounts. For more information about requirements, see the following sections:

- ♦ [Section 4.2.1, "Understanding User Name Restriction,"](#) on page 52
- ♦ [Section 4.2.2, "Understanding Unique E-Mails,"](#) on page 52
- ♦ [Section 4.2.3, "Understanding Password Policy,"](#) on page 53

4.2.1 Understanding User Name Restriction

A user account for the Dashboard cannot have a use name that contains the domain name `managedobjects.com`. The Dashboard uses this domain name for a reserved user account.

If there is a user with this domain name in the Operations Center server, it does not synchronize with the Dashboard and an error is outputted to the trace logs. For more information, see [Section D.1.1, "User ID Exception – Unable to Synchronize User,"](#) on page 261.

4.2.2 Understanding Unique E-Mails

In order for the synchronization of users to occur in the Dashboard with the Operations Center server, the user account in Operations Center must have a unique, valid e-mail address.

IMPORTANT: User accounts must contain a valid, unique e-mail address to correctly synchronize between Operations Center server and the Dashboard.

A valid e-mail address follows this pattern: `_@_.` where `_` is a character. A valid e-mail address does not contain any spaces and has only one `@` sign.

User accounts in the Operations Center server are not required to have e-mail addresses. When user accounts are synchronized with the Operations Center server, if the Dashboard encounters an account without an e-mail address, it creates an e-mail address similar to the following:

`incrementalcount@novell.com`

During the user synchronization, if the Dashboard encounters a user account with an e-mail address that already matches an e-mail address for an existing account in the Dashboard, the Dashboard attempts to address the problem by adding “generated_” to the beginning of the e-mail address. However, if there are multiple e-mail addresses that are the same, the Dashboard won’t be able to correct them and there will be errors.

4.2.3 Understanding Password Policy

The Dashboard uses account information including passwords from the Operations Center server. How the Operations Center server handles passwords depends on the type of account:

- ♦ **Native Accounts:** In Operations Center, these accounts are stored and authenticated in the Operations Center server. For these accounts, the Operations Center administrator can set password policies.
- ♦ **External Accounts:** These accounts are stored in an external directory that are authenticated using LDAP. For these accounts, Operations Center does not store any password information.

When an account is created in the Dashboard, the account is a native account in Operations Center. The Dashboard enforces the password policy for Operations Center native accounts by default. If a password is entered during the account creation that does not match the password policy, then the account is not created.

Dashboard administrators as well as the users themselves can change passwords for user accounts in the Dashboard if the account is a native account in Operations Center. The Dashboard verifies that the password follows Operations Center password policy and allows the change if it does. If it does not, the Dashboard displays an error message and the password is not changed. If the account is an external account in Operations Center, the Dashboard does not show an option to change the password.

For information on how to create user accounts and change passwords, see [Section 4.4, “Managing User Accounts,”](#) on page 60.

4.3 Configuring Dashboard User Account Structure

Before a user logs in, all users are considered a guest. The Operations Center guest account is used to display the default home page.

User accounts in the Dashboard are organized two ways:

- ♦ By a structure that represents the corporate hierarchy
- ♦ By groups

Groups from Operations Center are imported into the Dashboard automatically. Changes made to groups in the Dashboard do not impact the group in Operations Center. However, by default, changes made to groups in Operations Center do impact the group in the Dashboard; this setting can be changed in [Section 4.1.2, “Updating Access Control Synchronizer Settings,”](#) on page 51.

The following sections review how you might organize the Dashboard user accounts into corporate hierarchy structure or configure the Dashboard groups:

- ♦ [Section 4.3.1, “Understanding the Dashboard Portal Architecture,”](#) on page 54
- ♦ [Section 4.3.2, “Configuring Corporate Hierarchy via Organizations and Locations,”](#) on page 56
- ♦ [Section 4.3.3, “Configuring Groups,”](#) on page 59


4.3.1 Understanding the Dashboard Portal Architecture

The following addresses the relationship between the various entities that define the portal architecture.

- ◆ Portals are accessed by *Users*.
- ◆ *Users* can be collected into *User Groups*.
- ◆ *Users* can belong to *Organizations*.
- ◆ *Organizations* can be grouped into hierarchies, such as Home Office -> Regional Office -> Satellite Office.
- ◆ *Users, Groups, and Organizations* can belong to *Communities* that have a common interest.

The simplest way to think about this is that you have users and various ways those users can be grouped together. Some of these groupings follow an administratively organized hierarchy, and other groupings can be done by the users themselves (such as different users from multiple organizations starting a community called “Dog Lovers” that has a common interest in dogs). And other groupings can be done administratively via Roles for other functions that might cut across the portal (such as a Message Board Administrators role made up of users from multiple communities and organizations, allowing those users to administer any message board in the portal).

This way of organizing portal concepts can be illustrated in the following manner:



In the illustration above, each arrow can be read as “can be a member of.” So this means that Organizations can be members of Communities, Communities can be members of Roles, Users can be members of anything, and so on. Though this seems very complex, it provides a powerful mechanism for portal administrators to configure portal resources and security in a consistent and robust manner.

It is important to note that the diagram illustrates only users and their collections. Permissions do not flow through all of these collections: permissions can be assigned to roles only.

Users

Users can be collected in multiple ways. They can be members of organization hierarchies, such as *Your Company, Inc. > Security > Internet Security*. They can be collected into arbitrary user groups, such as *Bloggers*, which would enable them to create blog entries in their personal space. They can be

members of communities which draw together common interests. And they can have roles which describe their functions in the system, and these roles can be scoped by Portal, Organization, or Community.

For more information about the Dashboard user accounts including default user associations, see [Section 4.4, “Managing User Accounts,” on page 60.](#)

User Groups

User groups are simple, arbitrary collections of users, created by administrators. They can be members of communities or roles. Permissions cannot be assigned to user groups. Though user groups do not have pages like some of the other collections of users (such as communities or organizations), they do have page templates which can be used to customize users' personal sets of pages.

For more information about user groups, see [Section 4.3.3, “Configuring Groups,” on page 59.](#)

Roles

There are three kinds of roles:

- ◆ Portal Roles
- ◆ Organization Roles
- ◆ Pages Community Roles

These are called role *scopes*. Roles are used to define permissions across their scope: across the portal, across an organization, or across a community. For example, consider a role which grants access to create a Message Board category. A Portal role would grant that access across the portal, wherever there was a Message Board portlet. A Community role would grant that access only within a single community. An Organization role would grant that access only within an Organization.

Because Roles are used strictly for portal security, they also do not have pages, like Communities and Organizations.

Users, User Groups, Communities, or Organizations can be members of a role.

For more information about roles, see [Chapter 11, “Portal and Community Permissions,” on page 215.](#)

Organizations

Organizations are hierarchical collections of *Users*. They are one of the two types of portal resources that can have pages. There is also a special type of Organization called a location, which can define where users are specifically located.

Organizations are useful for defining where a user belongs in a particular hierarchy. For example, if implementing the portal for a large organization, it might help to define user Joe Smith via his position in the organization chart. If Joe Smith is a Sales Engineer located in the New Jersey office, working in the North East division of the Sales department, he might be a member of the following organizations:

- ◆ Sales
- ◆ North East Division
- ◆ New Jersey Location

Then, if you add an Asset Publisher portlet as a static portlet on every user's home page (via a User Group page template) you can inform employees of various announcements via the content management system. If content is tagged appropriately, Joe Smith gets any announcements that are meant for Sales, the North East Division, or the New Jersey location.

Organizations can be members of *Communities*.

For more information about organizations, see [Section 4.3.2, “Configuring Corporate Hierarchy via Organizations and Locations,”](#) on page 56.

Communities

Communities are collections of *Users* who have a common interest. The Dashboard's default pages are in the *Guest* community, because everyone—whether they are anonymous or members of the portal—has a common interest in the default, public pages of your site. There are three types of Communities:

- ♦ Open
- ♦ Restricted
- ♦ Hidden

An Open Community (the default) allows portal users to join and leave the Community whenever they want to, using the Control Panel or a Communities portlet added to a page to which they have access. A Restricted Community requires that users be added to the Community by a community administrator. Users can use the Control Panel or the Communities portlet to request membership. A Hidden community is just like a Restricted community, with the added concept that it does not show up at all in the Communities portlet or the Control Panel.

For more information about communities, see [Chapter 5, “Personal Pages, Page Configurations, and Communities,”](#) on page 67.

4.3.2 Configuring Corporate Hierarchy via Organizations and Locations

Organizations are hierarchical collections of *Users*. They are one of the two types of portal resources that can have pages. There is also a special type of Organization called a location, which can define where users are specifically located.

An example of an organization is *Operations Center USA*. Organizations can have any number of sub-organizations or locations. Example locations of the *Operations Center USA* organization are *Operations Center Chicago*, *Operations Center San Francisco*, and *Operations Center Los Angeles*.

The following sections cover managing organizations and locations:

- ♦ [“Understanding Organizations and Locations”](#) on page 57
- ♦ [“Adding an Organization or Location”](#) on page 57
- ♦ [“Configuring an Organization”](#) on page 58
- ♦ [“Searching for an Organization”](#) on page 58

Understanding Organizations and Locations

Dashboard organizations are intended to model organizations in real life. They can be used to represent different companies, non-profit organizations, churches, schools, clubs, and so on. They have been used to represent a sports league, with various sports (soccer, baseball, basketball, etc.) and their teams as sub-organizations. If you have a set of users that belong to the same grouping, you can model as an organization.

Your dashboard can have any number of organizations, depending on the kind of site you are building. For example, a corporate site can model its own organization hierarchy, while a social networking site can have users from many various organizations who access the site. Organizations can have a hierarchy to unlimited levels, and Users can be members of one or many organizations—inside of a hierarchy or across hierarchies.

Additionally, Organizations can be associated with Roles. For example, an IT Security group of a company. You can have an organization within your IT organization that handles security for all of the applications company-wide.

If you had users as members of this organization, you could grant the Administrator role you just granted to your own ID to the whole Organization, thereby giving the members of the IT Security organization administrative access to the portal. If a user in this organization later was hired by the Human Resources department, the simple administrative act of moving the user from the IT Security organization to the HR organization would remove this privilege from the user, since the user would no longer be in an organization that has the Administrator role. By adding the user to the HR organization, any roles the HR organization has (such as access to a benefits system in the portal) would be transferred to the user. In this manner, you can design your portal to correspond with your existing organization chart, and have users' permissions reflect their positions in the chart.

Of course, this is only one way to design it. If you have more complex requirements, you can combine Organizations with User Groups and scoped Roles to assemble the sets of permissions you wish to grant to particular users.

Organizations are one of two types of resources (the other being Communities) that can have its own pages. This allows members of the organizations (if they are granted the Manage Pages permission) to maintain their own pages. They can have a set of public pages which include information and applications appropriate for guests or logged in users who are not members of the Organization to make use of (such as a help desk ticket entry system for an IT page), and they can have a set of private pages with applications for the organization's own use (such as the back-end portlets of the same ticketing system).

Adding an Organization or Location

To add an organization:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Organizations*.
- 3 Click *Add*.
- 4 Specify a name for the new organization in the *Name* field.
- 5 Specify whether the new organization is a regular organization or location in the *Type* drop-down list.
- 6 If the organization is a location, select a *Country* and *Region*.
- 7 Click *Select link to specify a parent organization*. A list opens to select the organization that is the direct parent of the organization. Click the *Remove* button to remove the currently configured parent.

8 Click *Save*.

The page shows additional options for entering information. Use the links to provide contact information about the organization: e-mail addresses, mailing addresses, Web sites and phone numbers.

9 Click *View All* to return to the list of organizations.

Configuring an Organization

To configure an organization:

1 Click *Welcome* and select *Control Panel*.

2 Under *Portal*, select *Organizations*.

3 Click *Action* next to organization and select from the options to update and configure the organization.

- ◆ **Edit:** Edit organization information.
- ◆ **Manage Pages:** Lets you create and manage public and private pages for the Organization.
- ◆ **Assign User Roles:** Lets you assign Organization-scoped roles to users. By default, Organizations are created with three roles: Organization Administrator, Organization Member, and Organization Owner. You can assign one or more of these roles to users in the organization. All members of the Organization get the Organization Member role.
- ◆ **Assign Members:** Search and select users in the portal to be assigned to this organization as members.
- ◆ **Add User:** Add new users in the portal who will be a member of this organization.
- ◆ **View Users:** List of users who are members of this organization.
- ◆ **Add Regular Organization:** Add a child organization to this organization to create hierarchies of organizations with parent-child relationships.
- ◆ **Add Location:** Add a child Location, which is a special type of organization that cannot have any children added to it.
- ◆ **View Suborganizations:** View all organizations that are children of this organization.
- ◆ **Delete:** Deletes this organization from the portal. Make sure to verify that the organization has no users in it first.

4 Click *Save*.

NOTE: You are already a member of the organizations you create. By creating an organization, you become both a member and have the Organization Owner role, which gives you full rights to the organization.

Searching for an Organization

To search for an organization:

1 Click *Welcome* and select *Control Panel*.

2 Under *Portal*, select *Organizations*.

3 Enter the search criteria in the search field.

4 Click *Advanced* to enter additional information such as address, region, type, or country; and specify how to match. Select *All* to find organizations that contain all search criteria, or *Any* to find organizations that contain at least one of the search criteria.

5 Click *Search*.

The results display at the bottom of the page.

4.3.3 Configuring Groups

Groups are designed to be a convenient mechanism for assigning users to communities and assigning permissions to users. Users can be members of one or more groups.

- ♦ [“Understanding Groups” on page 59](#)
- ♦ [“Creating User Groups and Assigning Users” on page 59](#)
- ♦ [“Configuring Groups” on page 59](#)

Understanding Groups

Groups are created and assigned like user accounts in the Dashboard. User Groups are arbitrary groupings of users. These groups are created by portal administrators to group users together who don't have an obvious organizational or community-based attribute or aspect which brings them together. Groups cannot have permissions like roles, but User Groups can be added to Roles. Why would you use User Groups, then? They come into play when you have complex security requirements and for page templates.

Creating User Groups and Assigning Users

Use the Operations Center console to create user groups and assign users. Any groups manually created in the Dashboard are automatically deleted.

For information on creating users and groups, see [“User and Group Accounts”](#) in the *Novell Operations Center 5.0 Security Management Guide*.

Configuring Groups

IMPORTANT: Actions taken on groups in the Dashboard (such as creating, updating, or deleting groups) do not impact the group in the [Operations Center server](#). However, by default, changes made to groups in Operations Center do impact the group in the Dashboard.

To configure a group:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *User Groups*.
- 3 Click *Action* next to organization and select from the options to update and configure the organization.
 - ♦ **Edit:** Modify the name or description of the group.
 - ♦ **Permissions:** Define which Users, User Groups, or Roles have permissions to edit the group.
 - ♦ **Manage Pages:** User Groups don't have pages of their own, you can create page templates for a group. When a User Group has page templates, any users added to the group will have the group's pages copied to their personal pages. This allows you to do things like create a Bloggers user group with a page template that has the Blogs and Recent Bloggers portlets on it. The first time users who are added to this group log in to the portal, this page is copied to their personal pages. They automatically have a blog page that they can use.

- ♦ **Assign Members:** Search for and select users in the portal to be assigned to the group.
- ♦ **View Users:** View all users in a group.
- ♦ **Delete:** Deletes the group.

4 Click *Save*.

4.4 Managing User Accounts

Managing user accounts involves the following:

- ♦ Creating users
- ♦ Editing user settings including passwords
- ♦ Deactivating and activating users
- ♦ Deleting users

Administrators can create users for their entity in the corporate hierarchy. The Dashboard also has functionality to allow users to create their own accounts (such as self-service account creation).

User accounts created in the Dashboard are automatically added to the Operations Center server and assigned to the users group. The user account is restricted to accessing only to the Operations Center Dashboard.

If there are specific e-mail addresses and/or user IDs that should not be used, identify them as reserved. These options can be found on the Control Panel under *Settings > Reserved Credentials*.


NOTE: When you create or delete users or alter user settings, the action applies to user accounts in the Operations Center server. Deactivating and activating users impacts the user account only in the Dashboard and has no impact on the user account in Operations Center.

- ♦ [Section 4.4.1, “Self-Service User Account Creation, Authentication and Notification Settings,” on page 61](#)
- ♦ [Section 4.4.2, “Default Associations for User Accounts,” on page 62](#)
- ♦ [Section 4.4.3, “Creating User Accounts,” on page 62](#)
- ♦ [Section 4.4.4, “Activating, Deactivating, and Deleting Accounts,” on page 64](#)

4.4.1 Self-Service User Account Creation, Authentication and Notification Settings

By default, the Dashboard home page contains a Sign In portlet allowing users to create new accounts. New users receive an e-mail containing a password. If required, the user can be forced to create a new password on initial login.

Figure 4-1 Sign In Portlet



The image shows a 'Sign In' portlet with a title bar. Below the title bar are two input fields: 'Screen Name' and 'Password'. Below the 'Password' field is a 'Remember Me' checkbox. Below the checkbox is a 'Sign In' button. At the bottom of the portlet is a 'Create Account' link with a small user icon to its left.

By default, the Dashboard uses the default local host for the IMAP and POP3 host to send e-mail to new users, for password requests, and password change notifications. For more information, see [Section 3.6, “Configuring the Mail Server,” on page 39](#).

Disable various user account authentication-related features in the Control Panel in *Settings > Authentication* including:

- ◆ Automatic login.
- ◆ Forgotten password request.
- ◆ Self service user account creation with e-mail address.
- ◆ E-mail verification on new accounts.

Configure e-mail notification functionality, including e-mail content, in the Control Panel in *Settings > Email Notifications*.

Some of these features can be disabled by adding and editing the relevant properties to `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file.

For more information about user authentication or e-mail notification, see the Liferay 5.2 documentation at <http://www.liferay.com/documentation/liferay-portal/5.2/getting-started>. Liferay Password Policies settings for Password Lockout and Password Expiration are unsupported by the Dashboard.


For information about the `portal-ext.custom.properties` file, refer to [Section 3.9, “Understanding Portal Properties Files,” on page 43](#).

4.4.2 Default Associations for User Accounts

It is possible to select a default user groups, communities, and roles for all new users that are created in the dashboard.

To automatically assign all new users to one or more user groups, communities or roles:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Settings*.
- 3 Select *Default User Associations*.



Automatically assign new users to one or more user groups, communities or roles.

- 4 In the *Communities* field, enter one or more community names, one per line.
- 5 In the *Roles* field, enter one or more roles, one per line.
- 6 In the *User Groups* field, enter one or more user group names, one per line.
- 7 Click *Save*.

4.4.3 Creating User Accounts

Administrators can create and edit accounts for users through the Control Panel. By default, all new users are automatically active. Note that most users won't be able to perform most of the operations or have access to the Control Panel. Only those with administrative can perform all of the functions.

- ♦ [“Adding a User” on page 63](#)
- ♦ [“Configuring User Accounts” on page 63](#)
- ♦ [“Searching for Users” on page 64](#)

Adding a User

To add a new user:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Users*.
- 3 Click *Add*. The *Add User* form displays.
- 4 Specify user details in the fields provided.
First name, last name, e-mail address, and screen name are required.
- 5 Click *Organizations* to select any organizations and/or location for the user.
- 6 Click *Save*.
- 7 When the user ID is created, a password is automatically generated and an e-mail message with the password in it is sent to the user if the SMTP mail server connection was setup properly. Additional options are available through links on the right.
- 8 If you have not yet set up your mail server, click *Password* to change the default password for the user ID to something you can remember and send to the user.
Click *Save* after making changes.
- 9 Click *Roles* to assign administrative rights to the user if necessary. By default, all users are also assigned the *Power User* role. You can give this role certain permissions if you wish or disable it altogether.
Click *Select* to select any additional roles for the user.
Click *Save* after making changes.

NOTE: When a new user is added, the same user account is added to the Operations Center server and is automatically given access to the Operations Center Dashboard and is placed in the users group.

Configuring User Accounts

To configure a user account:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Users*.
- 3 Click *Action* next to the user and select from the options to update and configure the user account.
 - ◆ **Edit User:** Modify the user account.
 - ◆ **Permissions:** Define which Roles have permissions to edit the user.
 - ◆ **Manage Pages:** Edit any pages the user has.
 - ◆ **Impersonate User:** Browse the site as though you were the user in a new browser window.
 - ◆ **Deactivate:** Deactivate the user account.
- 4 Click *Save*.

Searching for Users

When you have a long list of users, you can search for a specific user.

To search for a user:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Users*.
- 3 Enter search criteria in the Search field.
Click *Advanced* to define additional search criteria.
- 4 Click *Search* to find any users matching the criteria.

4.4.4 Activating, Deactivating, and Deleting Accounts

Using the Control Panel, you can deactivate accounts, which prevents a user from logging in to the Dashboard. You can also restore the account so it is active. These actions do not affect the user account in the Operations Center server.

After an account has been deactivated, you can permanently delete it. A user account deleted in the Dashboard is also deleted in the Operations Center server.

To activate, deactivate or delete a user account:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Users*.
- 3 Do any of the following:
 - ♦ To deactivate a user account, click *Actions* and select *Deactivate* next to the user's name.
 - ♦ To restore a user account that has been deactivated, click *No* for the *Active* drop-down list in advanced search options, then click *Search* to view all deactivated users.
Click *Actions* and select *Activate*.
 - ♦ To delete a user account, first deactivate the account, then in the user list for accounts that are not active, click *Actions* and select *Delete*.

4.5 Understanding User Sign On

Users must sign into the portal with user name and password of a valid Dashboard account to access the Dashboard. User name and password can be entered into the Dashboard one of two ways:

- ♦ **Sign In portlet:** The Sign In portlet appears on the home page of the Dashboard by default and allows users to enter user name and password that the Dashboard uses to grant access. It can also be accessed by clicking *Welcome* selecting *Sign In*.
- ♦ **Auto-login:** The Dashboard has auto-login functionality that supports Single Sign On (SSO) capability, which allows users to log in just once into the system and gain access to various resources. If a user has already logged in, that user does not need to log in again to gain access to the Dashboard. Auto-login must be configured. For more information, see [Section 3.3.1, "Implementing Auto-Login with Your Web Server,"](#) on page 34.

4.6 User Maintained Account Settings

After a user has logged into the Dashboard, that user can access account settings and make changes. The option to edit your password is only available if the user account is a native account in Operations Center. For important information, see [Section 4.2.3, “Understanding Password Policy,” on page 53](#).

5 Personal Pages, Page Configurations, and Communities

Dashboard pages can be considered as desktops where portlets are added. These include personal pages for individual users and shared pages among multiple users. Shared pages are grouped together into communities. Communities offer content to users with a similar interest or skill.

Users can have both personal and shared pages. They switch between personal pages and communities using a link.

- ♦ [Section 5.1, “Customizing Default Personal Pages,” on page 67](#)
- ♦ [Section 5.2, “Creating and Maintaining Communities,” on page 68](#)
- ♦ [Section 5.3, “Adding Pages,” on page 72](#)
- ♦ [Section 5.4, “Community Provisioning,” on page 74](#)
- ♦ [Section 5.5, “Assign Users to a Community,” on page 76](#)
- ♦ [Section 5.6, “Changing Page Layout,” on page 78](#)
- ♦ [Section 5.7, “Changing the Look and Feel,” on page 79](#)
- ♦ [Section 5.8, “Configuring Default Home for User Groups, Communities and Organizations,” on page 86](#)
- ♦ [Section 5.9, “Importing and Exporting Data and Configurations from User Groups, Communities, or Organizations,” on page 88](#)

5.1 Customizing Default Personal Pages

Personal pages are Web pages that can be viewed and modified by a single user only. When a user logs in on the Dashboard home page, the user’s personal pages appear. Personal pages, and the portlets on them, are accessible only to that user. No other users, including administrators, can access these pages.

NOTE: The information from a portlet in a personal page can only be viewed by the page owner, even if view permissions are granted to other users. For example, in the case of a Calendar portlet, only the page owner could view the events on the calendar. To share information, place portlets on community or public pages.

To have personal pages, a user must be assigned the role of power user. For more information, see [Section 11.1, “Assigning Permissions Using Roles,” on page 215](#). For information on how to add pages, customize the look and feel of those pages and add content, see [Chapter 6, “Adding Content to a Page Using Portlets,” on page 91](#).

By default, power users have their own personal Web pages.

To modify the default setup of the power users personal Web page:

- 1 Add the following properties in the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file:

```
## Default User
##
#
# Users who have the Power User role must have at least one private
personal
# page. The settings for the initial private page are specified in the
# following properties.
#
#
# Set the layout name.
#
default.user.layout.name=Home
#
# Set the layout template id that matches an existing TPL.
#
#default.user.layout.template.id=1_2_1_columns
#default.user.layout.template.id=1_column
#default.user.layout.template.id=2_2_columns
#default.user.layout.template.id=2_columns_i
default.user.layout.template.id=2_columns_ii
#default.user.layout.template.id=2_columns_iii
#default.user.layout.template.id=3_columns
#
# Set the layout ids for the column specified in the layout template.
#
default.user.layout.column-
1=mo_alarms_WAR_ManagedObjectsPortlets,23,61,65,
default.user.layout.column-2=8,11,36,33,
default.user.layout.column-3=
default.user.layout.column-4=
#
# Enter either "800x600" or "1024x768" to set the layout resolution.
#
default.user.layout.resolution=800x600
```

In the above code, the following lines define the portlets and the columns where the properties can be displayed:

```
default.user.layout.column-
1=mo_alarms_WAR_ManagedObjectsPortlets,23,61,65,
default.user.layout.column-2=8,11,36,33,
```

- 2 To find a listing of all Operations Center portlets and determine their names to reference them, look at the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/portlet.xml` file.

Use the `<portlet-name>` in the list followed by `_WAR_ManagedObjectsPortlets` as shown above in the code sample for the `mo_alarms` portlet.

5.2 Creating and Maintaining Communities

Communities are very much like Organizations except that they are not hierarchical. They are designed instead to be islands to themselves which anyone from any organization (or from no organization at all) can join. Use Communities in any situation where you need to cut across the

organizational structure of your portal, or where you have a site that would apply to almost anybody. For example, the home page for the Intranet is probably best placed in a community that any member of the portal can access.

Communities are groupings of pages and users based on shared interests or skills. And, a user can belong to any number of communities. Examples of communities might include:

- ♦ A human resources community where staff members discuss issues related to health insurance.
- ♦ A tech support community of users who have the skills to provide technical support to an organization.
- ♦ A marketing community where marketing personnel shares marketing and corporate information.

The Dashboard default home page is in a community called *Guest*, and this is where you would put your public web site. As you can see, there are several scenarios in which you would want to use something like a community instead of an organization, and this is why they have a distinct role within Liferay Portal.

Communities can be created and managed in two ways. The first is through the *Control Panel*, like every other user/page collection. The second is through the *My Communities* portlet, which can be added to any page. Why two ways? Because the *My Communities* portlet also doubles as a way to navigate from community to community, and allows users to browse the list of communities.

Permissions can be assigned to users to delegate community management tasks. For more information, see [Chapter 11, “Portal and Community Permissions,” on page 215](#).

Every community must have at least one page (represented by a tab) to be active, but there is no limit on the number of pages that a community can have.

After a community is named, define its characteristics and add content pages. Consider the following:

- ♦ Every community must have at least one page (represented by a tab) to be active, but there is no limit on the number of pages that a community can have.
- ♦ Pages can be private or public. A public page can be accessed by a guest who has the appropriate URL. A private page can only be accessed by users who are logged in and assigned to the community.
- ♦ URLs must be defined for public and private pages.
- ♦ A default look and feel can be set for all private and public pages.

NOTE: You are already a member of the organizations you create. By creating an organization, you become both a member and have the Organization Owner role, which gives you full rights to the organization.


To create and configure communities:

- ♦ [Section 5.2.1, “Creating a New Community,” on page 70](#)
- ♦ [Section 5.2.2, “Performing Actions on a Community,” on page 70](#)
- ♦ [Section 5.2.3, “Updating Community Settings,” on page 71](#)

5.2.1 Creating a New Community

To create a community:

- 1 Do one of the following:
 - ♦ Go to a page that has a *My Communities* portlet. Click *Add Community*.
 - ♦ Click *Welcome* and select *Control Panel*. Under *Portal*, select *Communities*. Click *Add*.



The screenshot shows a web form titled "My Communities" with a "Return to Full Page" link in the top right. The form contains the following elements:

- View All Add** link
- Name** text input field containing "New Products"
- Description** text area containing "A community dedicated to new products and product features."
- Type** dropdown menu set to "Open"
- Active** checked checkbox
- Tags** text input field, followed by "Add Tags" and "Select Tags" buttons, separated by "Or"
- Save** and **Cancel** buttons at the bottom

- 2 Name the new community and optionally add a description.
- 3 Select one of the following to indicate the type of community:
 - ♦ **Open:** Appears in the *My Communities* portlet and users can join and leave the community whenever they want.
 - ♦ **Restricted:** Appears in the *My Communities* portlet but users must request membership and be approved before joining.
 - ♦ **Private:** Does not appear in the *My Communities* portlet. Users are added manually by a community administrator.
- 4 Deselect the *Active* check box to inactivate the community and no data can be added to it.
- 5 Specify keywords in the *Tags* field to identify the community and leverage the portals tagging feature.
- 6 Click *Save*.

5.2.2 Performing Actions on a Community

To configure a community:

- 1 Do one of the following:
 - ♦ Go to a page that has a *My Communities* portlet.

- ♦ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*.
- 2 Click *Action* next to the community and select from the options to update and configure the community.
 - ♦ **Edit:** Edit the community definition.
 - ♦ **Manage Pages:** Create and manage public and private pages for the community. Also update community settings.
 - ♦ **Assign User Roles:** Assign community-scoped roles to users. By default, communities are created with three roles: *Community Administrator*, *Community Member*, and *Community Owner*. Assign one or more of these roles to users in the community. All members of the community get the *Community Member* role.
 - ♦ **Assign Members:** Takes you to a screen where you can search and select users in the portal to be assigned to this community as members.
 - ♦ **Join/Leave:** If you are not a member of the community, you will have a Join or Request Membership option. If you are a member of the community you will see an option to leave the community.
 - ♦ **Delete:** Users with administrative access to the portal or who are owners of the community can delete it.
 - 3 Click *Save*.

5.2.3 Updating Community Settings

Various settings can be configured for each community including a friendly URL, a custom logo, generation of a sitemap structure to notify search engines, and monitoring through Google Analytics.

To update the settings for a community:

- 1 Do one of the following:
 - ♦ Go to a page that has a *My Communities* portlet.
 - ♦ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*.
- 2 Click *Action* next to the community and select *Manage Pages*.
- 3 Click the *Settings* tab.
- 4 Select from the following tabs to specify settings for the community.
 - ♦ **Staging:** Activate staging.
 - ♦ **Virtual Host:** Specify a public and private virtual host that maps to the public and private friendly URL. Also specify a friendly URL that is used for both public and private pages.
 - ♦ **Sitemap:** Generate a sitemap to notify Google and Yahoo of the structure of the community pages.
 - ♦ **Monitoring:** Specify a Google Analytics ID to setup tracking for community pages in an existing Google Analytics configuration.
 - ♦ **Logo:** Add a custom logo for the community.
 - ♦ **Merge Pages:** Configure the top level pages to merge with the top level Guest community. This helps user navigate between the two sites seamlessly.
- 5 Click *Save*.

5.3 Adding Pages

Pages can be added to a community in a hierarchy that creates pages under an existing page. It is possible to rearrange the order of child pages. The pages in the top-level of the hierarchy are added as tabs in the community. Pages that are children of a top-level page do not display on the tab unless a Navigation portlet is added to that tab.

Web pages can be personal or associated with a community.

- ♦ **Adding:** Add pages to personal or community pages using *Manage Pages*. Using this option, it is possible to add pages to the current community only. Pages can be added to other communities by using the *My Communities* portlet.
- ♦ **Exporting:** Export the pages of a community using *Manage Pages*.
- ♦ **Importing:** Import pages to a community using *Manage Pages* or the *My Communities* portlet. Importing a page overwrites all the pages in the community. Take caution, because importing a page overwrites the current page and thus discontinues access to the Dashboard. For more information on export and import options for a community, see [Section 5.2, “Creating and Maintaining Communities,” on page 68](#).

When building Web pages, particularly when adding portlets to add content, consider how the content is viewed. Users can view dashboard Web pages using a variety of devices, including mobile phones.

A user’s ability to add pages depends on the permissions assigned to the user. For more information, see [Chapter 11, “Portal and Community Permissions,” on page 215](#).


To make it easier to create a page, copy an existing page and save it as a new page using the *Copy* option. This option is available on the *Page* tab.

- ♦ [Section 5.3.1, “Adding Child Pages,” on page 72](#)
- ♦ [Section 5.3.2, “Editing an Existing Page,” on page 74](#)


5.3.1 Adding Child Pages

To add child pages:

- 1 Do one of the following:
 - ♦ Go to a page that has a *My Communities* portlet.
 - ♦ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*.
- 2 Click *Action* next to the community and select *Manage Pages*.
- 3 Select either *Public Pages* or *Private Pages*, depending on which set of pages you want to edit.



- 4 In the *Name* field, specify the name of the page.
- 5 From the *Type* drop-down list, select the type of page, choosing from *Portlet*, *Panel*, *Embedded*, *Web Content*, *URL*, or *Link to Page*.
The first page must be of *portlet* type.
- 6 Select the *Hidden* check box if the page is to be hidden.
- 7 Click *Add Page*. The new page shows in the list of links on the left side.



- 8 Define additional pages as required.
Pages added when the name of the community is selected are top-level pages that appear as tabs.
Select a page link to add child pages underneath. Select the *Copy Parent* check box to copy settings from the parent page.
- 9 Select each page and click the *Page* tab to specify various settings for the page including friendly URL, meta tags, custom JavaScript, and meta robot settings.
- 10 To change the order of the top-level page tabs, do the following:
 - ◆ Click the community name and select the *Display Order* tab.
 - ◆ Move the page names up and down as required.
 - ◆ Click *Update Display Order* to save your changes.
- 11 Click *Look and Feel* at any level to set the default theme and colors for all private or public pages or the specific page.
- 12 Click *View Pages* to open the community in a new browser window.
- 13 Click *Publish to Remote* to publish pages remotely.

5.3.2 Editing an Existing Page

To edit an existing page:

- 1 Click *Welcome* and select *Manage Pages*.
- 2 Select the page to edit, then click *Page*.
- 3 Edit the settings as necessary:
 - ♦ To copy the contents of another page to the selected page, select an existing page name from the *Copy Page* drop-down list.
For example, to copy the contents of *Support* to the *myFinances* page, click the *Support in the Copy Page* option. Note that any existing content on the page is overwritten.
 - ♦ To delete a page, edit it, then click *Delete*.
- 4 Click *Save*.

5.4 Community Provisioning

Communities are ideal workspaces for teams to collaborate on common projects. They provide an isolated area where a group of people can place all of their data pertaining to a particular topic, and many organizations have used them for this purpose. It is a far better way to share data than using e-mail and a shared folder on a network. Instead,

- ♦ The *Document Library* portlet (under *Content Management*) empowers users to access and update documents simultaneously, and all versions of the documents are preserved.
- ♦ A *Calendar* portlet (under *Collaboration*) can be used to keep track of the team's appointments and meetings, and can send notifications out to the team.
- ♦ A *Wiki* portlet (under *Collaboration*) can be used to document the project as it progresses.
- ♦ A *Message Boards* portlet (under *Collaboration*) can be used to keep all team discussions in one place.

The ad-hoc creation of communities for this purpose allows portal administrators to create communities based on templates. What this means is that you can create a template community that has a pre-defined set of pages and portlets, and then use that template to very quickly create multiple communities that are pre-populated with those pages and portlets. Defining community templates streamlines the community creation process for administrators, making it very easy to quickly create communities for teams.

Templates can be created for open, restricted, and private communities. Additionally, create a default template that applies to all kinds of communities.

To setup a community template:

- 1 Do one of the following:
 - ♦ Go to a page that has a *My Communities* portlet.
Click *Add Community*.
 - ♦ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*.
Click *Add*.

The screenshot shows a web form titled "My Communities" with a "Return to Full Page" link. The form contains the following elements:

- Name:** A text input field containing "DEFAULT_TEMPLATE".
- Description:** A text area containing "Main template for all pages." with a vertical scrollbar.
- Type:** A dropdown menu set to "Private".
- Active:** A checked checkbox.
- Tags:** A text input field followed by "Add Tags" and "Select Tags" buttons, separated by "Or".
- Buttons:** "Save" and "Cancel" buttons at the bottom left.

- 2 Name the community one of the following:
 - ◆ **DEFAULT_TEMPLATE:** to create a default template used by all types of communities.
 - ◆ **OPEN_TEMPLATE:** to create a template used by all open communities.
 - ◆ **RESTRICTED_TEMPLATE:** to create a template used by all restricted communities.
 - ◆ **PRIVATE_TEMPLATE:** to create the template used by all private communities.
- 3 Select *Private* for the community type.
- 4 Click *Save*.
- 5 Click *Actions* for the community template and select *Manage Pages*.
- 6 Click *Settings*. The *Setting* tab opens.

The screenshot shows the "Edit Pages for Community: DEFAULT_TEMPLATE" page. It features a navigation bar with tabs for "Public Pages", "Private Pages", and "Settings" (which is highlighted in blue). A "« Back" button is on the right. Below this is another set of tabs: "Staging" (highlighted in blue), "Virtual Host", "Sitemap", "Monitoring", "Logo", and "Merge Pages". At the bottom, there is an "Activate Staging" checkbox that is checked.

- 7 Select the *Activate Staging* check box.
- 8 Use the *Public Pages* or *Private Pages* tabs to create pages in the template and populate them with portlets.

Use *View Pages* to view the pages you are creating, to add portlets, and to change layouts. These pages will be surrounded by a red border. This indicates that you are working in a staging environment.

For more information about adding pages and portlets to a community, see [Section 5.3, "Adding Pages," on page 72](#).
- 9 Any future communities that you create will have the same layouts and portlets as what you have defined based on the default template and any templates defined for that community type.

IMPORTANT: Never publish changes to a template; leave it always in staging mode.

5.5 Assign Users to a Community

Users must be assigned to a private community in order to gain access to it. After assigned, the user accesses the community via the community's URL. Users who do not have personal pages go directly to the community pages on login.

Open communities allow users to join and leave at any time without approval from an administrator. Restricted communities force users to request membership which is approved by an administrator. Private communities only receive new members who are assigned by an administrator either individually or by association.

In the *My Communities* portlet, under the *Available Communities* tab, the user can join any open communities or request to join any restricted communities.

Community administrators can assign users to communities in two ways:

- ♦ **Directly:** Assign users directly to a community by assigning their user account to the community.
- ♦ **Indirectly:** Assign users indirectly by first assigning them to entities, such as groups, organizations, or locations, then assign these entities to a community. Users who belong to a group, organization, or location that is assigned to a community are also assigned to the community.

All community members, regardless of whether they were assigned directly or indirectly, have access to the same functionalities.

For more information about setting default communities for users, see [Section 4.4.2, "Default Associations for User Accounts,"](#) on page 62.


TIP: If the list of available users, user groups, organizations, or locations is long, use the Search function to locate specific entities.

- ♦ [Section 5.5.1, "Assign Users Directly to a Community,"](#) on page 76
- ♦ [Section 5.5.2, "Assign Groups, Organizations, or Locations to a Community,"](#) on page 77
- ♦ [Section 5.5.3, "Remove Users,"](#) on page 78

5.5.1 Assign Users Directly to a Community

To assign users directly to the community:

- 1 In the *My Communities* portlet, locate the desired community.
- 2 Click *Actions* and select *Assign Members* next to the community.
The *Users* tab displays the users currently directly assigned to the community.
- 3 Click *Available* to view a list of all users.



- 4 Select the check box next to the user names to add to the community.
- 5 Click *Update Associations*.


5.5.2 Assign Groups, Organizations, or Locations to a Community

To assign groups, organizations, or locations to a community:

- 1 In the *My Communities* portlet, locate the desired community.
- 2 Click *Actions* and select *Assign Members* next to the community.
- 3 Select *User Groups* or *Organizations*.

The selected tab displays the user groups or organizations currently directly assigned to the community.

- 4 Click *Available* to view a list of all available user groups, organizations, or locations.



- 5 Select the check box next to the entities to assign to the community.
- 6 Click *Update Associations*.

5.5.3 Remove Users

Users are able to remove themselves from open communities from the *My Communities* portlet (Click *Actions* and select *Leave*). Users are not able to remove themselves from private communities; they must be removed by a community administrator.

Community administrators can remove users from any community. If a user is a member of the community through membership in a group, organization, or location that is assigned to the community, you need to do one of two things:

- ♦ [“Removing Users Directly Assigned to a Community” on page 78](#)
- ♦ [“Removing A Group, Organization, or Locations Assigned to a Community” on page 78](#)

Removing Users Directly Assigned to a Community

- 1 In the *My Communities* portlet, locate the desired community.
- 2 Click *Actions* and select *Assign Members* next to a community.
The *Users* tab opens.
- 3 Click *Current*.
- 4 Deselect the check box next to the names of users to remove from the community.
- 5 Click *Update Associations*.

Removing A Group, Organization, or Locations Assigned to a Community


- 1 In the *My Communities* portlet, locate the desired community.
- 2 Click *Actions* and select *Assign Members* next to a community.
The *Users* tab opens.
- 3 Select *User Groups* or *Organizations*.
- 4 Deselect the check box next to the names to remove from the community.
- 5 Click *Update Associations*.

5.6 Changing Page Layout

By default, a dashboard page uses the two-column layout to display content on the Web page. The page can be easily changed to use another page layout using various page layout templates.

To change the layout of a page:

- 1 Click *Welcome* and select *Layout Template*.



- 2 Select the desired layout.
- 3 Click *Save*.

5.7 Changing the Look and Feel

Themes are used to set the look and feel for a page. To set these options, click *Welcome* and select *Manage Pages*, then click the *Look and Feel* tab. The look and feel for pages within a community can also be set by the community administrator on the *My Communities* portlet. A child page inherits the look and feel of a parent page unless it is specifically changed.

- ♦ [Section 5.7.1, “The Default Themes Library,” on page 79](#)
- ♦ [Section 5.7.2, “Selecting the Look and Feel,” on page 85](#)
- ♦ [Section 5.7.3, “Installing Additional Themes,” on page 85](#)

5.7.1 The Default Themes Library

The Dashboard comes with a small library of default themes and color schemes. Additional themes can be uploaded from the Liferay Marketplace at (<http://www.liferay.com/marketplace>).


The following sections describe the following default themes:

- ♦ [“Novell Theme” on page 80](#)
- ♦ [“Sleek Theme” on page 81](#)
- ♦ [“Simple Theme” on page 82](#)
- ♦ [“Classic Theme” on page 82](#)
- ♦ [“Desktop Theme” on page 84](#)

Novell Theme

The Novell theme is the default theme and is the selected theme for all images shown in this guide:

Figure 5-1 Novell Theme



Sleek Theme

The Sleek theme is simple, yet modern with lots of white space. Portlet icons become visible when the cursor is moved over the portlet's title bar.

Figure 5-2 Sleek Theme

The screenshot displays the NetIQ Sleek Theme dashboard. At the top left is the NetIQ logo. At the top right, a blue button says "Welcome Admin!". Below the logo is a horizontal navigation bar with links: "Welcome", "Performance Portlet", "Properties Table", "Information Portlet", "Chart Builder", "Layout portlet", and "Root Cause".


The main content area is divided into several sections:

- Add Page**: A sub-section with the title "About Dashboard". It contains three paragraphs of text describing the Novell Operations Center Dashboard, its features for personalization, and a reference to the Dashboard Guide. Below the text are three small icons: a globe, a gear, and a document.
- Sign In**: A box on the right side of the dashboard stating "You are signed in as Default Administrator."
- My Communities**: A section with three tabs: "Communities I Own", "Communities I Have Joined", and "Available Communities". Below the tabs is a search input field with a "Search" button and an "Add Community" button.

Simple Theme

The Simple theme is a very clean looking theme with a blue tabs and portlet title bars:


Figure 5-3 Simple Theme



Classic Theme

The Classic theme has a black header showing page portlets displayed in blue, green or orange boundaries.

Figure 5-4 Classic Theme




The Classic theme can be selected in the following colors:

- ◆ Blue (default)
- ◆ Green
- ◆ Orange

Desktop Theme

The Desktop Theme simulates a desktop look and feel. The Welcome menu is replaced with a spherical icon in the top left corner of the page for the Liferay version, with portlets displaying as tabs across the top.

Figure 5-5 Desktop Theme



The Desktop theme has the following variations:

- ♦ Liferay (as shown in the illustration above)
- ♦ Mac

5.7.2 Selecting the Look and Feel

To set the look and feel (such as theme and color scheme):

- 1 Click *Welcome* and select *Manage Pages*.
- 2 Click the *Look and Feel* tab.

Edit Public Page: [Guest](#) » [Welcome](#)


Page Children **Look and Feel**

Regular Browsers Mobile Devices

Use the general look and feel for the public pages? No

Themes CSS

Current Theme




Novell


Author
[Novell, Inc.](#)

Available Themes (4) [Install More](#)


Classic



Desktop



Simple



- 3 Select a theme and, if applicable, a color scheme.

5.7.3 Installing Additional Themes

New themes can be downloaded from the Liferay Marketplace at (<http://www.liferay.com/marketplace>). Or, if you have a custom theme, you can upload and install it using a `.war` file.

To install new themes:

- 1 Click *Welcome* and select *Manage Pages*.
- 2 Click the *Look and Feel* tab.
- 3 Click *Install More*. The *Plugin Installer* opens with the *Theme Plugins* tab open.
- 4 Click the *Upload File* tab, then browse for the new `.war` file to install.
- 5 Click *Install* to install theme. A message displays that theme is downloaded successfully and installation is in progress.

6 Click *Back* to return to the *Manage Pages > Look and Feel* page.

7 Select the new theme when it displays under the *Themes* tab.

5.8 Configuring Default Home for User Groups, Communities and Organizations

By default, the standard *Welcome* page is displayed on login for all users. However, specific landing pages can be defined for user group, community, or organization; by adding property settings to the `portal-ext.custom.properties` file. Depending on your requirements, it may require setting a *Friendly URL* in the page's Control Panel settings.

In the following example, using the simplest of declarations, a user is directed to the landing page for the first community that he is a member of. If not a part of any community, it directs him to the first organization that he is a member of. If not part of any organization, it directs him to the default landing page which is the guest home page. In all cases, it looks for `/home` pages.

```
login.events.post=com.mosol.liferay.authenticator.LoginPostAction,  
com.liferay.portal.events.DefaultLandingPageAction,  
com.mosol.liferay.portal.events.OrganizationLandingPageAction,  
com.mosol.liferay.portal.events.CommunityLandingPageAction
```

In the next example, if a user belongs to one of three groups, he is directed to that group's landing page. If the user belongs to more than one group, the *operator* group is given preference over *dba*, and *dba* is given preference over *analyst*. If the user does not belong to any of the groups, he is directed to the default landing page which is the guest home page.

```
login.events.post=com.mosol.liferay.authenticator.LoginPostAction,  
com.liferay.portal.events.DefaultLandingPageAction,  
com.mosol.liferay.portal.events.UserGroupLandingPageAction
```

```
dashboard.UserGroupLandingPageAction.group.order=operator, dba, analyst  
dashboard.UserGroupLandingPageAction.page.name=/home
```

Remember the following when configuring the `portal-ext.custom.properties` file for landing pages:

- ♦ A home page is designated when there is a `/home` page is defined for a user group, community or organization. Or when another page URL is explicitly set in the properties file.
- ♦ If `page.name` and `landing.page` property values are not specified, they default to `/home`.
- ♦ The property file is evaluated line-by-line and in order. The last successful match wins, so define the broadest evaluations first, and then narrow down to the most specific cases.
- ♦ If the specified URL cannot be found, the Dashboard shows a 404 error.
- ♦ If a user is not a member of a specified group, community or organization; the last valid match determines the user's home page.

While these configurations can be made complex, the simplest configuration would be to make sure each user group, community and organization in your Dashboard configuration has an existing `/home` page. Then specify the order of evaluation in the properties file, and set properties for group priority and ignore lists for communities and organizations.

Refer to the `portal-ext.properties` file for additional information and examples. For more information about the `portal-ext.custom.properties` file, refer to [Section 3.9, "Understanding Portal Properties Files," on page 43](#).

To configure the home page for a users:

- 1 In the Operations Center console, configure your users, groups communities and organizations.

For information on creating users and groups, see “[User and Group Accounts](#)” in the *Novell Operations Center 5.0 Security Management Guide*.

- 2 Verify there is a home page for user groups, communities or organizations as required.

For information on adding pages, see [Section 5.3, “Adding Pages,” on page 72](#). For information on importing pages, see [Section 5.9, “Importing and Exporting Data and Configurations from User Groups, Communities, or Organizations,” on page 88](#).

- ◆ Navigate to the page and note the URL. The value you will need is the part of the URL after the last slash (/).
- ◆ To change the URL for any page, set the *Friendly URL*:
 1. From the Dashboard, click *Welcome* and select *Control Panel*.
 2. Under *Portal*, select *User Groups, Communities, or Organizations*.
 3. Click *Actions* next to the desired group, community or organization; and select *Manage Pages*.
 4. Under *Pages*, create or select the page to be the default home page for the group.
 5. Click *Page*, then type */home* or the new page name URL in the *Friendly URL* field.

If changing pages for the */home* URL, modify the *Friendly URL* for the existing */home* page before you set the URL as */home* on the new page.
 6. Click *Save*.

Repeat these steps for each group, organization, or community that you wish to configure.

- 3 Configure the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file.

- 3a Add the following required lines as an initial declaration of comma delimited entries:

```
login.events.post=com.mosol.liferay.authenticator.LoginPostAction,  
com.liferay.portal.events.DefaultLandingPageAction
```

login.events.post=com.mosol.liferay.authenticator.LoginPostAction is required for Operations Center authentication.

com.liferay.portal.events.DefaultLandingPageAction takes the user to the guest home page if no other option is defined.

Optionally, add any of the following lines in the desired evaluation order:

com.mosol.liferay.portal.events.UserGroupLandingPageAction redirects the user to his group's home page on login. Then define additional properties related to user group in [Step 3b](#).

com.mosol.liferay.portal.events.OrganizationLandingPageAction redirects the user to his community's home page on login. Then define additional properties related to user group in [Step 3b](#).

- 3b Add and define any of the additional properties to customize.

- ◆ To customize by user group:

dashboard.UserGroupLandingPageAction.group.order=groupName1,groupName2,groupName3 lists (no spaces) of all groups in order of priority in case a user belongs to more than one.

dashboard.UserGroupLandingPageAction.page.name=/home is the landing page URL to use if the user does not belong to any of the listed groups.
- ◆ To customize by community:

community.landing.page=/home is the community home page.

community.landing.path=/web specifies the start of the URL to use for the landing page.

community.landing.ignoreList=Guest,TestCommunity comma delimited list (no spaces) of communities to ignore.

- ♦ To customize by organization:

organization.landing.page=/home is the organization home page.

organization.landing.path=/web specifies the start of the URL to use for the landing page. /web is the location for public pages and /group is the location for private pages.

organization.landing.ignoreList=Engineers,Finance is a comma delimited list (no spaces) of organizations to ignore.

- 4 Restart the Dashboard server for the changes to take affect. For more information, see [Section 2.3.1, "Starting the Dashboard," on page 27.](#)

5.9 Importing and Exporting Data and Configurations from User Groups, Communities, or Organizations

Various data can be imported and exported for communities using LAR files. Import and export options include pages, portlet configurations, permissions, themes, and categories.

Even though a LAR file might contain all data from a community, a partial import can be accomplished by disabling the data you do not wish to import.

IMPORTANT: Imported pages overwrite all existing pages.

To import pages:

- 1 Do one of the following:
 - ♦ If you are importing to a community, go to a page that has a *My Communities* portlet.

- ◆ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*, *User Groups*, or *Organizations*.
- 2 Click *Actions* next to the desired group, organization, or community and select *Manage Pages*.
- 3 Select the *Public Pages* or *Private Pages* tab.
- 4 Select the *Export / Import* tab.
- 5 Select the *Import* tab.

The screenshot shows the 'My Communities' interface for editing pages in the 'New Products' community. It features several tabs: 'Public Pages', 'Private Pages', and 'Settings' in the first row; 'Pages', 'Look and Feel', and 'Export / Import' in the second row; and 'Export' and 'Import' in the third row. The 'Import' tab is active. Below the tabs, there is a text prompt: 'Import a LAR file to overwrite the selected data.' This is followed by a text input field and a 'Browse...' button. Underneath, a section titled 'What would you like to import?' contains a list of checkboxes: 'Pages' (checked), 'Delete Missing Pages' (unchecked), 'Portlets' (checked), 'Setup' (checked), 'Archived Setups' (checked), 'User Preferences' (unchecked), 'Data' (checked), 'Permissions' (unchecked), 'Theme' (unchecked), and 'Categories' (unchecked). A 'More Options >>' link is located below the list. At the bottom of the form is an 'Import' button.

- 6 Click the *Browse* button to select the LAR file to import. then

WARNING: Imported pages replace all existing pages in the community.

- 7 Specify the data to import by selecting the desired check box options.
- 8 Click *Import*.

To export pages:

- 1 Do one of the following:
 - ◆ If you are exporting to a community, go to a page that has a *My Communities* portlet.

- ◆ Click *Welcome* and select *Control Panel*.
Under *Portal*, select *Communities*, *User Groups*, or *Organizations*.
- 2 Click *Actions* next to the desired community and select *Manage Pages*.
- 3 Select the *Public Pages* or *Private Pages* tab.
- 4 Select the *Export / Import* tab.
- 5 Select the *Export* tab.

The screenshot shows the 'My Communities' interface. At the top, there is a header 'My Communities' and a sub-header 'Edit Pages for Community: New Products'. Below this, there are three tabs: 'Public Pages', 'Private Pages', and 'Settings'. Under 'Public Pages', there are three sub-tabs: 'Pages', 'Look and Feel', and 'Export / Import'. Under 'Export / Import', there are two sub-tabs: 'Export' and 'Import'. The 'Export' tab is selected. Below the tabs, there is a text input field containing 'New_Products-201010251739.lar'. Below the input field, there is a section titled 'What would you like to export?' with several checkboxes: 'Pages' (checked), 'Portlets' (checked), 'Setup' (checked), 'Archived Setups' (checked), 'User Preferences' (unchecked), 'Data' (checked), 'Permissions' (unchecked), 'Theme' (unchecked), and 'Categories' (unchecked). Under 'Data', there is a 'Range:' section with three radio buttons: 'All' (selected), 'Date Range' (with a help icon), and 'Last' (with a dropdown menu showing '12 Hours'). At the bottom, there is a 'More Options >>' link and an 'Export' button.

- 6 Specify the name of the LAR file where the data is to be saved.
- 7 Specify the data to export including pages, portlets, permissions, theme and categories by selecting the desired check box options.
- 8 To export, click *Export*.

6 Adding Content to a Page Using Portlets

Any dashboard page can be customized by changing the layout, selecting themes for the “look and feel”, adding content via portlets, and adding navigation or other functionality to the page. These changes are saved between sessions. The various actions that a user can take depend on the permissions assigned. For more information about permissions, see [Section 3.12, “Granting or Denying Access to Portlets,”](#) on page 47.

Because some portlets rely on receiving information from other sources on the Internet, such as the RSS portlets, users must have Internet access in order for them to work properly.

Content from other sources can be added to the Dashboard using portlets. The Dashboard leverages portlets that are JSR-168 compliant and any third-party portlets built with this standard can be deployed in the Dashboard. For more information, see [Section 3.10, “Deploying Portlets to the Dashboard,”](#) on page 44.

The following sections list the various portlets or web applications that are available; and describe how to add them, share them as well as add various other features to a page:

- ♦ [Section 6.1, “Understanding Available Content via Portlets,”](#) on page 91
- ♦ [Section 6.2, “Adding Portlets,”](#) on page 94
- ♦ [Section 6.3, “Understanding Sharing Portlets,”](#) on page 97
- ♦ [Section 6.4, “Adding a Site Map, Breadcrumbs, or Navigation to a Page,”](#) on page 97
- ♦ [Section 6.5, “Adding a Refresh Feature to Pages,”](#) on page 99
- ♦ [Section 6.6, “Integrating Reports from External Reporting Tools Using iFrames,”](#) on page 99

6.1 Understanding Available Content via Portlets

The Dashboard ships with many default portlets that can be added to a Web page to add content to the page. You can disable portlets or restrict their use based on user permissions. For more information, see [Section 3.12, “Granting or Denying Access to Portlets,”](#) on page 47.

The Dashboard includes:

- ♦ A library of standard Liferay portlets, including basic page navigation features.

For Liferay 5.2 documentation and more information on their portlet library, go to <http://www.liferay.com/documentation/liferay-portal/5.2/> (<http://www.liferay.com/documentation/liferay-portal/5.2/>). Some portlets might require the installation of third-party software; check the software documentation for more information. For support for any third-party portlets, including Liferay portlets, contact the vendor that provided the portlet.
- ♦ Operations Center portlets that expose Operations Center Service Management content, such as alarms

For information, see [Chapter 7, “Exposing Operations Center Content,”](#) on page 103.

[Table 6-1](#) lists Operations Center portlets, followed by default Liferay portlets:

Table 6-1 *Dashboard Portlets*

Category	Description/Available Portlets
Operations Center	<p>Operations Center portlets allow you to surface Service Management data:</p> <ul style="list-style-type: none">◆ Alarms◆ Chart Builder◆ Charting◆ Element Properties◆ Layout◆ Operations Center server Profiles◆ Navigation◆ Performance◆ Properties Table◆ Public End User View◆ Refresh◆ Root Cause◆ Search◆ Show Impacted◆ Starter◆ Status◆ Summary◆ Tree Map <p>For more information, see Chapter 7, “Exposing Operations Center Content,” on page 103 and Chapter 8, “Configuring Operations Center Portlets,” on page 133.</p>
Collaboration	<p>Collaboration portlets facilitate interaction among coworkers:</p> <ul style="list-style-type: none">◆ Blogs◆ Blogs Aggregator◆ Calendar◆ Message Boards◆ Recent Bloggers◆ SMS Text Messenger◆ Wiki

Category	Description/Available Portlets
Community	<p>Community portlets allow the sharing of information among people with a similar skill, interest, or task to perform:</p> <ul style="list-style-type: none"> ◆ Bookmarks ◆ Directory ◆ Invitation ◆ My Communities ◆ Page Comments ◆ Page Ratings <p>For more information on communities, see Section 5.2, "Creating and Maintaining Communities," on page 68.</p>
Content Management	<p>Content Management System (CMS) portlets help manage documents and images and publish content. Some add navigation functionality to a page.</p> <ul style="list-style-type: none"> ◆ Asset Publisher ◆ Breadcrumb ◆ Categories Navigation ◆ Document Library and Document Library Display ◆ Image Gallery ◆ Navigation ◆ Nested Portlets ◆ Polls Display ◆ Recent Documents ◆ Site Map ◆ Tags Navigation ◆ Web Content Display, List and Search ◆ XSL Content <p>For generic instructions on how to add a portlet to a page as well as instructions for adding a site map, breadcrumbs and navigation to a page, see Chapter 6, "Adding Content to a Page Using Portlets," on page 91.</p>
Finance	<p>Finance portlets include tools and informative content:</p> <ul style="list-style-type: none"> ◆ Currency Converter ◆ Loan Calculator
News	<p>News portlets display or share news information:</p> <ul style="list-style-type: none"> ◆ Alerts ◆ Announcements ◆ RSS

Category	Description/Available Portlets
Sample	<p>Sample portlets include:</p> <ul style="list-style-type: none"> ◆ Hello Velocity ◆ Hello World ◆ IFrame ◆ Web Proxy
Tools	<p>Tools portlets include the following tools and functionality:</p> <ul style="list-style-type: none"> ◆ Dictionary ◆ Language ◆ Network Utilities ◆ Password Generator ◆ Quick Note ◆ Search ◆ Sign In ◆ Software Catalog ◆ Translator ◆ Unit Converter
Wiki	<p>Wiki portlets allow users to easily add content to a Web page:</p> <ul style="list-style-type: none"> ◆ Wiki ◆ Wiki Display

6.2 Adding Portlets

Portlets can be added to pages. When you add a portlet to a community, generally the objects in the portal belong to that community only. For example, if a Message Board is added to the Support community, all of the topics created through that portlet belong to the Support community only.


The admin portlets (Enterprise Admin, Organization Admin, and Location Admin) are the exception because they span all communities and thus can be accessed through multiple communities.

- ◆ [Section 6.2.1, “Adding a Portlet,” on page 95](#)
- ◆ [Section 6.2.2, “Moving Portlets on a Page,” on page 96](#)
- ◆ [Section 6.2.3, “Configuring Portlet “Look and Feel,” on page 96](#)


6.2.1 Adding a Portlet

To add a portlet:

- 1 Go to *Welcome* and click *Add Application*.



- 2 Click a category to open a list of portlets.
For Service Management portlets, expand *Operations Center*.




- 3 To add a portlet to the page, do one of the following:
 - ◆ Click *Add* next to a portlet.
 - ◆ Click the portlet name and drag to the desired position on the page.
- 4 Add more portlets as needed.

6.2.2 Moving Portlets on a Page

In the dashboard, new portlets are automatically added at the top of the page above any existing portlets (unless you've strategically placed it when dragging over from Add Applications onto the page). A portlet can be moved to a new location depending on the page layout. For example, if the page layout has two columns, a portlet can be moved from the left column into the right column.

To reposition a portlet to a different location on the same page:

- 1 Click the portlet title bar and drag the portlet to a new location on the page:





6.2.3 Configuring Portlet “Look and Feel”


After a portlet is added to a page, you can configure its appearance including:

- General portlet settings such as title and disable borders
- Text, background, and border styles
- Background styles
- Margin and padding
- Custom css for advanced styling
- WAP Styling

In addition to appearance, some portlets have other configuration options.

To configure the look and feel for a portlet:

- 1 Click  *Options*, and select  *Look and Feel*.



- 2 Select one of the following tabs:
 - ♦ **Portlet Configuration:** Set portlet title options, disable borders, and link portlet URLs to pages:
 - ♦ **Text Styles:** Define styles for portlet text including alignment, line height, and spacing.
 - ♦ **Background Styles:** Set the color for the portlet background.
 - ♦ **Border Styles:** Set color and spacing styles for the portlet border.
 - ♦ **Margin and Padding:** Set margin and spacing for the portlet.
 - ♦ **Advanced Styling:** Define any custom css.
 - ♦ **WAP Styling:** Set options for the portlet when viewed by a wireless device.
- 3 Make any changes, then click *Save*.

6.3 Understanding Sharing Portlets



Some portlets allow information to be shared among dashboard users. For users to access a portlet, the following is required:

- ♦ The user must be assigned a role that has permission to the portlet.
- For more information, see [Chapter 11, “Portal and Community Permissions,” on page 215](#).
- ♦ The portlet must be on a public page or a page governed by one of the roles the user is assigned.


6.4 Adding a Site Map, Breadcrumbs, or Navigation to a Page

Site Map, Breadcrumb, and Navigation portlets are available to add navigational features to any the dashboard page.



To add a site map, breadcrumb, or a navigation to a page:

- 1 Go to *Welcome* and click *Add Application*.
 - 2 To add a Site Map portlet, do the following:
 - ♦ Under *Content Management*, click and drag *Site Map* to a location on the page.
 - ♦ Click  *Options* and select  *Configuration* to configure the following options on the Site Map portlet:
 - Root layout:** The page where the site map begins.
 - Display depth:** The number of child levels displayed on each page.
- Click *Save*.

The Site Map portlet adds a hierarchical listing of all pages in a community:





3 To add a Breadcrumb portlet, do the following:

- Under *Content Management*, click and drag *Breadcrumb* to a location on the page.
 - Click  *Options* and select  *Configuration* to configure the following options on the Site Map portlet:
 - **Display Style:** Select 1 for plain type or 2 for bold type.
- Click *Save*.

The Breadcrumb portlet displays the current page, plus links back to the preceding parent pages:



4 To add a Navigation portlet, do the following:

- Under *Content Management*, click and drag *Navigation* to a location on the page.
 - Click  *Options* and select  *Configuration* to configure the Site Map portlet:
 - **Bullet style:** Varies the lines between the pages in the list.
 - **Display style:** Indicates how the page names are presented.
- Click *Save*.



The Navigation portlet displays a listing of links to all pages within the current portlet.



6.5 Adding a Refresh Feature to Pages

Add the Refresh portlet to the Web page in order to allow the user to refresh the page on demand or by scheduling a refresh as designated intervals.

To refresh data in a the dashboard Web page:

- 1 Go to *Welcome* and click *Add Application*.
- 2 Under *Operations Center*, click and drag *Refresh* to a location on the page.
- 3 Click *Refresh* in the Refresh portlet to reload the page.
- 4 To schedule automatic refresh, do the following:
 - 4a Click  *Options* and select  *Preferences* to configure the Refresh portlet.
 - 4b Select the desired interval to schedule the page refresh in the *Refresh Interval* list. Select *None* to disable automatic refresh.
 - 4c Click *Save*.

If a scheduled refresh is set, the date and time of the last refresh, as well as a countdown to the next refresh, are displayed.

If a scheduled refresh interval is not set, then a message displays, indicating the automatic refresh option is disabled.


6.6 Integrating Reports from External Reporting Tools Using iFrames

If you have reports from third-party reporting tools that include Operations Center data, you can now access and run these through the dashboard pages using iFrames.


This section explains how to integrate reports from Crystal Reports as an example. Sample reports leveraging Operations Center data are available in `/OperationsCenter_install_path/database/examples/mosql`. For more information about using Business Objects Crystal Reports for queries and reporting of Operations Center data, see the [Novell Operations Center 5.0 SQL Views Guide](#).

To integrate with Business Objects Crystal Reports from the Dashboard:


- 1 Add the *iFrame* portlet to a page.
Select *iFrame* under *Sample* in *Add Applications*. For more information on adding portlets to a page, see [Section 6.2.1, "Adding a Portlet," on page 95](#).
- 2 Click the configuration link inside the portlet.



- 3 Specify the URL of the reporting program in the Source URL field.



- 4 Specify other settings for the portlet as required.
- 5 Click *Save*.
- 6 Click the *Return to Full Page* link to display the page from the reporting tool.



7 Select and view the desired report.

The screenshot shows a web browser window displaying a report titled "Service Level Agreement Catalog" for Novell. The report is generated by Crystal Reports 2008. The report date is 9/28/2009 and the report time is 2:06:14PM. The report content is as follows:

Agreement	Objective	Element	Objective Definition
Silver on Portal	Availability - On	DB application Portal	During On periods, ensure 90% availability over 1 hour aligned and threshold condition Critical, Weight = 1
Silver on	Downtime	DB application	During On periods, allow a maximum of 2 minutes of

7 Exposing Operations Center Content

The data that can be viewed in a Operations Center portlet depends on the permissions the user has in Operations Center. This is true for all portlets except the [Public End User View portlet](#), which can be configured so guest users can see limited status information about selected elements. For more information about permissions in Novell Operations Center Script Debugger, see the [Novell Operations Center 5.0 Security Management Guide](#).

Review the following sections to

- ♦ [Section 7.1, “Understanding the Operations Center Portlets,” on page 103](#)
- ♦ [Section 7.2, “Configuring Portlet View Links,” on page 107](#)
- ♦ [Section 7.3, “Configuring Home and Starting Elements,” on page 108](#)
- ♦ [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,” on page 110](#)
- ♦ [Section 7.5, “Creating Custom Right-Click Menus,” on page 112](#)
- ♦ [Section 7.6, “Configuring URL Linking for the Layout Portlet,” on page 121](#)
- ♦ [Section 7.7, “Viewing Source Data for Charts,” on page 122](#)
- ♦ [Section 7.8, “Setting Technical Configurations for Operations Center Portlets,” on page 123](#)
- ♦ [Section 7.9, “Installing Third-Party Software,” on page 131](#)
- ♦ [Section 7.10, “Troubleshooting Operations Center Portlets,” on page 132](#)

7.1 Understanding the Operations Center Portlets

Operations Center portlets are [added to a page](#) in the same way as other content. Configuring the look and feel of these portlets is also the same as for other portlets. For more information, see [Chapter 6, “Adding Content to a Page Using Portlets,” on page 91](#).

- ♦ Some data, such as alarms, can be viewed in real time with [automatic updates](#) from the Operations Center server. Operations that are performed on alarms on the Operations Center console can also be performed in the Dashboard.
- ♦ Element status data from Operations Center is available in the Dashboard using Operations Center portlets. For some portlets, you can select the Operations Center server as the source for displayed content.
- ♦ Some portlets support custom condition/severity colors as set in the Operations Center console.
- ♦ The defaults for Operations Center portlets are read from an XML file that can be modified.
- ♦ For some portlets to display correctly, a third-party plug-in must be installed on the user’s computer.

Review the following sections to understand data types in Operations Center and how to set options for portlets:

- ◆ [Section 7.1.1, “Understanding Data Types in Operations Center,” on page 104](#)
- ◆ [Section 7.1.2, “Understanding Custom Colors in Portlets,” on page 106](#)
- ◆ [Section 7.1.3, “Setting Options for a Portlet,” on page 107](#)

7.1.1 Understanding Data Types in Operations Center

[Table 7-1](#) lists the types of data and views from Operations Center that can be displayed in the Dashboard:

Table 7-1 *Novell Operations Center Portlets by Portlet Type*

Type	Description/Available Portlets
Information Summary	<p>Information overview for an element, showing various types of related data based on preferences. Included data can include element properties, list of parents and children, alarm summary, alarms, layout/relationship diagrams, root cause and show impacted information. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Information <ul style="list-style-type: none"> For more information, see Configuring the Information Portlet (page 147).
Element Status	<p>Visual representation of the current condition of elements. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Status <ul style="list-style-type: none"> For more information, see Configuring the Status Portlet (page 178). ◆ Information <ul style="list-style-type: none"> For more information, see Configuring the Information Portlet (page 147). ◆ Public End User View <ul style="list-style-type: none"> For more information, see Configuring the Public End User View Portlet (page 169).
Properties	<p>Properties specified for an element. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Properties Table <ul style="list-style-type: none"> For more information, see Configuring the Properties Table Portlet (page 165). ◆ Element Properties <ul style="list-style-type: none"> For more information, see Configuring the Element Properties Portlet (page 147). ◆ Information <ul style="list-style-type: none"> For more information, see Configuring the Information Portlet (page 147).

Type	Description/Available Portlets
Alarms	<p>Both historical alarms and real-time alarms in either a full view or summary view. Operations can also be performed for real-time alarms in the full view. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Summary <p>For more information, see Understanding the Summary Portlet (page 180).</p> ◆ Alarms <p>For more information, see Configuring the Alarms Portlet (page 134).</p> ◆ Information <p>For more information, see Configuring the Information Portlet (page 147).</p> <p>Visual representation of alarms, both historical and real time. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Tree Map <p>For more information, see Configuring the Tree Map Portlet (page 181).</p>
Root cause/ Show impacted	<p>The cause of an element's state or the elements affected by the selected element. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Root Cause <p>For more information, see Configuring the Root Cause Portlet (page 170).</p> ◆ Show Impacted <p>For more information, see Configuring the Show Impacted Portlet (page 175).</p> ◆ Information <p>For more information, see Configuring the Information Portlet (page 147).</p>
Performance Charts	<p>A chart of performance metrics, SLA data, availability and downtime. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Charting <p>For more information, see Configuring a Performance Portlet (page 157).</p> ◆ Performance <p>For more information, see Configuring a Performance Portlet (page 157).</p>
Layout/ Relationships	<p>Visual representation of element relationships. Related portlets include:</p> <ul style="list-style-type: none"> ◆ Layout <p>For more information, see Configuring the Layout Portlet (page 153).</p> ◆ Information <p>For more information, see Configuring the Information Portlet (page 147).</p>

Type	Description/Available Portlets
Navigation/ Element Selection	<p>Related portlets include:</p> <ul style="list-style-type: none"> ◆ Navigation <p>Displays the hierarchy from the Operations Center server with an indicator for status and controls the elements shown on the other portlets on the page.</p> <p>For more information, see Configuring the Navigation Portlet (page 156).</p> ◆ Starter <p>Displays an element with an indicator for status and controls the elements shown on the other portlets on the page.</p> <p>For more information, see Configuring the Starter Portlet (page 176).</p> ◆ Search <p>Locate elements in Operations Center and display properties for the found elements. Found elements can also be selected to control the elements shown in other portlets on the page.</p> <p>For more information, see Search Portlet (page 171).</p>
Service Level Agreements	<p>Related portlets include:</p> <ul style="list-style-type: none"> ◆ SLA Compliance <p>For more information, see Section 9.2, “Configuring the SLA Compliance Portlet,” on page 185.</p> ◆ SLA Status <p>For more information, see Section 9.3, “Configuring the SLA Status Portlet,” on page 192.</p>
Administrative	<p>Related portlets include:</p> <ul style="list-style-type: none"> ◆ Operations Center Server Profiles <p>For more information, see Section 7.8.4, “Selecting an Alternate Operations Center Server Connection,” on page 126.</p>

7.1.2 Understanding Custom Colors in Portlets

As an option, users can select a custom color palette used for condition and severity colors in the Operations Center console. Only some portlets support this custom color selection.

The following portlets support custom color settings:

- ◆ Alarms
- ◆ ChartBuilder (all examples except the Element Property Gauge)
- ◆ Charting
- ◆ Information (Alarms list only)
- ◆ Performance
- ◆ Search
- ◆ SLA Status & Compliance Portlets (Compliance and Charts tabs only)
- ◆ Summary
- ◆ Tree Map (Element name labels only)

There are no configurations required to the portlets. However, current users must logout and re-login to see new severity colors after settings are changed in the Operations Center console.



For more information on custom color settings, see “[Managing Condition/Severity Colors](#)” in the *Novell Operations Center 5.0 User Guide*.

7.1.3 Setting Options for a Portlet

Data is displayed using components within portlets. Some of the components allow data to be updated automatically when the Operations Center server receives new data.

Options for data content and formatting are set within each portlet.

To set options for any portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Make changes to the options.
- 3 Click *Save*.



7.2 Configuring Portlet View Links

Nearly all Operations Center portlets, those that contain actual data from a Operations Center server, include multiple views within the portlet. When available and enabled, these views are accessible to the user via an *Actions* link at the top of the portlet:

- ◆ *Performance*
- ◆ *Alarms*
- ◆ *Layout*
- ◆ *Treemap*
- ◆ *Root Cause*
- ◆ *Impacted*
- ◆ *Properties*
- ◆ *Properties Table*
- ◆ *Chart Builder*

The *Actions* link and the portlet view links settings are only applicable for the above portlets.

To disable/enable the Actions and view links for a portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Advanced* tab.

3 Click the *Common* tab.

Portlet Information
Portlet Namespace: `mo_alarms_WAR_ManagedObjectsPortlets_INSTANCE_7qEe_`
Operations Center Server Profile: Display the Operations Center server profile icon.

Element Menu
Current Menu:

Portlet View Links
Hide these links: Actions Menu
 Home (on portlet's home page)
 Performance
 Alarms
 Layout
 Treemap
 Root Cause
 Impacted
 Properties
 Properties Table
 Chart Builder

Element Link Action
Portlet Tag: A unique tag for this portlet. Reference this tag from other portlets to drive this portlet.
Tags of Portlets to Drive: Enter tag(s) of portlet(s) that this portlet drives. Separate multiple tags with commas.

- 4 To hide the *Actions* menu link at the top of the portlet, select the *Actions Menu* option under *Portlet View Links*.
- 5 To add a *Home* link at the top of the portlet, deselect the *Home* option under *Portlet View Links*. By default this option is selected and a *Home* link does not appear on the portlet.
- 6 To hide any of the portlet links, select the undesired options under *Portlet View Links*. Select from *Performance*, *Alarms*, *Layout*, *Treemap*, *Root Cause*, *Impacted*, *Properties*, *Properties Table*, and *Chart Builder*.
By default these options are deselected and all links appear on the portlet.
- 7 Click *Save*.

The options for components vary depending on the portlet.

In addition to showing links to components in the main section of the portlet, links to other components can also be available through a right-click context menu. The right-click context menu can be used to add [functionality](#) to portlets.

7.3 Configuring Home and Starting Elements

The home element (starting element) for each user is set within the user or group account settings in the Operations Center console. The home element is used to populate element-based Service Management portlets if a starting element has not been defined for that portlet.

Starting elements can be changed “on the fly” for most portlets when Navigation Mode, or drive functionality, is configured. For more information, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,”](#) on page 110.


- ♦ [Section 7.3.1, “Changing the User’s Default Home Element,”](#) on page 109
- ♦ [Section 7.3.2, “Configuring Starting Elements for Portlets,”](#) on page 110

7.3.1 Changing the User's Default Home Element

The *Home* setting is found on the user's or group's property page in the Operations Center console. By default, all users start with the *Enterprise* element. The elements that a user can view depend on the user's permissions in Operations Center.

To set a user's or group's default starting element:

- 1 From the Operations Center console, in the *Explorer* pane, expand *Enterprise > Administration > Security > Users* (or *Groups*).
- 2 Right-click the user or group, then click *Properties*.
- 3 Select the *User* (or *Group*) property page.



The *Home* field shows the default starting element.



- 4 To select a new starting element click *Browse*.


Consider the user's or group's permissions for specific elements in the hierarchy when selecting the new starting element.

7.3.2 Configuring Starting Elements for Portlets

By default, portlets use the user's home element as their starting element.

To change the starting element for a portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Elements* tab.



- 3 Do one of the following:
 - ♦ Use the *Search* tab to search for elements. The search is by name and allows for the use of wildcards (*).
 - ♦ Use the *Navigate* tab to select an element from the hierarchy by clicking + and – to expand and contract the list.

7.4 Using Navigation Mode to Drive Multiple Portlets

By default, the “drive” or “navigation mode” configuration allows you to select an element in one portlet and automatically update content in other portlets (when available) on the same page. Or, you can configure the portlet to drive one or more specific portlets on the page.

For example, if we have a Navigation, Element Properties, Alarms and Information portlets on the same Dashboard page; when we click the *Administration > Server* element in the Navigation portlet, the other portlets (Element Properties, Alarms, and Information) update to show related information about the *Server* element.

The following sections describe more about enabling drive functionality as well as configuring only specific portlets to drive.

- ♦ [Section 7.4.1, “Understanding Drive Configuration,” on page 110](#)
- ♦ [Section 7.4.2, “Tagging Portlets to Drive Specific Portlets,” on page 111](#)

7.4.1 Understanding Drive Configuration

By default, the following portlets are used to drive other portlets without any configuration:

- ♦ [Navigation](#)
- ♦ [Search](#)
- ♦ [Starter](#)
- ♦ [Status](#)

When enabled, the following portlets can be used to drive other portlets:

- ♦ [Alarms](#)

- ◆ [Information](#)
- ◆ [Layout](#)

To enable or disable “drive” or “navigation mode”, see the configuration instructions for the portlet type you are configuring in [Chapter 8, “Configuring Operations Center Portlets,” on page 133](#).





Note that not all portlets can be driven. For example, the Navigation, Search, Starter and Performance portlets are among the portlets that cannot be driven.

In addition, an element’s [right-click context menu](#) can be used to perform this same drive functionality and update content on the page. For instructions on creating right-click menus, continue to [Section 7.5.1, “Adding Right-Click Context Menus,” on page 112](#).

7.4.2 Tagging Portlets to Drive Specific Portlets

In order to contain the drive functionality to specific portlets on a page, each driven portlet must be tagged, and then referenced by the driving portlet.

To enable specific portlets to be driven by element selection:

- 1 To set up identifiers for the portlets to be driven, do the following for each portlet to be driven:
 - 1a Click  *Options* and select  *Preferences*.
 - 1b Click the *Advanced* tab, then click the *Common* tab.
 - 1c Under *Element Link Action*, in the *Portlet Tag* field, specify a unique name for the portlet.
For example, if it is the Alarms portlet, you might enter Alarms.
 - 1d Click *Save*, then exit the preferences for the portlet.
- 2 To setup a portlet to drive the above portlet(s), do the following for the portlet that is the driver:
 - 2a Click  *Options* and select  *Preferences*.
 - 2b Verify the portlet is setup to “drive” other portlets. In most, this requires the Navigation Mode option to be selected.
For specific instructions, see the portlet’s configuration section in [Chapter 8, “Configuring Operations Center Portlets,” on page 133](#).
 - 2c Click the *Advanced* tab, then click the *Common* tab.
 - 2d Under *Element Link Action*, in the *Tags of Portlets to Drive* field, specify the identifier/tags set up in the previous procedure.
For example to reference and drive the Alarms portlet in the example setting from the previous step, we might enter Alarms.
When referencing more than one portlet, use commas to separate the entries without any extra spaces.
 - 2e Click *Save*, then exit the preferences for the portlet.
- 3 The driver portlet (Step 2) now drives the referenced portlets (Step 1) when an element is clicked.

7.5 Creating Custom Right-Click Menus


The following sections cover the creation of right-click menus in any portlet that supports right-click menu functionality. Menus can be used to access URLs, issue JavaScript commands, view other portlet, or perform Operations Center server-side operations.

- ◆ [Section 7.5.1, “Adding Right-Click Context Menus,” on page 112](#)
- ◆ [Section 7.5.2, “Accessing URLs from Right-Click Menu,” on page 115](#)
- ◆ [Section 7.5.3, “Issuing JavaScript Commands from Right-Click Menu,” on page 117](#)
- ◆ [Section 7.5.4, “Adding Portlet View Links to Right-Click Menus,” on page 118](#)
- ◆ [Section 7.5.5, “Performing Operations Center Server-Side Operations from Right-Click Menu,” on page 119](#)

7.5.1 Adding Right-Click Context Menu

A right-click context menu can be created, edited and used in any portlet that supports the right-click menu functionality (any portlet that has the *Advanced* > *Common* tab in its Preferences).

Figure 7-1 Root Cause Portlet with Right-Click Context Menu



When right-click context menus are implemented, right-clicking an element on the portlet can:

- ◆ [Update the contents of Operations Center portlets on a page to show the selected element's information](#)
- ◆ [Open additional components](#), such as the *Alarms* view, *Layout* view, *Root Cause* view, *Performance* view, and so on
- ◆ [Open any URL](#) and send context-sensitive information to the URL
- ◆ [Execute custom JavaScript commands](#)
- ◆ [Execute operations](#)



The right-click context menu functionality is currently available on the Operations Center Navigation, Search, Show Impacted, Status, and Root Cause portlets.

- ♦ [“Creating a New Menu” on page 113](#)
- ♦ [“Editing an Existing Menu” on page 115](#)

Creating a New Menu


While it is possible to create multiple menus for a portlet, only one menu can be active at a time. Multiple menu options can be grouped together on the right-click context menu under a submenu if a grouping title is specified.

To create a right-click menu:


- 1 Click  *Options* and select  *Preferences*.
- 2 If creating a context menu to drive page content, verify the portlet is enabled for “drive” or Navigation Mode functionality.

For specific information about this configuration option, see the portlet’s configuration section in [Chapter 8, “Configuring Operations Center Portlets,” on page 133](#).

- 3 Click the *Advanced* tab, then select the *Common* tab.



- 4 Click *Create New Menu*.



5 Specify a unique name for the menu, then click *Create*.

If the name already exists, a message indicates the menu failed to save. After a name has been entered, it cannot be changed.

Wizard: Menu

Menu Name:

Menu Title: Displays as the menu title.

Use element name for the title of the menu. The Menu Title above is ignored.

Drive Page Content: Display a menu item to drive the contents on the page with the selected element.

Menu Item Text:

Component Links: Display a menu item for each common component (i.e. Root cause, Impacted, Layout, etc).

Category Name: Leave blank if you do not want to group items under a category name.

Custom Links:

Name	URL		
JavaScript Example	This is an example showing JavaScript	Edit	Remove
Search Using Google	http://www.google.com	Edit	Remove

Category Name: Leave blank if you do not want to group items under a category name.

Operations:

Name	Operation
No records found.	

Category Name: Leave blank if you do not want to group items under a category name.

6 Do one of the following to determine the menu item text that displays in the right-click menu:

- ◆ Enter text in the *Menu Title*.
- ◆ Select the *Use element name for the title of the menu* check box to show the element's name as the menu name.

If neither option is specified, no title is displayed.

7 To provide a menu option to update other portlets on the page:

7a Under *Drive Page Content*, select the *Display a menu item to drive the contents on the page with the selected element* check box.

7b Specify a name for the menu option in the *Menu Item Text* box.

For information about driving other portlets, see [Section 7.3.2, "Configuring Starting Elements for Portlets," on page 110](#), and be sure the portlet is enabled for "drive" or Navigation mode as mentioned in [Step 2 on page 113](#).

8 To provide menu options that open common portlet components; such as Charting , Performance, Layout, Treemap, Root Cause, Impacted, and Properties Table:

8a Under *Component Links*, select the *Display a menu item for each common component* check box.

8b Specify a name under which to group these menu options in the *Category Name* box.

For information about portlet component links, see [Section 7.2, "Configuring Portlet View Links," on page 107](#).



- 9 Enter options to [open URLs](#), [execute JavaScript commands](#), or [execute operations](#) by adding custom links and operations.
- 10 To group the menu items, enter a title for the group in the associated *Category Name* option.
- 11 Click *Save*.

Editing an Existing Menu

After you have created a menu, it is available for use and editing in all portlets that support the right-click menu functionality. If you make changes to the menu in one portlet, those changes are applicable for all instances of the menu in all portlets.

To later edit or remove operations, return to the *Common* tab under *Advanced*. Under *Current Menu*, select the operation name and then click *Edit Menu*. To remove a link, click *Remove*.

To edit a menu:



- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Advanced* tab, then select the *Common* tab.
- 3 From the *Current Menu* drop-down list, select a different menu if required, then click *Edit Menu*.
A window opens with the menu options.
- 4 Make changes, then click *Save*.

7.5.2 Accessing URLs from Right-Click Menus

URLs can be included as menu options in portlet right-click context menus. These links can open any URL and send context sensitive information to it. This is a powerful way of launching third-party applications and allowing for context-sensitive display (such as display a remedy ticket associated with a particular element).

Parameters can be passed from the Dashboard to the new URL to customize what appears in the Web page that the URL opens. Parameters can be based on the element from which the user accessed the right-click content menu and can include the DName, element name, and a specified element property, which are all stored in the Operations Center server. For more information on elements including DName and properties, see [Viewing Element Properties](#) in the [Novell Operations Center 5.0 User Guide](#).

To create a menu option to a URL and optionally pass parameters:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Advanced* tab, then select the *Common* tab.
- 3 Do one of the following:
 - ♦ Select the desired existing menu from the *Current Menu* list, and click *Edit Menu*.
 - ♦ Click *Create New Menu* to create a new menu.

For basic steps about defining a new menu, see [“Creating a New Menu” on page 113](#).

Specific steps for defining a custom link are detailed in the remaining steps.

- 4 Under *Custom Links*, click *Create New Link*.

- 5 To specify basic link information to create the menu link and to set properties for the browser window that the URL will load in, do the following:

The screenshot shows a dialog box titled "Wizard: Menu Link". It has several sections:

- Menu Option Name:** A text box containing "Search Using Google". To its right is the instruction: "Enter the name to appear on the menu."
- Link URL:** A text box containing "http://www.google.com". To its right is the instruction: "Enter the full web address including protocol to use. For example, 'http://www.netiq.com'."
- JavaScript:** A checkbox labeled "Enable JavaScript for the URL above." which is unchecked. To its right is a button labeled "Replacement Keys". Below this is the instruction: "Enter JavaScript in the Link URL field to execute when the end user clicks the menu item. Activating this feature disables the Link Options below."
- Configuration Options:**
 - Target:** A text box containing "_blank". To its right is the instruction: "Enter '_blank' to open in a new window."
 - Parameters:** An empty text box. To its right is the instruction: "A comma delimited list of parameters used to set window settings. For example, 'toolbar=no,location=no'."

- 5a Specify the name of the option in the *Menu Option Name* field.
- 5b Specify a fully qualified URL for the link in the *Link URL* field.
- 5c Leave the *Enable JavaScript for the URL above* check box deselected.
- 5d Specify the name of the browser window to open the URL in the *Target* field.
Enter `_blank` if it is to always open in a new window.
- 5e Specify a comma delimited list of parameters to control the size and location of the window in the *Parameters* field.
For example, `toolbar=no,location=no`.
- 6 (Optional) To hide the URL link when a specific property value exists, select the *Show this link only when the name-value below is matched* check box.

This section contains a checked checkbox with the label "Show this link only when the name-value below is matched." Below the checkbox are two text boxes: "Property Name:" and "Property Value:". To the right of the "Property Value:" box is the instruction "Enter a regular expression."

Specify the property name and property value expression in the fields provided.

- 7 (Optional) To set up parameters that are passed by the URL, do the following as necessary:

This section contains four unchecked checkboxes, each with a "Parameter:" text box and an explanatory instruction:

- Send the element dname as a parameter to the url. Parameter: [text box]. Parameter to be used for the dname. For example, use "dname" to create a parameter of "dname=[dname value]".
- Send the element name as a parameter to the url. Parameter: [text box]. Parameter to be used for element name. For example, enter "name" to create a parameter of "name=[element name value]".
- Send an element property as a parameter to the url. Parameter: [text box]. Parameter to use for this match. For example, "property" creates a parameter of "property=[property value]".
- Append an element property to the url. This does not pass element property name as the parameter. Operations Center Property: [text box]. Property to match in Operations Center.

- ◆ To pass the element DName to the URL, select the *Send the element dname as a parameter to the URL* check box.
Specify the parameter expression that is appended to the URL in the field provided (such as `dname=dname_value`).
- ◆ To pass the element name to the URL, select the *Send the element name as a parameter to the URL* check box.
Specify the parameter expression that is appended to the URL in the field provided (such as `name=name_value`).


- ♦ To pass an element property name/value pair to the URL, select the *Send an element property as a parameter to the URL* check box and/or to append the URL with an element property, select the *Append element property to the url* check box.

Then specify:

- ♦ The parameter name to be used for the passed or appended property in the *Parameter* field.
- ♦ The property name to match for in the element's properties in Operations Center in the *Operations Center Property* field.

8 Click *Create*.

The new link definition displays under *Custom Links*:



7.5.3 Issuing JavaScript Commands from Right-Click Menus

JavaScript commands can be executed by menu options in portlet right-click context menu. Links for JavaScript commands are created and edited the same way as [URL links](#).


To create a right-click menu that issues a JavaScript command:

- 1 Click *Options* and select *Preferences*.
- 2 Click the *Advanced* tab, then select the *Common* tab.
- 3 Do one of the following:
 - ♦ Select the desired existing menu from the *Current Menu* list, and click *Edit Menu*.
 - ♦ Click *Create New Menu* to create a new menu.

For basic steps about defining a new menu, see [“Creating a New Menu” on page 113](#).
- 4 Under *Custom Links*, click *Create New Link*.
- 5 To specify basic link information to create the menu link and to set properties for the browser window that the URL will load in, do the following:
 - 5a Specify the name of the option in the *Menu Option Name* field.
 - 5b Specify the JavaScript command, including any parameters in the *Link URL* field.

- 5c Select the *Enable JavaScript for the URL above* check box.

For help in determining the parameters for the JavaScript to use elements and properties of an element from Operations Center, click *Replacement Keys*.



The keys shown in the table below may be used to replace items in the JavaScript.

Key	Replacement Value
\$element.name\$	Element's name
\$element.dname\$	Element's dname
\$element.identity\$	Element's identity
\$element.identity-b64\$	Element's identity base 64 encoded
\$element.condition\$	Element's condition
\$element.className\$	Element's class name
\$portlet.namespace\$	The namespace of the Portlet (unique identifier for the Portlet)
\$menu.trigger\$	The id attribute of the DOM element that this menu is triggered

For example, the following "alert('\$element.name\$');" will result in the element's name being shown in a browser popup when the menu item is clicked

- 5d Specify the name of the browser window to open the URL in the *Target* field.

Enter `_blank` if it is to always open in a new window.

- 5e Specify a comma delimited list of parameters to control the size and location of the window in the *Parameters* field.

For example, `toolbar=no,location=no`.

- 6 Click *Create* to save the menu.

The new JavaScript command definition displays under *Custom Links*.

7.5.4 Adding Portlet View Links to Right-Click Menus

Links that open other components (different portlets) can be included in portlet right-click context menus. When selected, the new portlet uses the element from which the right-click menu was accessed as the starting element.

The options for configuring the components links on the right-click context menu are available when [creating a new menu](#) or [editing an existing menu](#). For basic steps about defining a new menu, see "Creating a New Menu" on page 113.

To add component links, select the *Display a menu item for each common component* check box under *Component Links*. Each component name then appears on the right-click context menu.

7.5.5 Performing Operations Center Server-Side Operations from Right-Click Menus


Server-side operations defined in Operations Center can be added to portlet right-click context menus. For more information on operations, including how to define operations on the Operations Center console, see *Modifying Element and Alarm Menus* in the *Novell Operations Center 5.0 Server Configuration Guide*.

Custom operations can be added as the Dashboard right-click menu options. However, they require custom development to interface with the Dashboard. Contact [Novell Support \(http://support.novell.com\)](http://support.novell.com) for more information.

To create a menu option that runs a server-side operation:

- 1 In Operations Center console, create or note the operation you wish to access from the Dashboard.

Take note of the *Menu Text* specified for the operation definition.



For details on creating operations, see *Modifying Element and Alarm Menus* in the *Novell Operations Center 5.0 Server Configuration Guide*.


- 2 On the Dashboard portlet, on the portlet title bar, click (Options) and select click (Preferences).

Click the *Advanced* tab, then click the *Common* tab.

For basic steps about defining a new menu, see [“Creating a New Menu” on page 113](#).


Specific steps for defining the operations menu option are detailed in the remaining steps.

3 Click *Create New Menu*.




To edit the menu later, use *Edit Menu*.

4 In the Menu dialog box, enter the menu name, then click *Create*.



5 In the Wizard dialog box, under *Operations*, click *Create New Operation*. The Menu Operation dialog box displays.



6 Specify the name of the menu option in the *Menu Option Name* field.

This is the name that will show in the menu.

7 Enter `MO.NoUIOperation` in the *Operation* field.

8 Specify any parameters in the *Parameters* field using the following syntax:

```
opname=OperationMenuText, opcommand=
```

where *OperationMenuText* is the menu text for the operation created in Operations Center.

9 Because this is a server-side operation, leave the *This Operation is a client executed operation* check box deselected.

The type of operation (client side or server side) is defined when the operation is created on the Operations Center console. By default, the Dashboard assumes that the operation is server side and runs on the Operations Center server.

10 Select the *Display only when the property name-value pair below is matched* check box if the operation is to be unavailable if the *Property Name* and *Value* specified cannot be validated with the current element.

(Optional) Specify a *Property Name* and *Property Value* to be matched.


11 Click *Create*. The new operation displays in the Menu's Operations listing.

Operations:	Name	Operation	
	Perform Log Test	MO.NoUIOperation	<input type="button" value="Edit"/> <input type="button" value="Remove"/>

- 12 Click *Save* on subsequent dialogs to finish creating the new menu.
- 13 Verify the newly created menu is selected under *Currently selected menu* in *Preferences* for the *Advanced > Common* tab.

Click *Save* and exit *Preferences*.

The new menus are available in the right-click context menus for the portlet.



7.6 Configuring URL Linking for the Layout Portlet

Clicking an element in the Layout portlet can open a Web page using a fully qualified URL, instead of the expected behavior of drilling into the element's hierarchy.

URL linking requires the definition of a custom *layoutFollowURL* property for these elements in the Operations Center console. Instead of manually creating and defining this property on each individual element, use Metamodel Property Pages to create the new property, then dynamically associate the property page with elements through behavior models via class, or directly to behavior models using match expressions.

To configure navigation to a URL from a Layout portlet element:

- 1 Decide how you will propagate the new property via *Administration > Metamodel* features. Metamodel classes, behavior models and property pages are defined in the Operations Center console.

Choose one of the following:


- ♦ Attach a new property page to a new (or existing) Behavior Model that uses matching rules for selecting elements.
- ♦ Attach a new property page to a new (or existing) Behavior Model that is attached to a Class which can be assigned to elements.

For information about Service Model classes, behavior models and property pages, see [“Defining Classes, Behavior Models, and Property Pages”](#) in the *Novell Operations Center 5.0 Service Modeling Guide*.

- 2 When creating the new *layoutFollowURL* property for the desired Property Page, do the following:

- 2a Click the *Create a Property* icon and name the property *layoutFollowURL*.

The property must be named *layoutFollowURL* for this feature to function correctly.



2b Specify a fully qualified URL as desired.

In the illustration example above, we've defined a computed field property that uses a script expression to append the URL with the element name.

3 In the Dashboard Layout portlet, click the element to open the URL.

7.7 Viewing Source Data for Charts

Various charting-type portlets contain the ability to access the raw data used to generate the chart:

- ◆ Charting

For more information about the Charting portlet, see [Section 8.2, "Configuring the Charting Portlet," on page 144](#).

- ◆ Information, Charts tab

For more information about the Information portlet, see [Section 8.4, "Configuring the Information Portlet," on page 147](#).

- ◆ Performance


For more information about the Performance portlet, see [Section 8.7, "Configuring a Performance Portlet," on page 157](#).

- ◆ Chart Builder

For more information about Chart Builder portlet, see [Chapter 10, "Chart Builder Portlet," on page 199](#).

Clicking the *d* link or using the Chart Data option displays source data used to generate the chart as shown in [Figure 7-2 on page 123](#).

Figure 7-2 Source Data for Chart



7.8 Setting Technical Configurations for Operations Center Portlets

The following sections provide details on technical configurations that can be made to configure or increase performance for Dashboard portlets:

- ◆ [Section 7.8.1, “Configuring Default Alarms Limits Returned from the Operations Center Server,”](#) on page 124
- ◆ [Section 7.8.2, “Configuring Performance Data Point Retrieval from the Operations Center Server,”](#) on page 124
- ◆ [Section 7.8.3, “Configuring Regular Expression Look Up for the Performance Portlet,”](#) on page 125
- ◆ [Section 7.8.4, “Selecting an Alternate Operations Center Server Connection,”](#) on page 126
- ◆ [Section 7.8.5, “Scheduling Portlets,”](#) on page 126
- ◆ [Section 7.8.6, “Automatic Data Updates with Push Technology,”](#) on page 131

7.8.1 Configuring Default Alarms Limits Returned from the Operations Center Server

There is a default limit of 1000 historical alarms, outages, and breaches when using the SLA or Alarms portlets. This limit is set on the Operations Center server. If there are more historical alarms (Alarms portlet) or outages/breaches (SLA Compliance portlets) and you want them to be accessible via the dashboard, this limit needs to be appropriately set using the `HyperQuery.NumPoints.SizeLimit` property.

To increase the maximum number of alarms that are returned from the Operations Center server:

- 1 Open the `/OperationsCenter_install_path/config/Formula.custom.properties` file in a text editor.
If the `Formula.custom.properties` file does not exist, create it. For more information about the `Formula.custom.properties` file, see [“Making Custom Changes”](#) in the *Novell Operations Center 5.0 Server Configuration Guide*.
- 2 Add the following property and customize the value:
`HyperQuery.NumPoints.SizeLimit=30000`
- 3 Stop and restart the Operations Center server for the changes to take effect.

7.8.2 Configuring Performance Data Point Retrieval from the Operations Center Server

The amount of data points returned for a performance chart can increase or decrease rendering performance. The Operations Center server uses an algorithm to determine how many data points to return for the Performance portlet when charting raw data. Using a setting in the `mo-settings.xml` file, you can configure the aggressiveness of the algorithm to reduce the number of data points used to draw a line while preserving the natural line shape.

This setting is only applied when the Performance portlet is charting raw data.

To configure the level of data point retrieval for the Performance portlet:

- 1 Stop the Dashboard.
For information on stopping the Dashboard, see [Section 2.3.2, “Stopping the Dashboard,”](#) on [page 27](#).
- 2 Edit the `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEB-INF/mo-settings.xml` file to add the following:

```
<entry>
<string>performance.charts.ldpredict.rpd.epsilon</string>
<string>desiredvalue</string>
</entry>
```

Where *desiredvalue* is the level of aggressiveness between 0 and 1.0. Set to 0 to turn the algorithm off and return all data points. We recommend increasing the value slowly, if at all, in increments of .05. The default value is 0.1.
- 3 Start the Dashboard.
For information on starting the Dashboard, see [Section 2.3.1, “Starting the Dashboard,”](#) on [page 27](#).

7.8.3 Configuring Regular Expression Look Up for the Performance Portlet

Optionally, you can setup a list of regular expressions to be available for look up when configuring the Performance portlet. This requires adding code to the `globals.custom.xml` file.

NOTE: The regular expressions list is only loaded from the `globals.custom.xml` when the Performance portlet is created. If you wish to use this list with existing Performance portlets, you'll need to recreate the portlet reload new or modified look up lists.

To create a regular expression lookup list for Performance Portlet configurations:

- 1 Open the `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEBINF/data/globals.custom.xml` file in a text editor.

If the `globals.custom.xml` file does not exist, create it.

- 2 Modify the `globals.custom.xml` file to incorporate the following code:

```
<globals>
  <data>
    <components>
      <component>
        <name>performance</name>
        <preferences>
          <entry>
            <string>regularExpressions</string>
            <map>
              <entry>
                <string>expression_name</string>
                <string>regular_expression</string>
              </entry>
            </map>
          </entry>
        </preferences>
      </component>
    </components>
  </data>
</globals>
```

If creating a new `globals.custom.xml` file, you will need to paste in the entire example.

If an entry for the `performance` component already exists, paste in only the code for the `regularExpressions` entry, which goes inside the `<preferences>` tag.

Replace `expression_name` with a name for the regular expression entry and `regular_expression` with the actual regular expression code.

- 3 Add as many entries as needed inside the `<map>` tag to fully populate the look up list:

```
<map>
  <entry>
    <string>expression_name</string>
    <string>expression</string>
  </entry>
  <entry>
    <string>expression2_name</string>
    <string>expression2</string>
  </entry>
</map>
```

- 4 Save the file.
- 5 Restart the Dashboard.



For more information about starting and stopping the Dashboard, see [Section 2.3, "Starting and Stopping the Dashboard,"](#) on page 26.


7.8.4 Selecting an Alternate Operations Center Server Connection

By default, all Operations Center portlets retrieve data from the default Operations Center server. Within some portlets, it is possible to poll a different Operations Center server. In this case, a different server profile is selected for the portlet.

Server profiles are used by the Alarms, Charting, Element Properties, Information, Layout, Navigation, Performance, Properties Table, Root Cause, Search, Show Impacted, Starter, Status, Summary, and Tree Map portlets. For information about creating a server profile, see [Section 3.8, “Creating Operations Center Server Profiles,”](#) on page 41.

To select a server profile for a portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Advanced* tab, then select the *Common* tab.
- 3 From the *Select the Operations Center server profile where this portlet retrieves its data* option, select the server that serves up Operations Center data for the portlet.



The default establishes a connection with the default Operations Center server.

For steps on creating a new Operations Center server connection, see [Section 3.8, “Creating Operations Center Server Profiles,”](#) on page 41.

- 4 Because each server profile has an icon associated with it, select to display this icon on the portlet to help distinguish the server from which data is retrieved by selecting the *Display the Operations Center server profile icon* check box.

When the server profile icon is enabled to be displayed, hovering over this icon while viewing the content of a portlet shows the profile name in a tooltip.

- 5 Click *Save*.

7.8.5 Scheduling Portlets

Cached versions portlet reports can improve performance when viewing portlets by updating the data at scheduled intervals only; not upon every request to view the portlet. Note that the data displayed in a scheduled portlet is no longer real-time because it is serving up.

The following sections describe how to define schedules for portlets:

- ♦ [“Understanding Portlet Scheduling”](#) on page 127
- ♦ [“Defining the Schedule”](#) on page 128
- ♦ [“Forcing a Manual Refresh of Cached Data”](#) on page 129
- ♦ [“Understanding Cron Strings”](#) on page 129

Understanding Portlet Scheduling

Scheduled reports are useful when information needs to be published and shared with users on a regular basis. For example, a report could be scheduled to run every Monday morning at 6:00 a.m. so that when users log in first thing Monday morning, it is quick and easy to view the latest status.

A portlet can be scheduled to run hourly, daily, weekly, monthly; or a custom schedule specified by a Cron string, such as “every Friday at noon”, or “every weekday and 9:30 am”, or even “every 5 minutes between 9:00 am and 10:00 am on every Monday, Wednesday, and Friday”.

Only some portlets have the Scheduling feature. When available, a *Scheduling* tab will be available under the *Advanced* tab in *Preferences*.

Note the following important aspects and tips on portlet scheduling:

- ◆ Portlet data displays in Real-Time until a schedule is set and applied.
- ◆ Cached versions created by a schedule only save and cache data for the primary (home) view of the portlet. The extent of the cached data does vary by portlet. However, if a portlet contains links to other views, reports or portlets; these other pages are serving up live data, not cached data.
- ◆ When scheduling reports, we recommend running the report before scheduling it, so that a cached version is available in the portal page for the lapse of time before the next scheduled report generation.
- ◆ Subsequent changes to the preferences of a scheduled portlet does not take effect until the next scheduled run. To regenerate the report immediately after changes in *Preferences*, go to *Advanced > Scheduling* and click *Run Now*.
- ◆ Schedule portlets to run as infrequently as possible, as long as it provides meaningful data. For example, if you only care about data accurate to the hour, there is no need to schedule it more than once per hour. Also consider how long a scheduled portlet is taking to run so that the next scheduled run doesn't overlap with an existing job for the same portlet. And lastly, minimize the overall load by scheduling portlets in a way that it will not stress the server. For example, with larger reports that run once a day, schedule them during non-peak hours and stagger the start times.
- ◆ To confirm a schedule is defined and active for a portlet, go to *Preferences > Advanced > Scheduling*. If active, the following type of status information displays including the last time the portlet was run and the next scheduled time.



This portlet is currently scheduled.

This portlet is run every week on monday at the 10 hour and 0 minute.

Scheduled portlet job name: Scheduled_Portlet__mo_slaStatus_WAR_ManagedObjectsPortlets_INSTANCE_IpO2_

Last fire time: No information currently available.

Next fire time: Mon Nov 29 10:00:00 EST 2010

Schedule creation time: Thu Nov 25 10:36:09 EST 2010

- ◆ Scheduled portlets use the associated Operations Center Profile user account. In most cases, this is default profile, which uses the admin account.

When the scheduling job is kicked off in the background, it first logs in with the user account specified in the profile. If the user account is deleted, scheduled jobs fail. Therefore, it is recommended that you set up a profile with a common user that is not associated with a any specific person, so that this user account is always present in the system.

To change the Operations Center profile for the portlet, go to *Preferences > Advanced > Common*, and select a different profile. For information about creating new profiles, see [Section 3.8, “Creating Operations Center Server Profiles,” on page 41](#).

- ♦ The time a scheduled portlet takes to run can vary. To determine how long it is taking, look for the following debug category messages in the `formula.trc` log file:

```
time.log4j.category.com.mosol.portlet.schedule.PortletJob
```

An entry is logged when the job is kicked off and when it logs in and out of Operations Center. Calculate the time difference between the login and logout to find how long the job is running to produce the report.

For information about the `formula.trc` file, see [“Understanding Trace Logs and Content”](#) in the *Novell Operations Center 5.0 Server Configuration Guide*.

Defining the Schedule

To define a schedule for a portlet:

- 1 Click *Options* and select *Preferences*, then select *Advanced*.
- 2 Click *Scheduling*.

The report scheduler displays:


- 3 Select one of the *Select Schedule* radio buttons: *Hourly*, *Daily*, *Weekly*, *Monthly*, or *Cron*.

Depending on the time frame selected, specify the calendar day of the week, day of the month, hour, and minute values, or specify a cron string.

For more information about cron strings, see [“Understanding Cron Strings” on page 129](#).

- 4 Click *Start Schedule* to begin using the schedule.

The report is now generated based on the selected schedule and the following message screen displays:



It provides some basic information about the schedule, when it was created, when it last ran and when it is expected to run again. This screen also provides two possible actions:

- ♦ **Run Now:** Forces the portlet to re-cache its data immediately.
- ♦ **Stop:** Unschedules the portlet.

At this time, the Job Name is used internally only by the scheduling mechanism and should be left as the default, which uses the unique portlet namespace.

5 Click *Save*.


If you exit *Preferences* without clicking *Save*, your changes are lost.

Forcing a Manual Refresh of Cached Data

To define a schedule for a portlet:

- 1 Click *Options* and select *Preferences*, then select *Advanced*.
- 2 Click *Scheduling*.

The following message screen displays:



- 3 Click *Run Now* to generate a new version of the cached report.

Understanding Cron Strings

Cron expressions are strings that are actually made up of seven sub-expressions, that describe individual details of the schedule. These sub-expression are separated with white-space, and represent:

1. Seconds

2. Minutes
3. Hours
4. Day-of-Month
5. Month
6. Day-of-Week
7. Year (optional)

Cron expressions use the following special characters:

- ◆ * Use to select all values within a field.
- ◆ ? Use to declare no specific value. Use to specify something in one of the two fields in which the character is allowed, but not the other. For example, to fire on a particular day of the month (say, the 10th), but it doesn't matter what day of the week it happens to be, put "10" in the day-of-month field, and "?" in the day-of-week field.
- ◆ - Use to specify ranges within a sub-expression. For example, "10-12" in the hour field means "the hours 10, 11 and 12".
- ◆ , Use to specify additional values. For example, "MON,WED,FRI" in the day-of-week field means "the days Monday, Wednesday, and Friday".
- ◆ / Use to specify increments. For example, "0/15" in the seconds field means "the seconds 0, 15, 30, and 45". And "5/15" in the seconds field means "the seconds 5, 20, 35, and 50". You can also specify '/' after the " character - in this case " is equivalent to having '0' before the '/'. '1/3' in the day-of-month field means "fire every 3 days starting on the first day of the month".
- ◆ L (Last) has different meaning in each of the two fields in which it is allowed. For example, the value "L" in the day-of-month field means "the last day of the month" - day 31 for January, day 28 for February on non-leap years. If used in the day-of-week field by itself, it simply means "7" or "SAT". But if used in the day-of-week field after another value, it means "the last occurrence of that day in the month" - for example "6L" means "the last friday of the month". When using the 'L' option, it is important not to specify lists, or ranges of values, as you'll get confusing results.
- ◆ W (Weekday) Use to specify the weekday (Monday-Friday) nearest the given day. As an example, if you were to specify "15W" as the value for the day-of-month field, the meaning is: "the nearest weekday to the 15th of the month". So if the 15th is a Saturday, the trigger fires on Friday the 14th. If the 15th is a Sunday, the trigger fires on Monday the 16th. If the 15th is a Tuesday, then it fires on Tuesday the 15th. However if you specify "1W" as the value for day-of-month, and the 1st is a Saturday, the trigger fires on Monday the 3rd, as it doesn't 'jump' over the boundary of a month's days. The 'W' character can only be specified when the day-of-month is a single day, not a range or list of days.
- ◆ # Use to specify "the nth" XXX day of the month. For example, the value of "6#3" in the day-of-week field means "the third Friday of the month" (day 6 = Friday and "#3" = the 3rd one in the month). Other examples: "2#1" = the first Monday of the month and "4#5" = the fifth Wednesday of the month. Note that if you specify "#5" and there is not 5 of the given day-of-week in the month, then no firing occurs that month.

Table 7-2 Examples of Chron Expressions for Scheduling

Schedule fires...	Cron Expression
Every 5 minutes.	0 0/5 * * * ?
Every 5 minutes, at 10 seconds after the minute (i.e. 10:00:10 am, 10:05:10 am, etc.).	10 0/5 * * * ?
Exactly at 10:30, 11:30, 12:30, and 13:30, on every Wednesday and Friday.	0 30 10-13 ? * WED,FRI
Every half hour between the hours of 8 am and 10 am on the 5th and 20th of every month. Note that the trigger will NOT fire at 10:00 am, just at 8:00, 8:30, 9:00 and 9:30.	0 0/30 8-9 5,20 * ?
At 10:15am on the last Friday of every month.	0 15 10 ? * 6L

For additional information on the format of the Cron string, consult the [Quartz Enterprise Job Scheduler Web site \(http://www.quartz-scheduler.org/docs/tutorials/crontrigger.html\)](http://www.quartz-scheduler.org/docs/tutorials/crontrigger.html).

7.8.6 Automatic Data Updates with Push Technology

Using push technology, the Dashboard can receive data updates as they occur in the Operations Center server instead of having the Dashboard request updates on a regularly scheduled interval. When enabled, push technology ensures that data is refreshed in the Dashboard only when an event occurs, such as a state change.

Push technology is available for the following portlets: Alarms (except SLA alarms), Information, Layout, Navigation, Properties Table, Starter, Status and Tree Map. By default, these portlets are enabled to refresh content automatically from the Operations Center server. This feature can be disabled in the configuration settings for each portlet (or any portlet that utilizes these portlets as views/links).

Push technology can be enabled globally for all portlets in the Operations Center Dashboard Configuration Manager. See [Section 2.2.5, “Configuring the Dashboard and Operations Center,” on page 20](#). The settings within each portlet override the global setting in the Operations Center Dashboard Configuration Manager.

7.9 Installing Third-Party Software

Some of the portlets in the Dashboard rely on plug-ins or third-party software to display properly.


- ◆ [Section 7.9.1, “SVG Viewer,” on page 132](#)
- ◆ [Section 7.9.2, “Flash Player,” on page 132](#)

7.9.1 SVG Viewer

The Layout and Chart Builder portlets rely on an Adobe* SVG Viewer to render images properly. Note that as Chart Builder SVG rendering is not supported on Mozilla* Firefox, users must select Flash, PNG, or JPG before accessing data through the Chart Builder portlet.

If the Adobe SVG plug-in is not installed on your machine, you are prompted to install it when you first access the Layout portlet. Follow the on-screen instructions to download and install the SVG plug-in.

Figure 7-3 SVG Plug-in Not Installed Message



To properly view Chinese fonts in the report created from the Layout portlet, the Chinese version of the Adobe SVG Viewer must be installed on your machine.

Adobe SVG plug-ins can be downloaded from the [Adobe SVG Viewer download area \(http://store1.adobe.com/svg/viewer/install/\)](http://store1.adobe.com/svg/viewer/install/).

7.9.2 Flash Player

Portlet charts can be rendered in 3D by using the Flash format. However, the Adobe Flash* player does not support a 64-bit Internet Explorer (IE) browser, so when you configure any charting portlet to display Flash graphics, the charts do not display properly in 64-bit Internet Explorer.

You are prompted to install the Flash player. However, if you manually install the player and restart browser, the 64-bit Internet Explorer still asks you to install the plug-in.

Refer to [Flash Player support on 64-bit operating systems \(http://www.adobe.com/cfusion/knowledgebase/index.cfm?id=6b3af6c9\)](http://www.adobe.com/cfusion/knowledgebase/index.cfm?id=6b3af6c9) for more information on this issue.

7.10 Troubleshooting Operations Center Portlets

- ♦ [Section 7.10.1, “Operations Center server Unavailable,” on page 132](#)

7.10.1 Operations Center server Unavailable

The Operations Center server is currently not accessible. message displays when the Operations Center server is not available. Contact your Operations Center administrator to see when the server is available again. After the Operations Center server is back up, you must log out of the Dashboard and log back in to the Dashboard to see current data.

8 Configuring Operations Center Portlets

The following sections contain descriptions and details about Operations Center portlets:

- ◆ [Section 8.1, “Configuring the Alarms Portlet,” on page 134](#)
- ◆ [Section 8.2, “Configuring the Charting Portlet,” on page 144](#)
- ◆ [Section 8.3, “Configuring the Element Properties Portlet,” on page 147](#)
- ◆ [Section 8.4, “Configuring the Information Portlet,” on page 147](#)
- ◆ [Section 8.5, “Configuring the Layout Portlet,” on page 153](#)
- ◆ [Section 8.6, “Configuring the Navigation Portlet,” on page 156](#)
- ◆ [Section 8.7, “Configuring a Performance Portlet,” on page 157](#)
- ◆ [Section 8.8, “Configuring the Properties Table Portlet,” on page 165](#)
- ◆ [Section 8.9, “Configuring the Public End User View Portlet,” on page 169](#)
- ◆ [Section 8.10, “Configuring the Root Cause Portlet,” on page 170](#)
- ◆ [Section 8.11, “Search Portlet,” on page 171](#)
- ◆ [Section 8.12, “Configuring the Show Impacted Portlet,” on page 175](#)
- ◆ [Section 8.13, “Configuring the Starter Portlet,” on page 176](#)
- ◆ [Section 8.14, “Configuring the Status Portlet,” on page 178](#)
- ◆ [Section 8.15, “Understanding the Summary Portlet,” on page 180](#)
- ◆ [Section 8.16, “Configuring the Tree Map Portlet,” on page 181](#)

8.1 Configuring the Alarms Portlet

The alarms portlet shows a detailed listing of alarms that allows you to click and open the alarm's properties. A total alarm count indicates the total number of alarms for the element while severity indicators show the number of alarms for each severity. As in the Operations Center console, alarm operations can be performed (when available), alarm filters can be created and applied, and alarm data can be exported to an Excel or PDF file.

Figure 8-1 Alarm Portlet

Severity	Element	Date/Time	ID	Identifier
MINOR	100.42.83.44	August 9, 2012 11:36:13 AM EDT	1243126	e@a167e89@a167e89:0.0:0
MINOR	102.11.23.52	August 8, 2012 6:54:27 PM EDT	1239832	e@a164556@a164556:0.0:0
MINOR	120.455.27.77	August 1, 2012 3:02:47 PM EDT	1205154	e@a16484a@a16484a:0.0:0
MINOR	100.355.23.12	August 1, 2012 12:22:49 PM EDT	1204522	e@a16484f@a16484f:0.0:0
MINOR	120.37.578.56	August 8, 2012 7:31:54 PM EDT	1239969	e@a164853@a164853:0.0:0
MINOR	100.87.03.122	August 9, 2012 4:14:53 PM EDT	1244163	e@a164a78@a164a78:0.0:0
MAJOR	102.59.99.128	July 23, 2012 6:15:42 PM EDT	1160874	Attempt to login as root from
MINOR	102.55.009.11	August 3, 2012 10:51:39 AM EDT	1214023	e@a164b8e@a164b8e:0.0:0
MINOR	100.500.39.05	August 9, 2012 10:17:03 AM EDT	1242827	e@a164cad@a164cad:0.0:0
MINOR	100.399.27.84	August 8, 2012 1:00:41 PM EDT	1238458	e@a164c2e@a164c2e:0.0:0
MINOR	100.500.34.66	July 31, 2012 12:56:36 PM EDT	1199310	e@a164c54@a164c54:0.0:0
INFORMATIONAL	102.44.856.12	August 9, 2012 11:26:26 AM EDT	1243088	e@a6368a0@a6368a0:0.0:1
MINOR	102.899.90.11	August 9, 2012 1:57:18 PM EDT	1243645	e@a6368a0@a6368a0:0.0:0
MINOR	100.755.12.11	July 27, 2012 11:58:01 AM EDT	1179633	e@a636832@a636832:0.0:0
MINOR	100.35.69.102	August 8, 2012 2:15:42 PM EDT	1238746	e@a463112a@a463112a:0.0:0

The Alarms portlet returns a maximum number of alarms based on a property set on the Operations Center server. For instructions on configuring this property, see [Section 7.8.1, "Configuring Default Alarms Limits Returned from the Operations Center Server,"](#) on page 124.

The Alarms Portlet can also be used to set the starting element for other portlets on the Web page, similar to the [Navigation portlet](#). To configure the Alarms portlet to drive other portlets using Navigation, see [Step 3 on page 138](#) and [Section 7.4, "Using Navigation Mode to Drive Multiple Portlets,"](#) on page 110.

The Alarms portlet is also available as a view from other Operations Center portlets including Summary, Layout, Performance, Tree Map, Element Properties, Properties Table, Show Impacted, Root Cause, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Alarms* from any of these portlets.

[The following sections cover various Alarm portlet functionality:]

- ◆ [Section 8.1.1, "Viewing Alarms,"](#) on page 135
- ◆ [Section 8.1.2, "Performing Alarms General Configuration,"](#) on page 137
- ◆ [Section 8.1.3, "Applying and Creating Alarm Filters,"](#) on page 138
- ◆ [Section 8.1.4, "Performing Alarm Operations,"](#) on page 144

8.1.1 Viewing Alarms

The actual alarms shown in the portlet/view depend on various factors set in the configuration options:

- ◆ **Alarm Type:** Displays the following types of real-time events:

- alarms
- audit events
- service level breaches
- service level metrics

For more information on alarms, see [Alarms View](#) in the *Novell Operations Center 5.0 User Guide*.

For more information on service level breaches and metrics, see the *Novell Operations Center 5.0 Service Level Agreement Guide*.

- ◆ **Severity:** Displays alarms of varying severities.

For more information on alarm severities, see [Viewing Alarm Severity](#) in the *Novell Operations Center 5.0 User Guide*.

- ◆ **Alarm Filters:** Limits the number of alarms shown. You can check to see which alarm filters are enabled.

To view the *Alarms* listing:

- 1 Do any of the following:

- ◆ Click a severity color indicator to hide or show matching alarms.
- ◆ Click any column heading to sort the rows in the table in either ascending or descending order.
- ◆ Use the arrow or number buttons to move through data in either the alarm properties or the alarms listing.

- ◆ Double-click any alarm to open a list of all alarm properties in a new window.
If the Alarm Properties window becomes hidden behind the main browser window when another alarm is clicked, switch back to the Alarm Properties window to view properties on the new alarm.



The screenshot shows a Mozilla Firefox browser window with the address bar displaying `http://engdemo:9080/ManagedObjectsPortlets/managedobjects/action/compon`. The main content area displays a table with the following data:


Name	Value
Description	Current Response is 98.5%
Affected element	safari
status	OPEN
Message	Current Response is 98.5%
Response	98.5
hostname	reston
class	TEST
severity	OK
period	day
date	Mon Nov 16 10:38:30 EST 2009
msg	Current Response is 98.5%
id	133
Source	safari
originating_tec_hostname	safari
Status	OPEN
source	safari
Class	TEST
originating_event_id	32

- ◆ Click *Refresh* to refresh the data.
- ◆ Click the Excel or PDF icons to export the alarm data to an Excel or PDF file.
If the file download window does not open, check your browser settings to see if pop-up dialog boxes are blocked.

8.1.2 Performing Alarms General Configuration

To configure preferences for the Alarms portlet:

- 1 Click  *Options* and select  *Preferences* and update settings on the *General* tab:



The screenshot shows the 'Alarms' configuration page with the 'General' tab selected. The page has a top navigation bar with 'Alarms', 'Element', and 'Advanced' tabs. Below this is a sub-navigation bar with 'General' and 'Filters' tabs. The 'General' tab contains the following settings:

- Alarm Table Width: 100% (with a tooltip: "Enter width as a percentage, such as "100%".")
- Alarm Table Height: auto (with a tooltip: "Enter height in pixels, such as "300px".")
- Filter by Severity: (with a tooltip: "A comma separated list of alarm severities to not show. For example, "CRITICAL,MAJOR" filters out all CRITICAL and MAJOR alarms. Leave empty to show all.")
- Alarm Columns: (with a tooltip: "A comma separated list of alarm columns to display. Leave empty to show all alarm columns.")
- Sort Alarms by: Severity (with a tooltip: "The alarm column to use for the initial sort of alarms.")
- Alarms per Page: 20 (with a tooltip: "Number of alarms per page.")

Below these settings are several checkboxes:

- Enable alarm selectors and filter options.
- Sort alarms in ascending order by default.
- Highlight alarm rows with severity color.
- Enable alarm operations.
- Show PDF/Excel export links
- Refresh portlet when updates occur.
- Pause alarms when selecting or driving alarms.
- Enable navigation mode. Click an alarm to drive the content of other portlets on the page.
- Enable historical alarms. Show the following type of alarms by default:

At the bottom of the checkbox section, there are two dropdown menus: 'Real-time' and 'Alarms'. At the very bottom are 'Save' and 'Reset' buttons.

For other portlets, the *Alarms* tab is found under the *Advanced* tab.

- 2 Specify the following options:

Alarm Table Width: The size of the table expressed as a percentage of the portlet page. Defaults to 100%.

Alarm Table Height: The number of rows displayed at one time in the table; expressed in pixels. Defaults to 300.

Filter by Severity: Specify a comma separated list of severities (such as "CRITICAL,MINOR") to hide alarms with specific severity levels. Alarms with matching severities will not show in the alarms portlet. Leave this field empty to show all alarms. In addition to this option, you can also filter alarms by severity using the colored bar when viewing the alarms.

Alarm Columns: Specify a comma separated list of alarm columns to display (and hide all other columns). Leave blank to display all columns. Columns available to display are dependent on the source of the alarms.

If alarms are currently displayed in the portlet, click the browse (...) button to select columns from a list based on a sampling from the current alarms. If no alarms are currently displayed in the portlet, the selector is unable to show columns to select from. Use the left and right arrow buttons to move a column name between the Available list and the Selected list. Use the up and down arrows to reorder column names.

Sort Alarms by: Specify a column name to use as a sort key for displayed alarms. Severity is the default sort key. You can also change the sort key while viewing the alarms table by clicking a column heading.

Alarms per Page: Specify the maximum number of alarms to show on each page.

3 Select or deselect the following check box options:

Show alarm selectors and filter options: Selected by default. Shows alarm selectors at the top of the alarms portlet. This includes alarm type drop-down lists and update/pause buttons to apply, alarm filters by severity and options to select or unselect all alarms. Deselect the check box to hide these options.

Sort alarms in ascending order by default: Selected by default. Deselect the check box to initially sort in descending order. Use this option or click column headings when viewing the table to change the sort order.

Highlight alarm rows with severity color: Not selected by default; only the alarm severity column is shaded in each row. When selected, shades the entire row the same color as the severity.

Enable alarm operations: Selected by default. Enables alarm operations to be performed in the Dashboard as they are on the Operations Center console. Deselect the check box to prevent users from performing alarm operations.

Show PDF/Excel export links: Selected by default; allows exporting alarms. Deselect to remove the export options.

Refresh portlet when updates occur: Selected by default. Enables the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur. Deselect to manually control updates. Note that the Alarm portlet does not support push updates for SLA alarms.

Pause alarms when selecting or driving alarms: Selected by default. Incoming alarms are halted when an alarm is selected. To resume alarms, click the *Resume alarms* link.

Enable navigation mode: When selected, click an alarm to drive the content in other portlets. A double-click opens alarm properties regardless of whether this option is enabled or not. For more information about setting up portlets to be driven by other portlets, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,”](#) on page 110.

Enable historical alarms: By default, real-time alarms are shown. To show real-time audit events, service level breaches, or service level metrics; select the associated check box, then select the desired options for type of alarms and date range from the drop-down lists.

4 Click *Save*.

8.1.3 Applying and Creating Alarm Filters

View a subset of alarms by applying a filter based on one or more alarm properties, such as severity, element ID, or date/time stamp. For example, apply a filter to display only those alarms with a specific severity message or class, or alarms received within a specific date and time range. Each filter consists of one or more conditions, combined using AND or ANY logic.

- ♦ [“Understanding Alarm Filters”](#) on page 139
- ♦ [“Enabling an Alarm Filter”](#) on page 139
- ♦ [“Creating an Alarm Filter”](#) on page 140
- ♦ [“Understanding Operators and Alarm Values”](#) on page 142
- ♦ [“Editing and Deleting Filters”](#) on page 143

Understanding Alarm Filters

Note the following important rules about Alarm filters on portlets:

- ♦ **Alarm Filters are shared by all Alarm portlets:** A single list of alarm filters is available to users of any alarm portlet.
- ♦ **Applying an alarm filter does not change the total alarm count for each severity:** At the top of the alarms portlet (if the *Show Alarm Options* check box is selected on the *General* tab). For example, if there are a total of 100 CRITICAL alarms, but an applied filter removes these alarms from the table, 100 still displays next in the red severity button.
- ♦ **Filters are applied in the order in which they are listed:** Multiple filters are applied using the AND operator, meaning the resulting set of alarms must match all the active filters.

When *Show Alarm Options* is enabled in portlet *Preferences*, alarm count totals displays at the top of the alarms component. These alarm count totals do not change even when alarm filters are applied.

Figure 8-2 Alarms for Script Adapter

The screenshot shows the 'Alarms for ScriptAdapter' portlet. At the top, there are controls for 'Real-time' and 'Alarms' with 'Update' and 'Pause' buttons. Below this, it says 'Total: 100' and shows a row of colored buttons representing severity counts: 31 (red), 16 (orange), 18 (yellow), 16 (green), 19 (light green), 0 (dark green), and 0 (blue). There are also 'select' and 'unselect all visible alarms.' links. Below the buttons is a table with columns for severity, time, and days. The table contains four rows of 'INFORMATIONAL' events from November 16, 2009.

Severity	Time	Days
INFORMATIONAL	November 16, 2009 1:58:30 PM EST	113day 12
INFORMATIONAL	November 16, 2009 3:58:30 AM EST	173day 72
INFORMATIONAL	November 16, 2009 2:28:30 PM EST	110day 9
INFORMATIONAL	November 16, 2009 1:18:30 PM EST	117day 16

Enabling an Alarm Filter

To enable an alarm filter (or to see what is enabled):

- 1 Click *Options* and select *Preferences* to open the *Filters* tab.

Note that for other portlets, open the *Advanced* tab to get to the *Alarms* tab.

The screenshot shows the 'Alarms' configuration window with the 'Filters' tab selected. It has sub-tabs for 'Alarms', 'Element', and 'Advanced'. Under 'Filters', there are 'General' and 'Filters' sub-tabs. A 'New Filter Wizard...' button is visible. Below is a table with columns for 'Name', 'Type', and 'Active'. Two filters are listed: 'Open' and 'Critical Only', both with 'Include' type and checked 'Active' boxes. 'Edit' and 'Remove' buttons are next to each filter. At the bottom are 'Save' and 'Reset' buttons.

Name	Type	Active	
Open	Include	<input checked="" type="checkbox"/>	Edit Remove
Critical Only	Include	<input checked="" type="checkbox"/>	Edit Remove



- 2 Select the *Active* check box next to filters that should be applied.
Only the active filters are applied to the alarms; other filters are ignored.
- 3 From the *Type* drop-down list, specify if matching alarms should be included in the view or excluded from the view by selecting *Include* or *Exclude*.


- 4 Click *Save* to apply the settings, then click the  (Back Arrow and Return to Full Page link) to return to the alarms view.

The active filters are applied and the filtered alarms display.

Creating an Alarm Filter

To create an alarm filter:


- 1 Click  *Options* and select  *Preferences* to open the *Filters* tab.
Note that for other portlets, open the *Advanced* tab to get to the *Alarms* tab.
- 2 On the *Filters* tab, click *New Filter Wizard* to open the Alarm Filter dialog box.
- 3 In the *Filter Name* field, specify a name for the filter.
- 4 Click *Add* to display a filter condition row:



- 5 Define the condition statement by selecting the following:

- ◆ **Alarm Column:** Click the *Select Alarm Column* link to specify the alarm column whose values are considered.

The available alarm column selectors varies depending on adapter and currently selected elements. The input field at the bottom can be used to enter a column name that is not listed. This could be used later for alarms that originate from other elements, because filters are shared by all Alarm portlets.



- ◆ **Operator for Comparison:** An operator is used to compare the alarm column value to a specified value (greater than, less than, and so on).

Operators and comparison value selectors vary depending on the alarm column type and adapters. For more information, see [“Understanding Operators and Alarm Values” on page 142.](#)

For example, the following condition selects alarms received within the last 30 minutes:

Wizard: Alarm Filter

Filter name: (must be unique) Last 30 Minutes

Match any of the following Match all of the following

theDate/Time of the alarm is less than 30 minutes before current time

- ◆ **Comparison Value:** A comparison value is used to determine whether an alarm is selected.

When Severity is the selected alarm column, a drop-down list of severity codes and colors displays in the right column. The codes vary among adapters.

For a specific date/time comparison, use the calendar selector to select a date. In some cases, a relative “rolling” date/time comparison is necessary. For example, a filter could select alarms that are within 30 days of the current date/time. Use the “is less than” or “is more than” operator to specify the time interval for comparing the current date and time. Also specify whether the filter should pull alarms that are before or after the current date/time.

February, 2011							
Today							
wk	Sun	Mon	Tue	Wed	Thu	Fri	Sat
4			1	2	3	4	5
5	6	7	8	9	10	11	12
6	13	14	15	16	17	18	19
7	20	21	22	23	24	25	26
8	27	28					

Time: 12:53


Select date

- ◆ **Text-Type Columns:** Specify case-sensitive matching for text-type alarm columns. Select the check box to match exactly each letter in the alarm column with the string entered in the filter field.

theStatus of the alarm is OPEN Case sensitive

6 To define another condition, click *Add*.

The following example shows a filter with two statements.



The filter matches alarms with a date and time stamp before the specified date/time and a CRITICAL severity.

7 Select the *Match any of the following* or *Match all of the following* radio button to determine whether alarms must meet any (OR logic) or all (AND logic) of the condition statements defined for the filter.

8 Click *Create* to create the filter.

Don't forget to enable the filter! See ["Enabling an Alarm Filter" on page 139](#).

Understanding Operators and Alarm Values

[Table 8-1](#) provides an overview of the relationships among the three fields used to define alarm filters. The available operators depend on the type of alarm column.

Table 8-1 Relationships Among Alarm Filter Values

Alarm Column Type	Operators	Match Criteria	Notes
Text-based (such as Element, Class, Status, Description)	contains does not contain is is not begins with ends with matches regex	Specify appropriate value based on selected alarm column.	<ul style="list-style-type: none"> For exact matches, use is/is not. For partial matches anyplace in an alarm value, use contains/ does not contain. For partial matches using the first or last characters, use begins with/ends with. To match column content with a Java Regular Expression, use matches regex and specify the expression in the far right field. In regular expressions, standard wildcards (?) and (*) are allowed, as well as standard operators, such as OR and BETWEEN.
Date, Time	is is not is before is after	Specify Date/Time.	To select a date range, create a before and an after statement, joined by the Match all operator.

Alarm Column Type	Operators	Match Criteria	Notes
	is less than is more than	Specify a date/time interval to compare with current time. This is a relative date/time comparison.	For example, to match dates that are within 30 days earlier than the current date, use the criteria: date/time is less than 30 days before the current date.
Severity	is is not is higher than is lower than	Select from severity levels appropriate to the adapter.	Use is to not exclude all but one severity code. To select a contiguous range of severity codes, create two statements using higher than and lower than, joined by the Match all operator.
Numeric	begins with contains does not contain ends with is is greater than is less than is not	Enter the number.	For exact matches, use is/ is not. For partial matches anywhere in an alarm value, use contains/ does not contain. For partial matches using the first or last characters, use begins with/ends with. To select a contiguous range of values, create two statements using greater than and less than, joined by the Match all operator. After placing the cursor in the filter value column (the last column in the row), enter a value. Otherwise, it is not possible to edit the other columns or close the Alarm Filter dialog box. An error message prompts for a numeric value.

Editing and Deleting Filters

Alarm filters can be edited and deleted.

IMPORTANT: Ask other users who might share an alarm filter before you modify or remove it.

To edit or delete filters:


- 1 To edit a filter:
 - 1a Edit the filter.
 - 1b Click *Save*.
 - 1c Click *Edit* next to a filter name to open the Alarm Filter dialog box.
- 2 To delete a filter:
 - 2a Click *Remove* next to a filter name to display a confirmation dialog box.
 - 2b Click *OK* to confirm the deletion.
The filter disappears from the *Alarm Filter* pane.

8.1.4 Performing Alarm Operations

With the alarms portlet, you can perform many of the same operations against alarms that can be performed in the Operations Center console. In some cases, as with Service Level Breaches, alarm operations available in the Dashboard are not identical to those available in the Operations Center console.

Alarms operations are enabled by default in the alarm portlet configuration. The Dashboard has a global option to show alarm operations in all portlets that is set in the [Operations Center Dashboard Configuration Manager](#). However, the configuration options in each portlet override the settings in the Operations Center Dashboard Configuration Manager.

To perform alarm operations:

- 1 (Optional) Select more than one alarm by selecting the check boxes for the desired alarms.
- 2 Right-click the  icon for an individual alarm or for one of the selected alarms, then select the alarm operation.

If multiple alarms are selected, alarms operations are applicable for all currently selected alarms.

The operations available depend on the source of the alarm(s). For more information about alarms, see [Alarms View](#) in the [Novell Operations Center 5.0 User Guide](#).

8.2 Configuring the Charting Portlet

The Charting portlet allows you to graphically measure up to 10 metrics from any of these types of data:


- ♦ **Element Performance Metrics:** shows element performance or alarm data over time.
- ♦ **Availability:** shows element availability (not in a CRITICAL state) during a period of time.
- ♦ **Downtime:** shows element downtime (in a CRITICAL state) during a period of time.
- ♦ **SLA Compliance:** view SLA data charts to determine if the objectives of a Service Level Agreement are being met.

It creates line, area, column bar, or condition charts that allow you to easily navigate and compare performance over time, and view raw data points if required.

The Charting portlet has the convenience of a left settings panel to configure the chart without having to go back and forth between view-side and edit-side preferences. Once your chart is configured, you can collapse or hide the left panel.

The following chart shows server memory usage. Hover over any data point to see details in a tool tip.

Figure 8-3 Charting Portlet




To view charts:



1 Do any of the following to configure your chart:

- ◆ Click the *Manage Elements* link to add or remove metrics from the chart.
 - ◆ Click a parent or child element to navigate through the element hierarchy.
 - ◆ Select specific metrics to chart, or configure metrics matchers using a regular expression. If more than 10 metrics are selected or found, only the first 10 found are charted.

When selected element or metric identifiers are not always predictable, it is best to use a regular expression to match profile expressions. For example, when the portlet is driven by another portlet, the selected element will not be fully predictable and a regular expression can match a number of predicted expressions for the element. For instructions on driving, see [Step 3 on page 146](#).

Or, if the selected profile captures metrics against a correlated service model created by an SCM definition, regular expressions are necessary to match a number of predicted expressions because expression identifiers for correlated metrics are renamed during the Operations Center server restart process or if the correlated service model element is renamed. Correlated metrics are easily recognizable by their naming convention of *Correlated Element Name: Unique Identifier*.

- ◆ For manually selected metrics:
 - ◆ Change the metric name, type, line color, thickness and fill for any of the selected metrics.
 - ◆ A  next to the metric name indicates this metric is used to populate the data display in the preview slider bar. Click the grayed icon next to a different metric to change the display.


- ◆ Click the *Basic* tab to configure titles, threshold, y-Axis value range, auto-refresh, and hide or show various chart features.
- ◆ Click the panel's arrow button to collapse the left panel, widening the chart viewing area. Click the arrow button again to expand the left panel.
- ◆ Hide the left configuration panel. On the portlet title bar, click  *Options* and select  (*Preferences*), and select *Hide View Side Options*.
- ◆ Click *Update* to view changes in your chart. Click *Publish* to save changes and push them out to users.

Non-published changes are not persisted between sessions. Only administrators and owners have permissions to publish.

2 Do any of the following when viewing data in the chart:

- ◆ Use the preview slider bar to zoom in, click any of the range buttons, or select new dates and times from the date range.
- ◆ Select a smaller charting range when data is summarized or incomplete.



When a request exceeds the maximum number of data points can be charted at one time, Operations Center generates an automatic representation of existing data and trending. When information can be summarized (for example, when values are numbers and not element conditions), the chart uses averaged data points from the original data and displays a message that there is summarized data. If the data cannot be averaged, metric data is clipped to the maximum number of points possible and the chart displays a message that there is incomplete data.

- ◆ Click any metric name in the legend to hide it from the chart.
- ◆ Click the  icon and select *Chart Data* to view a list of values for all data points currently showing in the chart. Any hidden metrics are excluded.
- ◆ (*NetIQ AppManager elements only*) Click on a specific data point to open a *Details* dialog showing more information about the data point in that series. Currently, this is only available for NetIQ AppManager elements. For more information, see "[AppManager Operations Portal Features for Charting NetIQ AppManager Data](#)" in the *NetIQ AppManager Operations 5.0 Portal Getting Started Guide*.

3 Use the Charting portlet in drive mode:

3a Configure your metrics using a regular expression.

While it is not required to use a regular expression when driving, it is likely the most effective way to configure the matcher since metric names are usually slightly different even if similar. By casting a wider net, there is a better chance metrics can be found from element to element.

3b The  next to the element name shows that this is the configuration to use when driving. Click the  grayed icon next to different configuration to change driving configurations.


3c Click a new element in a *Navigation*, *Search*, *Starter*, or *Status* portlet to update the chart. If data is found for that element using the driving configuration, data shows in the chart.

For information about driving, see [Section 7.4, "Using Navigation Mode to Drive Multiple Portlets,"](#) on page 110.

3d Click  to exit drive mode and return to the configuration point.

8.3 Configuring the Element Properties Portlet

The Element Properties portlet displays all the properties of the selected element.





The screenshot shows a window titled "Element Properties" with a table of properties. The table has two columns: "Name" and "Value". The "Condition" and "http://formulaapi/elementCondition" rows have a red "CRITICAL" status. The "http://formulaapi/alarmsSeverityCounts" row has a value of "l@6cddadfc".

Name	Value
Algorithm Disseminates	
Algorithm Parameters	
Condition	CRITICAL
Element	151.155.244
Last Reported	Tue Nov 02 11:16:35 EDT 2010
_ID11_Subnet	151.155.244
_formulapulse	Tue Nov 02 13:18:15 EDT 2010
http://formulaapi/alarmsSeverityCounts	l@6cddadfc
http://formulaapi/algorithm	
http://formulaapi/elementCondition	CRITICAL
http://formulaapi/lastElementUpdate	Tue Nov 02 11:16:35 EDT 2010
http://formulaapi/message	

Property information can be exported from the Element Properties portlet into Excel and PDF formats. Click the Excel or PDF icon to export the data.

The Element Properties portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Performance, Tree Map, Properties Table, Show Impacted, Root Cause, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Properties* from any of these portlets.

To configure the Element Properties portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Element* tab to select the element to display.

The only configuration option for the properties component is selecting the element to display.

8.4 Configuring the Information Portlet

The Information portlet provides a summarized view of an element's status. It might also include a graphical display of the element's layout view and/or an alarms chart.


Based on its settings, the portal can also allow navigation down to any children or up to the parent's view and displays the current condition and status. Various information is available via tab views including element properties, alarms, layout, root cause, impacted elements, and charts.

In the *Alarms* tab, as in the Operations Center console, alarm operations can be performed (when available), alarm filters can be created and applied, and alarm data can be exported to an Excel or PDF file.

In the *Charts* tab, as in the Operations Center console's Performance view, view a chart of performance and service level metrics. A preview slider bar allows you to see data trending and easily adjust the selected range. When a metric exceeds the maximum number of data points that can be charted at one time, Operations Center automatically generates the best representation of the data as possible, either by summarizing when data points are numeric values or clipping the data. In either case, you can narrow the chart range to display additional data.

All options are configurable to create a custom display.

Figure 8-4 Information Portlet



The Information portlet is optimized to display at a resolution of 1280 (or greater) in width, and inside a column layout that expands to 50% or greater. For smaller configurations, scroll bars will be implemented on components, such as performance charts.

The Information Portlet can also be used to set the starting element for other portlets on the Web page, similar to the [Navigation portlet](#). To configure the Information portlet to drive other portlets using Navigation, see [Step 3 on page 138](#) and [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,” on page 110](#).

The following sections provide detailed information about the Information portlet:

- ◆ [Section 8.4.1, “Viewing Element Information,” on page 148](#)
- ◆ [Section 8.4.2, “Configuring the Information Portlet,” on page 150](#)

8.4.1 Viewing Element Information

The actual information shown in the portlet/view depend on various settings in the configuration options:

- ◆ **Element Status:** Displays the condition of the element with date/time of last update.
- ◆ **Parents/Children:** Displays simple lists of both parents and children. Click an element name to update the Information portlet for that element.
- ◆ **Information Tabs:** View element properties, alarms, alarm summary information, layout/relationship diagrams, root cause, and impacted elements; as well as chart any available performance metrics.

NOTE: Data in the *Layout* tab displays based on the time zone of the Operations Center server, and not the time zone configured for the Dashboard.

To view element information:


1 Do any of the following:

- ◆ Click the arrow button to close the left panel, expanding viewing area for information in tabs. Click the arrow button again to open the left panel.
- ◆ Click a parent or child element to update the portlet information and navigate through the element hierarchy.
- ◆ Click any of the tabs to view additional information about the current element.
- ◆ In the *Alarms*, *Root Cause*, *Impacted*, and *Charts* tabs, click the *Refresh* button to force an update of the information.

2 In the *Charts* tab, do any of the following:



- ◆ Click the metrics selected link to add or remove metrics from the chart.
- ◆ Select a smaller charting range when data is summarized or incomplete. Use the preview slider bar to zoom in, click any of the range buttons, or select new dates and times from the date range.


When a request exceeds the maximum number of data points can be charted at one time, Operations Center generates an automatic representation of existing data and trending. When information can be summarized (for example, when values are numbers and not element conditions), the chart uses averaged data points from the original data and displays a message that there is summarized data. If the data cannot be averaged, metric data is clipped to the maximum number of points possible and the chart displays a message that there is incomplete data.

- ◆ Click any metric name in the legend to hide it from the chart.
- ◆ Click the  icon and select *Chart Data* to view a list of values for all data points currently showing in the chart. Any hidden metrics are excluded.

8.4.2 Configuring the Information Portlet

To configure preferences for the Information portlet:

- 1 Click  *Options* and select  *Preferences* and update settings on the *Information* tab:



- 2 To change the default view for the portlet, select a new tab name from the *Default Tab* drop-down list.
- 3 Deselect the *Refresh portlet when updates occur* option to manually control updates. When selected, enables the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur. Note that the Alarm portlet does not support push updates for SLA alarms.
- 4 Deselect the *Enable navigation mode* to disable the portlet from updating other portlets on the page when an element is selected in the Information portlet.

When Navigation mode is enabled, the Information portlet functions as a driver for the content displayed in other portlets except for the Navigation portlet. Selecting an element in the Information portlet displays information about the element in other portlets on the page. This feature is only available when using SVG on IE, and is not supported on Firefox. For more information about setting up portlets to be driven by other portlets, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,”](#) on page 110.

5 Select or deselect the following check box options for the header and status panels:

Show element notes: Selected by default. Deselect the option to hide element notes in the header.

Show condition indicator: Selected by default. Deselect the option to hide the element's condition indicator in the status panel.

Show last updated date/time: Selected by default. Deselect the option to hide the date and time of the last update.

Show parents: Selected by default. Deselect the option to hide the list of parent elements.

Then, select or deselect the following check box options for parents:

- ♦ **Allow navigation above originating element:** Selected by default. Deselect the option to restrict upward navigation to the selected element in portal preferences.
- ♦ **Filter parents via originating element:** Selected by default. Shows the parent element whose DName partially matches the selected element; this is the parent where the selected element was originally created in the Operations Center hierarchy. Deselect the option to show all parents -- this includes any parents under Service Models where the element is linked.

For example, if the selected element is from a NetIQ AppManager adapter, and is also linked from three Service Model elements, we would see only one parent listed (the parent element in the NetIQ adapter hierarchy) when this option is selected. We would see a total of four parents listed (the parent in the NetIQ adapter hierarchy, plus the three parents in the Service Model hierarchy) when this option is unselected.

Show children: Selected by default. Deselect the option to hide the list of children elements.

Then, specify the following options for children:

- ♦ **Halt navigation:** Specify the number of levels of children that are available for navigation under the selected element in portal preferences.

6 Select or deselect the following check box options for the *Properties* tab:

Show Properties tab: Selected by default. Deselect to hide the *Properties* tab.

7 Select or deselect the following options for the *Alarms* tab:

Show Alarms tab: Selected by default. Deselect to hide the *Alarms* tab.

Default View: Specify the type of alarm information to show. Select between *Alarm Summary* and *Alarm Listing*.

Filter by Severity: Specify a comma separated list of severities (such as "CRITICAL,MINOR") to hide alarms with specific severity levels. Alarms with matching severities will not show in the information portlet. Leave this field empty to show all alarms. In addition to this option, you can also filter alarms by severity using the colored bar when viewing the alarms.

Alarm Columns: Specify a comma separated list of alarm columns to display (and hide all other columns). Leave blank to display all columns. Columns available to display are dependent on the source of the alarms.

If alarms are currently displayed in the portlet, click the browse (...) button to select columns from a list based on a sampling from the current alarms. If no alarms are currently displayed in the portlet, the selector is unable to show columns to select from. Use the left and right arrow buttons to move a column name between the Available list and the Selected list. Use the up and down arrows to reorder column names.

Sort Alarms by: Specify a column name to use as a sort key for displayed alarms. Severity is the default sort key. You can also change the sort key while viewing the alarms table by clicking a column heading.

Alarms per Page: Specify the maximum number of alarms to show on each page.

Then, select or deselect the following check box options for alarms:

Sort alarms in ascending order by default: Selected by default. Deselect the check box to initially sort in descending order. Use this option or click column headings when viewing the table to change the sort order.

Highlight alarm rows with severity color: Not selected by default; only the alarm severity column is shaded in each row. When selected, shades the entire row the same color as the severity.

Enable alarm operations: Selected by default. Enables alarm operations to be performed in the Dashboard as they are on the Operations Center console. Deselect the check box to prevent users from performing alarm operations.

Show PDF/Excel export links: Selected by default; allows exporting alarms. Deselect to remove the PDF and Excel options.

- 8 Select or deselect the following check box options for the *Layout* tab:

Show Layout tab: Selected by default. Deselect to hide the *Layout* tab.

Then, specify the following options for the layout diagram:

- ◆ **Layout Type:** Specify the type of layout to display. Select between *Classic* and *Relationships*.
- ◆ **Output Type:** Specify the type of technology used to display the diagram. Select between *SVG* and *Flash*.
- ◆ **Show layout type selector in view mode:** Selected by default to allow the user to toggle between layout types in view mode.

- 9 Select or deselect the following check box options for the *Root Cause* and *Impacted* tabs:

Show Root Cause tab: Selected by default. Deselect to hide the *Root Cause* tab.

Show Impacted tab: Selected by default. Deselect to hide the *Impacted* tab.

- 10 Select or deselect the following check box options for the *Charts* tab:

Show Charts tab: Selected by default. Deselect to hide the *Charts* tab.

Then, specify the following options for the chart:

- ◆ **Default Range:** Select the length of time shown in the chart when it initially loads.
- ◆ **Default Metrics:** Specify a regular expression to select and chart performance metrics to chart by default. If specified, the Information portlet attempts to find and charts metrics based on the regular expression. If no matching metrics are found for the selected element, you can manually select metrics applicable to that element. If matching metrics are found, the chart renders the first 10 metrics found. The chart can then be edited to change the selected metrics.

- 11 Click *Save*.


8.5 Configuring the Layout Portlet

The Layout component displays either the *Layout View* or the *Relationship View* (created in the Relationship Browser window) from the Operations Center console. For more information about the *Layout View*, see the [Novell Operations Center 5.0 Custom Drawing and Layout Guide](#). For information on the Relationship Browser drawings, see the [Novell Operations Center 5.0 Service Modeling Guide](#).

The Layout portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Performance, Tree Map, Element Properties, Properties Table, Show Impacted, Root Cause, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Layout* from any of these portlets.

By default, [Figure 8-5](#) shows the element's *Layout View* and is **automatically updated** when the element changes in the Operations Center server:

Figure 8-5 Layout Portlet showing a Layout view for an Adapter



NOTE: Data in the Layout portlet displays based on the time zone of the Operations Center server, and not the time zone configured for the Dashboard.

To view and configure the Layout portlet:

- ◆ [Section 8.5.1, "Navigating in the Layout Portlet,"](#) on page 153
- ◆ [Section 8.5.2, "Configuring the Layout Portlet,"](#) on page 154


8.5.1 Navigating in the Layout Portlet

While viewing the *Layout* portlet, do any of the following:

- ◆ Click an element to drill down.
- ◆ Click the home icon to return to the element first displayed.
- ◆ Click the back icon to view the previous element or other previously viewed parent elements.
- ◆ When defined, click the element to open a Web page or URL.

This feature requires a custom property definition configuration in the Operations Center console. For information, see [Section 7.6, "Configuring URL Linking for the Layout Portlet,"](#) on page 121.

- ◆ When a predefined tool tip or pop-up dialog was configured in the *Layout View* of the Operations Center console, hover the mouse over an element to show the tool tip or pop-up:




For information on how to define a tool tip/pop-up dialog, see “[Adding Tooltips or Pop-Ups to Portlets in the Dashboard](#)” in the *Novell Operations Center 5.0 Custom Drawing and Layout Guide*.

8.5.2 Configuring the Layout Portlet

In order to view the *Layout* portlet, the Adobe SVG Viewer 3.0 must be installed on the computer. For more information about the Adobe SVG Viewer, see [Section 7.9.1, “SVG Viewer,” on page 132](#).

If the Dashboard cannot detect this plug-in, the following message displays. Follow the on-screen instructions to download and install the SVG plug-in.

Figure 8-6 SVG Plugin Not Installed Message



If the message continues to appear after you have successfully installed the Adobe plug-in, then verify that your browser is configured to allow Active X controls to run.

To configure the Layout portlet/view:

- 1 Click *Options* and select *Preferences*.
- 2 Click the *Layout* tab.

For other portlets other than Layout, the *Layout* tab is found under the *Advanced* tab.

3 Specify the following options:

Diagram Width: Determines the size of the diagram within the portlet and is expressed as a percentage. The default is 100%.

Diagram Height: Determines the height of the diagram within the portlet and is expressed as pixels. The default is auto.

Output Format: Select SVG or Flash. Note that custom background colors are not rendered when using Flash output.

4 Select or deselect the following check box options:

Show the relationships instead of Layout diagram: By default, this option is not selected and the layout diagram displays. Select the check box to show relationships between the current element and other elements.

Show navigation options: Selected by default. Displays the home and back/history icons in the diagram. Deselect to hide the options.

Automatically scale diagram: Select the check box to render the SVG diagram using the specified width and height. Deselect the check box to render the diagram using the dimensions calculated by the software, which, in general, provide the best scaled view of the diagram.

Enable navigation mode: If selected, enables the Layout portlet to function as a driver for the content displayed in other portlets except for the Navigation portlet. Selecting an element on the Layout drawing displays information about the element in other portlets on the page. This feature is only available when using SVG on IE, and is not supported on Firefox. For more information about setting up portlets to be driven by other portlets, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,” on page 110.](#)

Then, specify additional options for navigation mode:

- ◆ **Allow drill-down when clicking on elements:** If selected, updates the Layout diagram to display children of a selected element. If not selected, the diagram does not change. Navigation mode must be enabled for this option to apply.
- ◆ **Portlet Identifiers:** Specify a comma-separated list of portlet tags corresponding to other portlets on the page that should update to display information related to an element selected on the Layout portlet. For information on tagging portlets, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,” on page 110.](#)

Refresh portlet when updates occur: Selected by default. Enables the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur. Deselect to manually control updates.

Refresh portlet every X Seconds/Minutes/Hours: If selected, forces a refresh of layout portlet content. Specify the time interval to perform the refresh action.

When using SVG, and containing charts with a refresh interval (configured in Operations Center), the chart refresh interval is used if set to be more frequent than the Refresh portlet setting above. If there is more than one chart in the layout, the shortest (most frequent) refresh interval configuration is used for the portlet.


- 5 Click *Save* before exiting the configuration options.

8.6 Configuring the Navigation Portlet

Use the Navigation portlet to set the starting element for other portlets on a page. The Navigation portlet displays an element hierarchy with icons show the element's current condition. For more information on element status, see [Monitoring Elements and Element State](#) in the [Novell Operations Center 5.0 User Guide](#).

The elements displayed depend on the user's permissions in Operations Center. Click the + and - icons to expand and collapse the element hierarchy displayed on the Navigation portlet.



Figure 8-7 Navigation Portlet




By default, the element selected on the Navigation portlet is the element shown in all portlets on the page (where applicable). This is similar to the [Configuring the Starter Portlet \(page 176\)](#). The default starting element is the user's home element.

If both a Navigation portlet and a Starter portlet exist on the same page, either portlet can be used to drive other portlets on the page. However, after a portlet is set up to be driven by the Navigation portlet, it is no longer driven by the Starter portlet (and vice versa), unless set up on the Starter portlet, too.

To configure the Navigation portlet:

- 1 Click  *Options* and select  *Preferences*.

The Navigation tab opens.



- 2 In the *Height* field, specify the height in pixels, or `auto` to allow the portlet to grow vertically as needed.
 - 3 From the *Indicator Image* drop-down, select a status icon shape, or select `None` to hide status indicators.
 - 4 From the *Element Link Behavior* drop-down, select the expected behavior to happen when element name links are clicked:
 - ♦ **Expand and Drive:** Expands the tree to show any element children and updates the content on the page.
 - ♦ **Expand Only:** Expands the tree to show any element children.
 - ♦ **Drive Only:** Updates the content on the page.
- When the *Element Link Behavior* is set to drive other portlets, the Navigation portlet updates all other portlets on the page when clicking on an element name. To drive only specific portlets on the page, you need to reference those portlets in the Advanced options. For instructions, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,”](#) on page 110.
- 5 Deselect the *Refresh portlet when updates occur* option to manually control updates to the portlet. This option is selected by default and enables the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur.
 - 6 Click *Save*, then exit the preferences for the portlet.


8.7 Configuring a Performance Portlet

The Performance portlet can create line or bar charts that graphically measure:

- ♦ **SLA Compliance:** view SLA data charts to determine if the objectives of a Service Level Agreement are being met.
- ♦ **Element Performance Metrics:** shows element performance or alarm data over time.
- ♦ **Availability:** shows element availability (not in a CRITICAL state) during a period of time.
- ♦ **Downtime:** shows element downtime (in a CRITICAL state) during a period of time.

The following bar chart shows the availability for a selected element:

Figure 8-8 Performance Chart



For some types of elements, clicking on a specific data point opens a *Data Point Details* dialog showing more information about the data point in that series. Currently, this is only available for NetIQ AppManager elements and when specific configurations are enabled:

- ◆ The chart display format is FLASH. Data point details are not available for JPEG or PNG outputs.
- ◆ The chart type is line. Data point details are not available for bar charts.
- ◆ The *Plot actual data points, instead of normalizing data* option is enabled.

When charting raw data, increase performance by reducing the number of data points returned while preserving the natural shape of the line. For more information about configuring this custom setting, see [Section 7.8.2, “Configuring Performance Data Point Retrieval from the Operations Center Server,”](#) on page 124.

The Performance portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Tree Map, Element Properties, Properties Table, Show Impacted, Root Cause, Chart Builder and Summary. Click *Actions* and select *Go to > Performance* from any of these portlets.


To view and define the Performance portlet:

- ◆ [Section 8.7.1, “Viewing a Performance Chart,”](#) on page 159
- ◆ [Section 8.7.2, “Configuring the Performance Portlet,”](#) on page 159

8.7.1 Viewing a Performance Chart

While viewing the Performance chart, do the following:

- 1 Click *Options* to select another metric, adjust the chart interval or range, or change the portlet size:



Enable the *Options* link by selecting *Enable chart controls on portlet display* in the portlet configuration preferences.

Any changes made using the *Options* link apply to the chart for the duration of the session and requires the user to manually adjust the settings to return to chart defaults during that session.

For additional information on specifying chart metric settings, see [Section 8.7.2, “Configuring the Performance Portlet,” on page 159](#).

- 2 Click the *d* link located in the lower right to view the data used to render the chart.

For more information about viewing source data, see [Section 7.7, “Viewing Source Data for Charts,” on page 122](#).

8.7.2 Configuring the Performance Portlet

To configure the performance portlet:

- 1 Click *Options* and select *Preferences*. Begin defining the Performance component by selecting one or more [starting elements](#).

The current starting element(s) display in the top of the *Performance Chart* tab.

To change or add elements, use the *Elements* tab.

For more information, see [Section 7.3.2, “Configuring Starting Elements for Portlets,” on page 110](#).



- 2 Do the following for each element selected:

- 2a If charting performance metrics, select *Performance Metrics* in the *Display* drop-down list.

Performance metrics are based on user-defined profiles that collect performance and alarm data for selected elements. When a profile is defined, expressions are added to select which element properties are stored. For example, an expression can save the total number of alarms by severity for selected elements.

When the Performance Metrics chart type is selected, you must specify a profile and associated expression, which together determine the chart content.


Display: Performance Metrics ▾
Profile: ElementProfile ...
Expression: Select

IMPORTANT: When selected element or metric identifiers are not always predictable, it is best to use a regular expression to match profile expressions. For example, when the portlet is driven by another portlet, the selected element will not be fully predictable and a regular expression can match a number of predicted expressions for the element.

Or, if the selected profile captures metrics against a correlated service model created by an SCM definition, regular expressions are necessary to match a number of predicted expressions because expression identifiers for correlated metrics are renamed during the Operations Center server restart process or if the correlated service model element is renamed. Correlated metrics are easily recognizable by their naming convention of *Correlated Element_Name: Unique_Identifier*.

Then, to configure the Performance Metrics chart:

1. To select a profile, click the browse button.
Click to select the desired profile from the list.
2. To specify a profile expression, click *Select*. The Chart Expressions dialog opens.



Do one of the following:

- ◆ **Match profile expressions by regular expression:** Enter the regular expression to match in the *Regular Expression* field. A preview of matching expressions displays in the panel below.

For example, instead of specifying `Heap memory.PS Eden Space.Committed` as the expression for the Server element; using a regular expression, we could define any of the following:

[ABCH]eap.* Match any expression that has A,B,C or H in the beginning of the word.

.*Heap.* Match any expression that has "Heap" in its name.

^Heap.* Match any expression that begins with Heap.

\Deap.* Match any expression that begins with a non-digit and then has "eap".

[^abc]eap.* Match any expression with any character except a, b or c before "eap".

Regular expressions must conform to the Java standard regexes. For more information, go to the [Java API for java.util.regex.Pattern \(http://download.oracle.com/javase/1.4.2/docs/api/java/util/regex/Pattern.html\)](http://download.oracle.com/javase/1.4.2/docs/api/java/util/regex/Pattern.html).

Click *Look Up* to view a list of useful regular expressions if your Administrator has configured this. For more information about configuring the regular expression Look Up feature, see [Section 7.8.3, "Configuring Regular Expression Look Up for the Performance Portlet," on page 125](#).

- ♦ **Select specific profile expressions from a list determined from a regular expression:** Do the above, then select the *Enable manual selection of expression* check box. Click to select any expressions that you wish to chart.

Do not use this option when element or metric identifiers are not always predictable -- for example, when charting correlated metrics. Instead, match using a regular expression.

- ♦ **Select specific profile expressions from a list of all available profile expressions:** Switch to the *Browse* tab, then click to select each expression that you wish to chart.

Do not use this option when element or metric identifiers are not always predictable -- for example, when charting correlated metrics. Instead, match using a regular expression.

Click *Save* to close the Chart Expressions dialog. The Expression's Select button updates to show the type of expression settings defined. For example, if you define a regular expression, the button label is *RegEx Defined*. Hover over the button to see details.

For more information about profiles and expressions, and instructions on defining them, see [Capturing Alarm and Performance History](#) in the *Novell Operations Center 5.0 Server Configuration Guide*.

- 2b** If charting Service Level Agreement metrics, select `SLA Data` in the *Display* drop-down list. SLA data charts show if the objectives of a Service Level Agreement are being met. Then, to configure the SLA Data chart:

- 2b1** To select a Service Level Agreement, click the SLA browse button. Click to select the desired agreement from the list.

Display: ▾

SLA:

Objective:

Metric: ▾

- 2b2** To select an Objective, click the Objective browse button.

Click to select the desired agreement from the list.

2b3 Select the type of metric from the *Metric* drop-down list. Options are:

- ◆ **Availability:** The amount of time that a service is operational.
- ◆ **Breaches:** Breach alarms are issued for an SLA when an objective is out of compliance (fails). The defined health rules determine when an SLA is in violation.
- ◆ **Condition:** Tracks element conditions over time.
- ◆ **Health:** Health grades assigned to an SLA based on the health of each objective. Operations Center uses health as a measurement for whether the SLA is in or out of compliance.
- ◆ **Outages:** Incidents that result in key services, such as data or call centers, becoming unavailable (going offline). An outage occurs when an element reaches or goes below a specified condition.
- ◆ **Key Metric:** Formed from querying data in an external data source. (The key metric can then be used to determine SLA compliance by defining a calculation objective for the element based on the SLA Metric Catalog properties.)



For details on defining SLAs, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#).

2c If charting availability, select *Availability* in the *Display* drop-down list.

The Availability chart shows element availability (not in a CRITICAL state) during a period of time. Failures are highlighted in red and are easy to identify at a glance.

Then, to configure the Availability chart:

2c1 (Optional) Select a calendar from the *Calendar* drop-down list.




Display: 
Calendar: 

2d If charting downtime, select *Downtime* in the *Display* drop-down list.

The Downtime chart shows element downtime (in a CRITICAL state) during a period of time.

Then, to configure the Downtime chart:

2d1 Select the time interval from the *Display in* drop-down list.

Display: 
Display in: 
Calendar: 

2d2 (Optional) Select a calendar from the *Calendar* drop-down list.

2e (Optional) In the *Name* field, specify a custom name for the series.

The name can display in the chart legend and/or the chart title. If left blank, the default name is formatted as *ElementName,Profile,Expression* for Performance Metrics charts and *ElementName,SLA,Objective* for SLA data charts.

If there is more than one matching series, when a regular expression is defined for the Expression, the default naming convention is used instead of the custom name.

2f (Optional) Specify a chart format for the series by selecting *Line* or *Bar* from the drop-down list.

2g (Optional) Do one of the following to specify the color for the data series.

- ◆ Select the *Auto-generate color* radio button to have the color randomly selected.
- ◆ Select *Custom color* radio button, then enter a six-character hex color value in the *Custom color* field.

2h (Conditional) Click the *Use this configuration when driving the portlet* check box to use the associated configuration settings when the portlet is updated from an element selection in another portlet.

In this scenario, even though the element changes, the portlet continues using the selected configuration settings for charting the new element including chart type and other chart selections, as well as labels, type, and color selections as defined in this configuration.

When more than one configuration has this option selected and regular expressions are in use (Performance Metrics only), the Performance portlet uses settings from the configuration that first matches a profile expression for the element.

3 To specify time control settings for the chart, select one of the following:

- ◆ **Interval:** Defines a fixed interval.

Select only the current (*This*) hour/day/week/month or select multiple intervals (*Last...*).

If *Last* is selected, select the *Rolling* check box to calculate the interval using the current time as the ending of the interval. If rolling is unselected, the interval is calculated in full units and the end of the interval is the end of the preceding unit of time. For example, if the current time is 4:35pm and the interval is for the last 2 hours, without rolling the interval is 2-4pm. Whereas with rolling selected, the interval is 2:35-4:35pm.

Specify the time interval displayed in the chart from the *Display in* list. Select *Minutes*, *Hours*, *Days*, *Weeks* or *Months*.

- ◆ **Range:** Specifies a start and end date.

Click inside the *To* or *From* fields to open a calendar, then select a date.

Specify the time interval displayed in the chart from the *Display in* list. Select *Minutes*, *Hours*, *Days*, *Weeks* or *Months*.

- 4 Customize the chart format and appearance using any of the chart title and size, output file format, line axis or x axis appearance, and date format options:

Chart Option	Description
General Chart	<ul style="list-style-type: none"> ◆ Chart Title: Specify a title for the chart. This displays at the top of the chart. Use the variable <code>\$element\$</code> to dynamically populate the chart title with the element name(s). For example, <code>Performance Data for \$element\$</code> shows the following title when the chart includes two elements: <code>Performance Data for <i>Server1_Name</i>, <i>Server2_Name</i></code> ◆ Chart Title Style: Specify the font name, style and size to use for the chart title. The default is <code>Name:Helvetica; Size:12.0; Style:Bold;</code>. Changing the title color is optional. ◆ Chart Width: The chart height as a percentage. ◆ Chart Height: The chart width as a percentage. ◆ Output Format: The type of file that the chart generates: FLASH, JPEG, or PNG.
Line Axis Style	<ul style="list-style-type: none"> ◆ Grid Color: A six-character hex color value to use for the color of horizontal grid lines. ◆ Tick Style: Specify the style of the tick marks on the vertical axis. The default <code>Name:Helvetica; Size:12.0; Style:Bold;</code>. Changing the tick mark color is optional. ◆ Label: Specify the text used to label the vertical axis. ◆ Label Style: Specify the font name, size and style to use for the vertical axis label. The default is <code>Name:Helvetica; Size:12.0; Style:Bold;</code>. Changing the label color is optional.
X Axis Style	<ul style="list-style-type: none"> ◆ Grid Color: A six-character hex color value to use for the color of vertical grid lines. ◆ Tick Style: The style of the tick marks on the horizontal axis. The default <code>Name:Helvetica; Size:12.0; Style:Bold;</code>. Changing the tick mark color is optional. ◆ Label: Specify the text used to label the horizontal axis. ◆ Label Style: Specify the font name, size and style to use for the horizontal axis label. The default is <code>Name:Helvetica; Size:12.0; Style:Bold;</code>. Changing the label color is optional.
Date Formats	<ul style="list-style-type: none"> ◆ Year: The syntax used to display the chart year. Defaults to yyyy. ◆ Month: The syntax used to display the chart month. Defaults to MMMM. ◆ Week: The syntax used to display the chart week. Defaults to MM/d. ◆ Day: The syntax used to display the chart day. Defaults to MM/d. ◆ Hour: The syntax used to display the chart hour. Defaults to h:mm:a. ◆ Minute: The syntax used to display the chart hour. Defaults to hh:mm. <p>For more information on date formats, see the Oracle Web page for the SimpleDateFormat class (http://docs.oracle.com/javase/6/docs/api/java/text/SimpleDateFormat.html).</p>

- 5 (Optional) To enable chart view time options, select the *Enable chart controls on portlet display* check box.

The *Options* link displays at the top of the portlet on the dashboard page. If this option is deselected, users must go into the portlet Preferences to adjust any chart selections.

- 6 To plot all available data points, select the *Plot actual data points, instead of normalizing data.* check box.

Up to 10,000 data points are plotted on the chart regardless of the time interval selected.

If the option is unselected, the chart plots a maximum of:

- ◆ 60 data points when displaying in seconds.
- ◆ 360 data points when displaying in minutes.
- ◆ 160 data points when displaying in hours.
- ◆ 90 data points when displaying in days.
- ◆ 52 data points when displaying in weeks.
- ◆ 12 data points when displaying in months.
- ◆ 2 data points when displaying in years.


When the option enabled, it is possible to increase performance by reducing the number of data points returned while preserving the natural shape of the line. For more information about configuring this custom setting, see [Section 7.8.2, “Configuring Performance Data Point Retrieval from the Operations Center Server,”](#) on page 124.

- 7 To display the date and time the chart was last updated, select the *Show date/time of last update.* check box.
- 8 Click *Save*.

8.8 Configuring the Properties Table Portlet

The Properties Table portlet provides a summary view of an element and its children. It can be customized for the number of properties shown and the order that they display.

Figure 8-9 Properties Table Portlet



Name	Condition	Last Reported
Boston-7513-1	CRITICAL	Tue Nov 02 15:41:08 EDT 2010
NYC-7513-1	MAJOR	Tue Nov 02 15:41:39 EDT 2010
NYC-Alpha-1	CRITICAL	Tue Nov 02 15:35:44 EDT 2010
NYC-Alpha-2	OK	Tue Nov 02 15:36:39 EDT 2010
Phila-7513-1	MAJOR	Tue Nov 02 15:43:00 EDT 2010
Phila-Internet_Server-1	OK	Tue Nov 02 15:39:42 EDT 2010
Washington-7513-1	MINOR	Tue Nov 02 15:36:30 EDT 2010
Washington-Internet_Server-1	MAJOR	Tue Nov 02 15:38:28 EDT 2010

Property table information can be exported from the Properties Table portlet into Excel and PDF formats. Click the Excel or PDF icon to export the data.

The Properties Table portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Tree Map, Element Properties, Show Impacted, Root Cause, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Properties Table* from any of these portlets.

- ♦ [Section 8.8.1, “Viewing the Properties Table Listing,” on page 166](#)
- ♦ [Section 8.8.2, “Configuring the Portlet Properties Table,” on page 166](#)

8.8.1 Viewing the Properties Table Listing

To view the *Properties Table* listing:

- 1 To sort data by severity, click the *Condition* heading.
- 2 To sort the data in descending or ascending order according to that property, click any column heading.
- 3 Click the Excel or PDF icons to export the element property data to an Excel or PDF file.



If the file download window does not open, check your browser settings to see if pop-up dialog boxes are blocked.

8.8.2 Configuring the Portlet Properties Table


- ♦ [“Configuring Columns for the Properties Table” on page 167](#)
- ♦ [“Adding Properties” on page 168](#)

Configuring Columns for the Properties Table

To configure column heading for the Properties Table:

- 1 Click  *Options* and select  *Preferences*.

The columns currently displayed appear on the *Current* tab.




Property Name	Disable	Edit Property
<input type="checkbox"/> Condition [Condition]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Script [Script]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Pager [Pager]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Phone [Phone]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Fax [Fax]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Contact [Contact]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> PropagateSecurity [PropagateSecurity]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Algorithm Parameters [Algorithm Parameters]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> DisplaySourceElements [DisplaySourceElements]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> SourceElements [SourceElements]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Correlated [Correlated]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Algorithm Disseminates [Algorithm Disseminates]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Email [Email]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Last Reported [Last Reported]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> ExcludedFromImpact [ExcludedFromImpact]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Address [Address]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> IgnoreChildAlarms [IgnoreChildAlarms]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> URL [URL]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Company [Company]	<input type="checkbox"/> Disable	Edit Property
<input type="checkbox"/> Matches [Matches]	<input type="checkbox"/> Disable	Edit Property

- 2 Deselect the *Refresh portlet when updates occur* option to manually control content updates to the portlet. This option is selected by default and enables the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur.
- 3 Deselect the *Hide parent element from display* option to show the parent element in the properties table.
- 4 Make changes to the property columns included in the portlet:
 - ◆ To remove the column from the Properties Table display without deleting it from Preferences, select the option's *Disable* check box.
 - ◆ To edit any of the properties, click the associated *Edit Property* link.
For instructions, see [“Adding Properties” on page 168](#).
 - ◆ To delete a property column from Preferences, select the option's check box, and click *Remove*.
- 5 After making the necessary configurations, click *Save*.

Adding Properties

To add a new property to the *Properties Table*:

- 1 Click *Add Properties*.



The screenshot shows a web interface titled "Properties Table" with a "Return to Full Page" link in the top right. Below the title are three tabs: "Properties Table", "Element", and "Advanced". Under "Properties Table", there are two checked checkboxes: "Refresh portlet when updates occur." and "Hide parent element from display." Below these are two more tabs: "Current" and "Add Properties". The "Add Properties" tab is active and contains the following fields and options:

- Property Name*:** A text input field with the description "(Required) Name to show in the property's column header."
- Operations Center Property*:** A text input field with the description "(Required) The name of the property to retrieve from Operations Center."
- Text Before:** A text input field with the description "Text to show before the property value (e.g. \$)."
- Text After:** A text input field with the description "Text to show after the property value (e.g. %)."
- Highlight property background when the following conditions are met:**
 - If the property value is Enter value to compare.
 - then set the background color to the color of the condition
-

- 2 Specify the following options:

Property Name: Specify the name to display on the portlet.

Operations Center Property: Specify the name of the Operations Center property.

Text Before: (Optional) Specify any text to display in front of the property's value. For example, \$.

Text After: (Optional) Specify any text to display after the properties value. For example, %.

- 3 Specify the following check box options:

Highlight property background when the following conditions are met: If enabled, use the selectors to set a value at which the background is highlighted, then specify a background color.

The colors are mapped to conditions on the Operations Center console. For more information, see [Managing Condition/Severity Colors](#) in the *Novell Operations Center 5.0 User Guide*.


- 4 Click *Add Property*.

- 5 Click the *Current* tab to specify the display order for the new property.

8.9 Configuring the Public End User View Portlet

The Public End User View portlet provides a quick indication of status to guest users (not logged into the Dashboard and Operations Center).

Figure 8-10 Public End User View Portlet





Elements display with a graphical status indicated by a weather condition graphic. In the illustration, the state of the elements is as follows:



- ◆ NYC-7513-1 is currently in an OK state
- ◆ NYC-Alpha-1, Phila-7513-1, and Washington-7513-1 are currently in a CRITICAL state

For more information on elements and their various states, see [Monitoring Elements and Element State](#) in the *Novell Operations Center 5.0 User Guide*.

When this portlet is added to a private or community page, logged in users can see the elements for which they have View permissions in the Operations Center server. They can also configure the elements displayed using the [Elements tab](#) in the preferences.

To enable guest users view the Public End User View portlet:

- 1 Log in to the Dashboard.
- 2 Add the portlet to a public dashboard Web page.
- 3 To set the log in credentials for the portlet on the *Home* tab of the preferences:
 - 3a On the portlet title bar, click  *Options* and select  *Preferences*.
 - 3b Click the *Home* tab.
 - 3c Specify the *Login* and *Password* for a user who has the permissions required to view the selected elements.
 - 3d Click *Save*.


- 4 To set the configuration option for the portlet to allow guest users to view the portlet:
 - 4a On the portlet title bar, click  *Options* and click the  (*Configuration*) icon. The *Permissions* tab displays.
 - 4b Configure Guest permissions as desired.
 - 4c Click *Submit*.
- 5 Select the elements to be displayed using the [Elements tab](#) of the preferences.

8.10 Configuring the Root Cause Portlet

The Root Cause portlet displays both a summary and details regarding the cause of the selected element's current state.

The Root Cause portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Tree Map, Element Properties, Properties Table, Show Impacted, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Root Cause* from any of these portlets.



Figure 8-11 Root Cause Portlet Displaying the Root Cause Component with Display Notes Selected



Element state is indicated by a status icon, the color of which corresponds to the element's current condition that is mapped to colors in the Operations Center server. For more information about element condition settings, see [Managing Condition/Severity Colors](#) in the *Novell Operations Center 5.0 User Guide*.

Element details can vary by the type of element and the alarms associated with it. Details, which is a configuration turned off by default, can include the number of active alarms, the highest alarm severity, the alarm id numbers, and so on.

To configure the Root Cause portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Root Cause* tab.
 - For other portlets other than Root Cause, the *Root Cause* tab is found under the *Advanced* tab.
- 3 Select the *Display Notes* check box to display more details for each element.
- 4 Click *Save*.

8.11 Search Portlet

The Search portlet is used to find elements in the Operations Center hierarchy. The Search portlet returns only native elements within the Operations Center hierarchy, and does not return any linked instances of an element.

Figure 8-12 *The Search Portlet*



View information about the properties of found elements in the search results. Or, use it to update the [starting elements](#) in other portlets by selecting one of the found elements. In addition, you can:

- ♦ [Section 8.11.1, "Configuring Search Parameters," on page 172](#)
- ♦ [Section 8.11.2, "Configuring Properties for Found Elements," on page 173](#)



8.11.1 Configuring Search Parameters


To configure search parameters:

- 1 To search for elements, enter the element name or a portion of the name and a wildcard (*), then click *Search*.

This is the default type of search.

Define other types of searches using the search parameters.

- 2 To set search parameters, click  *Options* and select  *Preferences*.
- 3 Click the *Search* tab, then click the *Configuration* tab:



- 4 Configure the following options that are available to portlet users:

Element Name Label: Creates a label that shows next to the element name field.

Property: (Optional) Creates a new search field on the specified element property. Type the property name as it appears in Operations Center. Also specify a text description of the property in the *Property Label* field; this can aid users in knowing what to enter for the search.

To look up a property name in the Dashboard, use the [Element Properties](#) portlet or [Information](#) portlet. For information on looking up element properties in the Operations Center console, see [“Viewing Element Properties”](#) in the *Novell Operations Center 5.0 User Guide*.

Enable Max Results option: (Optional) Provide users with the option of setting a maximum number of results before conducting the search.

Max Results Label: (Optional) Add a text description for the Max Results option. The description displays on the Search portlet. Defaults to *Max Results* when not specified.

5 To narrow the search, add the following search constraints:

Class: To limit the search to elements of a specific class, enter the class name as it appears in Operations Center. The search results include elements in that class only. For more information about classes, see the [Novell Operations Center 5.0 Service Modeling Guide](#).

Condition: To limit the search to elements of a specific condition, enter the condition as it appears in Operations Center. For more information on element conditions, see [Managing Condition/Severity Colors](#) in the [Novell Operations Center 5.0 User Guide](#).

Scope: Restrict the search to only the top level at which the element is first found by selecting ONELEVEL. To include child elements of the first found element, select *SUBTREE*.

Depth: Select the number of levels to search for elements. The default is 10.

Timeout: To prevent the search from running indefinitely, add a timeout value as the number of minutes. The default is 1.

Default Results: The number of search results to display. Defaults to 20. If set to 0, then no limit is set and all results are returned.

TIP: Consider implementing options that sets limits on search results. Restricting the search results can be helpful to reduce the amount of time it takes for users to obtain results.


6 Click *Save*.

8.11.2 Configuring Properties for Found Elements

By default, elements found using the Search portlet display the element condition, including both the condition severity text and associated color. Other properties associated with an element in the Operations Center server might also be displayed.

For information on properties in Operations Center, see [Viewing Element Properties](#) in the [Novell Operations Center 5.0 User Guide](#). For instructions on creating custom element properties for service model elements, see [Defining Properties for a Property Page](#) in the [Novell Operations Center 5.0 Service Modeling Guide](#).

Figure 8-13 Search Portlet with Eleven Results





NAME	Condition	Last Updated
NYC-Alpha-2	MAJOR	Wed Nov 03 09:22:14 EDT 2010
NYC-Alpha-1	OK	Wed Nov 03 09:26:32 EDT 2010
NYC-7513-1	MAJOR	Wed Nov 03 09:24:28 EDT 2010
mcddb73	OK	Mon Nov 01 14:44:21 EDT 2010
mcddb75	OK	Mon Nov 01 14:44:21 EDT 2010
mcddb75	OK	Wed Nov 03 08:44:14 EDT 2010
mcddb75	OK	Mon Nov 01 14:44:22 EDT 2010
mcddb75	OK	Mon Nov 01 14:44:31 EDT 2010
mcddb73	OK	Mon Nov 01 14:44:31 EDT 2010
mcddb75	OK	Mon Nov 01 14:44:31 EDT 2010
mcddb75	OK	Mon Nov 01 14:44:32 EDT 2010


To configure properties for found elements:

- ◆ [“Adding Properties Displayed in Search Results”](#) on page 174
- ◆ [“Setting the Order in Which Properties are Displayed”](#) on page 175

Adding Properties Displayed in Search Results

To add properties displayed for elements found after a search:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Search* tab, then click the *Add Properties* tab:



The screenshot shows the 'Add Properties' configuration page within the 'Search' interface. The page has a header with 'Search' and 'Return to Full Page' (with a green arrow icon). Below the header are tabs for 'Search', 'Element', and 'Advanced'. Underneath are sub-tabs for 'Configuration', 'Current', and 'Add Properties'. The main content area contains several input fields: 'Property Name*' (Required), 'Operations Center Property*' (Required), 'Text Before:' (Text to show before the property value (e.g. \$)), and 'Text After:' (Text to show after the property value (e.g. %)). There is a checkbox labeled 'Highlight property background when the following conditions are met'. Below this checkbox, there is a dropdown menu with '>' selected, a text input field containing '100' (with the note 'Enter value to compare.'), and another dropdown menu with 'CRITICAL' selected. At the bottom of the form is an 'Add Property' button.

- 3 Specify the following options:

Property Name: Enter the name to display in the column to describe the property. This field is required. It can be any text.

Operations Center Property: Enter the property name as it appears in Operations Center. The name is required, is case-sensitive and must match exactly.

To look up a property name in the Dashboard, use the [Element Properties](#) portlet or the [Information](#) portlet. For information on looking up element properties in the Operations Center console, see "[Viewing Element Properties](#)" in the [Novell Operations Center 5.0 User Guide](#).

Text Before: To display anything before the property value, such as a dollar sign (\$), enter it here.

Text After: To display anything after the property value, such as a % sign, enter it here.

- 4 Specify the following check box options:

Highlight property background when the following conditions are met: If enabled, use the selectors to set a value at which the background is highlighted, then specify a background color.

The colors are mapped to conditions on the Operations Center console. For more information, see [Managing Condition/Severity Colors](#) in the [Novell Operations Center 5.0 User Guide](#).

- 5 Click *Add Property*.
- 6 Click the *Current* tab to specify the display order for the new property.
- 7 Click *Add Property*.

Setting the Order in Which Properties are Displayed

To set the order that the properties are displayed and edit the properties displayed:

- 1 Click the *Current* tab:



- 2 After selecting properties to display for elements found after a search, edit a property by clicking *Edit Property*.

The options are the same as when you added the property. The properties display in a table after the search is complete according to the order that they were added.

- 3 Click the up and down arrows next to the property to change the order.
- 4 Click *Save* after making any changes.
- 5 To remove a property, select it, then click *Remove*.

WARNING: This option cannot be undone. When you remove a property, you must add it again in order to see it in the portlet.


- 6 Click *Update* to save all changes.

8.12 Configuring the Show Impacted Portlet

The Show Impacted portlet shows the elements that are affected by the current state of the selected element in both a summary view and a detailed view.

The Show Impacted portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Tree Map, Element Properties, Properties Table, Root Cause, Chart Builder, Performance and Summary. Click *Actions* and select *Go to > Impacted* from any of these portlets.



Figure 8-14 Show Impacted Portlet Displaying Impacted Component with Display Notes Selected



Element state is indicated by a status icon, the color of which corresponds to the element's current condition that is mapped to colors in the Operations Center server. For more information about element condition settings, see the [Managing Condition/Severity Colors](#) in the *Novell Operations Center 5.0 User Guide*.

Element details can vary by the type of element and the alarms associated with it. Details, which is a configuration turned off by default, can include the highest child condition, the highest alarm severity, the number of active alarms, the number of active critical alarms, and so on.

To configure the Impacted portlet/view:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Impacted* tab.
For portlets other than Show Impacted, the *Impacted* tab is found under the *Advanced* tab.
- 3 Select the *Display Notes* check box to display more details for each element.
- 4 Click *Save*.

8.13 Configuring the Starter Portlet

The element displayed on the Starter portlet is the starting element for all the portlets on the page. The Starter portlet initially shows the home element for the user.


You can select an icon to display as a status indicator for the element. The color of the icon identifies its current condition. The color is based on the colors set for condition in the Operations Center server. For more information, see [Managing Condition/Severity Colors](#) in the *Novell Operations Center 5.0 User Guide*.

Figure 8-15 Starter Portlet



To change the starting element for all portlets on the page:

- 1 On the Starter portlet, Click  *Options* and select  *Preferences*.
- 2 Click the *Advanced* tab, then click the *Elements* tab.



The current start element displays on the *Current Element(s)* tab.

- 3 Click the *Available Element(s)* tab.
- 4 Use the *Search* or *Navigate* tabs to locate, then select one or more elements.
- 5 Click *Add Element(s)*.
- 6 Click *Save*.
- 7 Click the *Navigation* tab to select the status indicator icon.

- 8 Specify the following options:

Height: Enter the size of the portlet height in pixels. For example, enter *300px*.

Status Indicator: Select a diamond, square, oval, or arrow for the type of icon to display the current condition. Click *None* to not display any status indicator icon.

Element Link Behavior: Specify the expected behavior when the user clicks on an element name. Select *Expand Only* to drill-down in the element hierarchy tree, select *Drive Only* to update other portlets with the element's information, or select *Expand and Drive* for both behaviors.

- 9 Select the *Refresh portlet when updates occur* option to allow the Dashboard to receive [automatic updates](#) from the Operations Center server as content changes occur. Selected by default; deselect to manually control updates.
- 10 Click *Save*.

8.14 Configuring the Status Portlet

The Status portlet shows the current condition of one or more elements. The condition color is the same severities as shown on the Operations Center console. For more information about element condition and the color indicators, see *Managing Condition/Severity Colors* in the *Novell Operations Center 5.0 User Guide*.

The Status Portlet can also be used to set the starting element for other portlets on the Web page, similar to the [Navigation portlet](#). To configure the Status portlet to drive other portlets, see [Section 8.14.2, “Configuring the Status Portlet,” on page 179](#) and [Section 7.3.2, “Configuring Starting Elements for Portlets,” on page 110](#).

Figure 8-16 Status Portlet



- ♦ [Section 8.14.1, “Viewing the Status Portlet,” on page 178](#)
- ♦ [Section 8.14.2, “Configuring the Status Portlet,” on page 179](#)

8.14.1 Viewing the Status Portlet



To view a Status portlet:


- 1 Hover the mouse over the name of the element to view any available element information or any menu options.
You might see the date and time that the element was last updated, notes for the element, and links to other components.
- 2 If the Status Portlet is being used as a driver portlet, click any element to update other portlets on the page.

8.14.2 Configuring the Status Portlet

You can configure the type of icon displayed shown on the Status portlet. By default, the condition is automatically updated when the element's condition changes in the Operations Center server. You can turn off this option in the preferences.

To configure the Status portlet:

- 1 On the portlet title bar, click  *Options* and select  (*Preferences*). Click the *Status* tab.



Note: For other portlets other than Status, the *Status* tab is found under the *Advanced* tab.

- 2 Specify the following options to configure the Status portlet to display the condition of an element:

Show Elements: Show selected elements only, selected elements with children elements, or selected elements children elements only. Regardless of the selection, the Dashboard implements user permissions as assigned in Operations Center. A user must have permission to view an element in order to see its status. For more information on permissions, see the [Novell Operations Center 5.0 Security Management Guide](#).

Status Indicator: Select a square, oval, or arrow for the type of icon to display the current condition. The default is a square.

Number of Columns: Enter a number and the portlet calculates how to display the elements using the specified number of columns. The default is 3.

Status Title: Specify a description for the portlet information in the Status Title text area. HTML coding is accepted in the text description. Use HTML for additional formatting, such as font style or line breaks. Select the *Hide title*. check box to use no description on the portlet.

Click the *Align Status Title* list, then select left, right, or center to display the descriptive text horizontally.

- 3 Select the following options to enable mouse-over options on elements:

Select the *Date/time of last update*. check box to show the last date and time that the element was updated, when the mouse hovers over the element.

Select the *Element notes*. check box to show all comments saved for the element on the Operations Center console, when the mouse hovers over the element. For more information on comments associated with elements, see [Monitoring Elements and Element State](#) in the *Novell Operations Center 5.0 User Guide*.

Select the *Links to view element in different portlet* option to show links to additional components, when the mouse hovers over the elements. Then expand the option to select the actual components to show links for. Click the *Advanced* tab to configure the options for each component.

- 4 Select the *Refresh portlet when updates occur* option to enable [automatic updates](#) of the condition of elements displayed. The condition of an element changes automatically when the condition changes in the Operations Center server. Deselect the check box to control updates manually.
- 5 Click *Save*.
- 6 Click the *Element* tab to select the elements to display.
- 7 For options to use the Status portlet to set the starting element of other portlets on the Web page, click the *Advanced* tab, then click the *Common* tab.


For information about making these configurations, see [Using Navigation Mode to Drive Multiple Portlets \(page 110\)](#).

- 8 Click *Save*.

8.15 Understanding the Summary Portlet

The Summary portlet shows the total number of alarms for the element. It also shows a breakdown of the number of alarms by severity as indicated by color in the pie chart. No actions can be taken in this portlet and there are no configuration options except to select the element to display.

Figure 8-17 Summary Portlet




8.16 Configuring the Tree Map Portlet

A tree map allows you to visualize data significance. The size of a square provides an indication of the data element's importance either by condition or alarm count. And, the color of each square represents its severity.

The Tree Map portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Element Properties, Properties Table, Show Impacted, Root Cause, Chart Builder, Performance, and Summary. Click *Actions* and select *Go to > Treemap* from any of these portlets.

Figure 8-18 Tree Map Portlet



- Section 8.16.1, “Changing the Tree Map Portlet Display,” on page 181
- Section 8.16.2, “Configuring the Tree Map,” on page 182



8.16.1 Changing the Tree Map Portlet Display


While viewing a Tree Map portlet, do the following options to change the display:

- 1 To hide elements based on their color, click the color in the color bar.
The color indicators for severity are set on the Operations Center console.
For more information, see [Managing Condition/Severity Colors](#) in the *Novell Operations Center 5.0 User Guide*.
- 2 Use the *Element Depth* list to specify the number of levels traversed to calculate the value for the weight of the element.
- 3 To change how the element is evaluated to determine the size of the square, click the *Size Area by* list to select between *Condition* or *Alarm Count*.
- 4 To drill down into the hierarchy, click the name in a square.

8.16.2 Configuring the Tree Map

To configure the Tree Map portlet/view:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Tree Map* tab.



Tree Map [Return to Full Page](#)

Treemap | Element | Advanced

Width: 400 Do not use %.

Height: 300 Do not use %.

Element Depth: 2 The number of levels to traverse in the element tree.

Size Area by: Condition Data used to determine the area for each element's rectangle.

Refresh portlet when updates occur.

Save Reset

For other portlets other than Tree Map, the *Tree Map* tab is found under the *Advanced* tab.

- 3 Specify the following options:

Width: Sets the width of the tree map within the portlet and is expressed as pixels. Set to *auto* to automatically allow the dashboard to set the width of the tree map. The default is 400.

Height: Sets the height of the tree map within the portlet and is expressed as pixels. Set to *auto* to automatically expand the height of the tree map and portlet as large as the page allows. The default is 300.

Element Depth: Sets the default number of levels the tree is traversed and the default depth option when viewing the tree map.

Size Area by: Sets the default weight value which determines the area for each element's rectangle in the tree map.

- 4 Select the *Refresh portlet when updates occur* option to enable [automatic updates](#) of the condition of elements displayed. The condition of an element changes automatically when the condition changes in the Operations Center server. Deselect the option to control updates manually.
- 5 Click *Save*.

9 SLA Reporting Portlets

This section describes how to use portlets that are designed to create reports using Service Level Agreement (SLA) data from Operations Center. For more information about SLAs, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#).

- ♦ [Section 9.1, “Understanding the SLA Reporting Portlets,” on page 183](#)
- ♦ [Section 9.2, “Configuring the SLA Compliance Portlet,” on page 185](#)
- ♦ [Section 9.3, “Configuring the SLA Status Portlet,” on page 192](#)

9.1 Understanding the SLA Reporting Portlets

The Service Level Manager (SLM) is required in Operations Center to store and use data related to SLAs. The SLM is a separate product that has its own licensing. For more information about the SLM, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#).

Reports related to SLA compliance and availability provide data on the compliance/health, availability, and downtime for Service Level Agreements and objectives. You can use predefined portlets in the Dashboard to create the following types of reports that use data related to SLAs compliance and availability:

- ♦ **SLA Compliance:** a detailed view that shows health, downtime, availability, outages, and breaches related to SLAs for specified elements over a specified interval of time.
- ♦ **SLA Status:** shows the compliance/availability from a status or summary perspective with links to SLA Compliance reports.

SLA data from Operations Center can also be accessed via the Alarm portlet and the Performance portlet. For more information about the Alarms Portlet, see [Section 8.1, “Configuring the Alarms Portlet,” on page 134](#). For more information about the Performance portlet, see [Section 8.7, “Configuring a Performance Portlet,” on page 157](#).

9.1.1 Generating SLA Report Portlets

The SLA-related portlets allow you to set when the report data is generated (for example, when the portlet receives new data from the Operations Center server). The options are:

- ♦ **Live:** Whenever the user clicks on the portlet, the report data is generated in real-time.
- ♦ **Scheduled:** You set when the portlet generates report data. Data is cached for better performance.
For more information about scheduling, see [Section 7.8.5, “Scheduling Portlets,” on page 126](#).
- ♦ **Ad hoc:** (*SLA Compliance Portlet only*) Allows a user to run a report again, on-the-fly, with new selections for time categories, date range/date interval and exception-based reporting options. These selections do not affect saved portal report setup and are not retained after the user logs out of the portal. See [Section 9.2.3, “Regenerating the Report with Ad-Hoc Options,” on page 191](#).

If you do not set a report to be either live or scheduled, the data in the report is current as of the time of the initial report display. For example, if the report is run at 4:16 p.m., all of the tabs show data as of 4:16 p.m.

9.1.2 SLA Report Portlet Options

These reports have the following helpful options for configuring SLA reporting:

- ♦ (*SLA Status Report Only*) Allow the user to select the element to use by configuring a Starter portlet, Navigation portlet, Search portlet, or Status portlet to dynamically control element selection for a SLA Status portlet implemented within the same portal page.

For more information about setting up user navigation to drive the *SLA Status* portlet, see [Section 9.3.3, “Setting Up User Navigation to Drive an SLA Status Portlet,”](#) on page 196.

- ♦ Report scheduling to set when data for the report is generated.

For more information about report scheduling, see [Section 7.8.5, “Scheduling Portlets,”](#) on page 126.

- ♦ (*SLA Compliance Report Only*) Allow the user to rerun the report with new selections for time categories, date range/date interval and exception-based reporting options.

For more information about ad-hoc options, see [Section 9.2, “Configuring the SLA Compliance Portlet,”](#) on page 185 and [Section 9.2.3, “Regenerating the Report with Ad-Hoc Options,”](#) on page 191.

- ♦ Time zone setting to customize data display for international users.


9.2 Configuring the SLA Compliance Portlet

The SLA Compliance portlet displays compliance/agreement health or availability/downtime data, outage counts, breaches counts, root cause, and a detailed listing of all outages and breaches for specified intervals of time.

Health/compliance, availability, or downtime for agreements and objectives (OLA) are shown in a calendar view. This report can include charts of the agreement health or downtime or availability, lists of outages, and lists of breaches. Data can be shown at various levels of detail (for example, year, month, week, day, hour, minute). The *Show Key Metric* feature can chart the objective value being measured as a percentage or inverted value.

The report portlet can reveal up to six reports, or tabs, of information for the user: *Compliance/Availability, Root Cause, Breaches, Details, Charts, and Outages*. These tabs can be hidden from display with report settings found in *Preferences*.




Figure 9-1 SLA Compliance Portlet showing the Compliance tab



For samples of other tabs in this report, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#)

Table 9-1 describes the icons and indicators that are used by the SLA Compliance to show levels of data availability, compliance, and relevance.

Table 9-1 Degrees of Data Availability and Relevance

Icons	Type	Description
	Data Available	Indicates the amount of data available for the measured period of time. Icons indicate specific value targets or ranges of values, such as 0%, 0.1%–33%, 33.1%–65.9%, 66%–99.9%, 100%.
	Compliance Grades	Indicates a level of compliance from A–F based on compliance percentage. Icons indicate the range where, by default, green is 80–100%, blue is 70–89%, yellow is 60–69%, orange is 50–59%, and red is any compliance less than 50%.
	Data Relevance	Indicates the relevancy of data to the reported period of time. For instance, there can be data available, but it is not considered (relevant) if the associated Time Category is filtered out (for example, a blackout). Icons indicate specific value targets or ranges of values, such as 0%, 0.1%–33%, 33.1%–65.9%, 66%–99.9%, 100%.

For more information about the data displayed in this report, particularly information about outage duration, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#)

Note the following tips and information when setting up the *SLA Compliance* report:

- ◆ There are three main types of reports: compliance/health, availability, and downtime. Each one has slightly different options to select in *Preferences*. When creating any of these reports, select a calendar from Operations Center to filter the display based on time category selection.
- ◆ To create a report on health and compliance, select the objective definition option for the calculation rules, then select an agreement and objective. For this type of report, the calendar for the agreement is always used. By default, the time defined in the objective is used to calculate compliance.
- ◆ For downtime reports, time category filtering does not affect the summary metrics.
- ◆ To allow users to change the calendar and other various report parameters on-the-fly, enable *Show Options*. The calendar appears as one of the options when the user clicks *Options*. In *Preferences*, you must select both the *Show Options* option and the *Show Calendar* option for the user to see both the *Options* link in the portlet view and the calendar within those options.
- ◆ When specifying a time span for any type of report, make sure to specify one that is reasonable for reporting. Users typically want to look at a year’s worth of data in months or weeks, rather than hours or minutes, with the ability to drill down into hours or minutes.
- ◆ The SLA Compliance portlet returns a maximum number of outages and breaches based on a property set on the Operations Center server. For instructions on configuring this property, see [Section 7.8.1, “Configuring Default Alarms Limits Returned from the Operations Center Server,” on page 124](#).
- ◆ Setup a schedule to run the report at specified intervals. Users view a cached version for improved performance. Cached versions are saved for the main tabbed reports. If drilling into data, views at that level are real-time and not cached.



For more information about scheduling, see [Section 7.8.5, “Scheduling Portlets,” on page 126](#).


The following sections cover how to configure the *SLA Compliance* portlet settings, using the portlet at run-time and ad-hoc options:

- ◆ [Section 9.2.1, “Setting Up the SLA Compliance Portlet,” on page 187](#)
- ◆ [Section 9.2.2, “Using the SLA Compliance Portlet,” on page 190](#)
- ◆ [Section 9.2.3, “Regenerating the Report with Ad-Hoc Options,” on page 191](#)


9.2.1 Setting Up the SLA Compliance Portlet

To configure the SLA Compliance Portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Elements* tab to select the element for the report to generate data on.
The default element selection is *Enterprise*. For more information on selecting the element, see [Section 7.3.2, “Configuring Starting Elements for Portlets,” on page 110](#).
- 3 Click the SLA Compliance tab to specify report parameters and options.
- 4 Configure the report title by doing the following:
 - ◆ Specify the report title in the *Report Title* field.



- ◆ Select the *Use default title* check box to use the default title for all displays.
 - ◆ Select the *Hide title* check box to not show a title in the report.
- 6 Under *Selected Element*, select whether the report is to be run for a specific agreement, or on availability, or downtime in the *Agreement* drop-down list.



- 6 If reporting on an agreement, select *All* or select a specific objective from the *Objective* drop-down list.

If a specific objective is selected, do any of the following:

- ◆ Select the *Calculate Health Using the Time Indicators as Objective Interval* check box to have the specified time indicators used as the interval over which the objective is evaluated to determine compliance.
- ◆ Select the *Display Key Metric Values* check box to use any of the following sub-options:
 - ◆ Select *Show Key Metric as a Percentage* check box to display the key metric as a percentage value.
 - ◆ Select *Show Inverse of Key Metric* check box to display the inverse value of the key metric.

7 If reporting on availability or downtime, do the following:

7a Click the *Calendar* drop-down list, then select a calendar.

The screenshot shows a configuration window for availability/downtime calculation rules. At the top, there are dropdown menus for 'Agreement' (set to 'Availability') and 'Calendar' (set to 'Default'). Below these is a link for 'Specify Availability/Downtime Calculation Rules: Hide'. Three radio buttons are present: 'Use Element Outages' (selected), 'Specify Outage Definition', and 'Apply the follow Agreement definition'. Under 'Specify Outage Definition', there is a text input for 'Minimum Outage Duration Of' with the value '0' and the unit 'seconds', and a dropdown for 'Outage Threshold Condition' set to 'CRITICAL'. Under 'Apply the follow Agreement definition', there are dropdowns for 'Agreement' (set to 'Bronze') and 'Objective'.

7b Specify Availability/Downtime calculation rules by selecting one of the following radio button options:

- ◆ **Use Element Outages** to calculate outages in the report.
- ◆ **Specify Outage Definition** which requires specifying a minimum outage duration and threshold condition.

Specify the minimum duration (in seconds) for outages to include in this report in the *Minimum Outage Duration* field.

Select the lowest severity level to include in this report from the *Outage Threshold Condition* list.


- ◆ **Apply Agreement Definition** which requires selecting an agreement and an objective. Select an agreement from the *Agreements* list. If the selected element has no associated agreements, then no agreement names display. Remote agreements are listed with the prefix "Remote."

Select an objective from the *Objective* list, or select *All* to display all objectives. If the selected agreement has no associated objectives, no objective names display.

8 Under *Time Control*, select one of the following time selectors:


The screenshot shows the 'Time Control' section with three radio buttons: 'Use Interval' (selected), 'Use Date Range', and 'Use Real-time'. Under 'Use Interval', there are options for 'Last 1 Days', 'This Hour', and a 'Display in Days' dropdown. Under 'Use Date Range', there are 'From' and 'To' fields with calendar icons and a 'Display in Days' dropdown.

Use Interval: Use the various options to select an interval range for the report to run against. Time intervals are always determined relative to the time that the report is run.

Use Date Range: Use the various options to select a specific start and end time for the report to run against. Click the  (*Calendar*) icon to select a date/time.

Use Real-Time: (Agreements only) Reports on real-time data (only available if reporting on health and compliance and an agreement is selected in the *Agreement/Availability* drop-down list).

9 Under *Time Categories*, indicate the time categories for the report to run against by selecting the check boxes.



10 Click the *Home Page* drop-down list, then select the tab for the report to use as the default report page.

11 Select any of the *Display Options* check boxes options to enable various report features:

Show Header Information: Displays the summary header information in the box at the top of each tab. The header information includes calendar and time category selections, overall health or downtime or availability metrics, and the overall data available and data relevance indicators.

Show Root Cause: Includes the *Root Cause* tab in the report. Only applies to health and compliance for Agreements.

Show Breaches: Includes the *Breaches* tab in the report. Only applies to health and compliance for Agreements. Also, select from the following options:

- ◆ **Show Objective Breaches:** Displays objective breaches in the *Breaches* tab.
- ◆ **Show Major Breaches:** Displays major condition breaches, which are breach warning alarms, in the *Breaches* tab.
- ◆ **Show Cleared Breaches:** Displays cleared breaches in the *Breaches* tab. Excluding cleared breach alarms eliminates all warning and violation breaches associated with a cleared breach alarm. Only applies to health and compliance reports.
- ◆ **Show Breach List:** Displays a detailed list of all breaches in the *Breaches* tab. By default, shows breach violations (CRITICAL) only. Includes cleared and warning (MAJOR) breaches based on *Show Cleared Breaches* and *Show Major Breaches* selections. Only applies to health and compliance reports.

Show Details: Includes the *Details* tab in the report. Only applies to health and compliance for Agreements.

Show Charts: Includes the *Charts* tab in the report.

Show Outages: Displays the *Outages* tab. Also, select from the following options:

- ◆ **Show outages not generated by element condition changes:** Includes manually entered or imported outages, as well as system generated outages (for example, based on real-time state data) when reporting on downtime, availability, and agreement or objective health.
- ◆ **Show Outages List:** Displays a detailed list of outages in the *Outages* tab. Outages include only those outages that start in the report interval.

Show Options: Displays options for the user viewing the report to change the time intervals and time categories in the report.

- ◆ **Show Calendar:** Displays a calendar under *Options* that allows users to select to run the report using a different calendar than the one selected in Edit mode. *Show Options* must be selected for this option to have any effect.

Show PDF Link: Displays a link to save the report in PDF format.

- 12 Click the *Report Time Zone* drop-down list, then select the time zone for the report to use in presenting data.
- 13 Click *Save*.




If you exit *Preferences* without clicking *Save* first, your changes are lost.


- 14 If this report is to be run automatically on scheduled intervals, click *Advanced*, then click *Scheduling* to configure the report to run at regular intervals.

For more information about *Scheduling*, see [Section 7.8.5, “Scheduling Portlets,” on page 126](#).

9.2.2 Using the SLA Compliance Portlet

While viewing the *SLA Compliance* portlet, do any of the following:

- ◆ Click any of the available tabs (*Compliance*, *Details*, *Chart*, *Outages*, *Breaches*, or *Root Cause*) to change the display to that view.
- ◆ Click *Next/Previous* to navigate to the next or the previous time period for the given report.
- ◆ Click  to return to the default home view of the *SLA Compliance* report as defined in *Preferences*.
- ◆ Click  to print the report.
- ◆ Click  to save the report as a PDF file.
- ◆ Click *Objectives* to view objectives related to the SLA. A tool tip displays with information on the objectives. Click the icons to view compliance, root cause, breaches, details or charts for the objective.



- ◆ Click *Options* to runs an ad hoc query. The *Options* panel opens, as shown in the following figure:

Options

Report on:

On

Peak

Non-Peak

OFF

Blackout

Critical

Calendar Default

Use Interval

Use Date Range

Use Real-time

10/13/2010 11:02:54 AM To

10/29/2010 11:02:57 AM

and report in Days

Run

For more information, see [Section 9.2.3, “Regenerating the Report with Ad-Hoc Options,”](#) on page 191.

9.2.3 Regenerating the Report with Ad-Hoc Options

While viewing the *SLA Compliance* portlet, there are various on-the-fly options that can be used to modify and rerun the report. These options are available if *Show Options* is enabled in *Preferences*.

The *Options* selections do not change the original report options as set in *Preferences* or *Scheduling*. They are used only for the immediate view. When the view is changed or the session expires, these selections are not retained.

To change the time categories, calendar or reporting ranges for the portlet:

- 1 Click the *Options* link.
- 2 Use the *Report On* check boxes to select or clear any time categories.
- 3 Click the *Calendar* drop-down list, then select a calendar to use for filtering time categories.
- 4 Select one of the following radio buttons to adjust the time reported on:
 - ◆ **Use Interval** to select a date interval, such as the last 30 days.
 - ◆ **Use Date Range** to select a date range.
Select the time to report on: minutes, hours, days, weeks, months, or years.

- ♦ Use **Real-Time** to report on real-time data (only available if reporting on health and compliance for an agreement).

5 Click *Run* to run the report with the new selections.

9.3 Configuring the SLA Status Portlet

The *SLA Status* portlet displays a status summary on agreement health, availability, or downtime for the selected element's children during the specified time frames. This report uses the same data as an *SLA Compliance* portlet and includes access to SLA Compliance reports by clicking any of the metrics.

Figure 9-2 The SLA Status Portlet

The screenshot shows the 'SLA Status' portlet interface. At the top, it says 'Availability for All IT' with time categories 'Critical, Peak, On, Non-Peak, OFF' and a 'Last updated' timestamp. Below this is a 'Refresh' button. The main part of the portlet is a table with columns for 'Today', 'Yesterday', 'This Week', 'Last Week', 'This Month', 'Last Month', 'This Quarter', 'Last Quarter', 'This Year', and 'Last Year'. The rows represent different IT services: 'All IT', 'DocumentManagement', 'Email', 'ERP', and 'Web'. Each cell in the table contains a percentage value and a small green or red arrow indicating a trend. For example, 'All IT' shows 74.519% today, which is a decrease from 61.758% yesterday. 'DocumentManagement' shows 100% availability across all periods. 'Email' shows 74.514% today, a decrease from 61.758% yesterday. 'ERP' shows 100% availability across all periods. 'Web' shows 100% availability today and yesterday, but a decrease to 97.009% last week. The 'Last Year' column for all rows is 'NA'. At the bottom of the portlet, there are two footnotes: '*NA* for all time categories indicates that objective might be disabled.' and '*<' indicates that the results are rounded to 100%'.

	Today	Yesterday	This Week	Last Week	This Month	Last Month	This Quarter	Last Quarter	This Year	Last Year
All IT	74.519% ↓	61.758% ↓	86.24% ↓	63.975% ↓	97.876% ↓	55.403% ↓	84.28% ↓	99.731% ↓	95.97% ↓	NA
DocumentManagement	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	NA
Email	74.514% ↓	61.758% ↓	86.238% ↓	65.648% ↓	97.876% ↓	62.523% ↓	86.679% ↓	100% ↑	96.642% ↓	NA
ERP	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	100% ↑	99.731% ↓	99.932% ↓	NA
Web	100% ↑	100% ↑	100% ↑	97.009% ↓	100% ↑	88.317% ↓	96.063% ↓	100% ↑	99.008% ↓	NA

The *SLA Status* portlet can also display child availability and child downtime. Detailed information in this report shows outages, downtime, availability, committed time, downtime contributed (as a percent), and outages contributed (as a percent) for leaf children.

Note the following tips and information when setting up the *SLA Status* report:

- ♦ When configuring the report, decide whether the user of the report can see only that element (selected element option) or that element and its children (viewable elements option). The elements that the user can view are governed by privileges set in Operations Center.
- ♦ When reporting on child availability and downtime, you must select a calendar to use to calculate values. You must also select to define outages as either element outages, outages based on a minimum duration and threshold that you set, or apply an SLA agreement and objective.
- ♦ In contrast to the *SLA Compliance* portlet, instead of selecting a use interval or data range, you select the time periods for which data displays and whether an arrow or status box displays.
- ♦ Setup a schedule to run the report at specified intervals. Users view a cached version for improved performance.



For more information about scheduling, see [Section 7.8.5, "Scheduling Portlets,"](#) on page 126.


The following sections cover how to configure the *SLA Status* settings, using the portlet and user navigation options:

- ♦ [Section 9.3.1, "Setting Up the SLA Status Portlet,"](#) on page 193
- ♦ [Section 9.3.2, "Using the SLA Status Portlet,"](#) on page 196
- ♦ [Section 9.3.3, "Setting Up User Navigation to Drive an SLA Status Portlet,"](#) on page 196

9.3.1 Setting Up the SLA Status Portlet

To configure the SLA Status Portlet:

- 1 Click  *Options* and select  *Preferences*.
- 2 Click the *Elements* tab to select the element(s) for the report to generate data on.
The default element selection is *Enterprise*. For more information on selecting the element, see [Section 7.3.2, “Configuring Starting Elements for Portlets,” on page 110](#).
- 3 Click the SLA Status tab to specify report parameters and options.
- 4 Select whether the report is to be run for selected elements only, selected specific elements including children, or the children of the selected elements from the *Show Elements* drop-down list.
- 5 For each selected element, do the following:
 - 5a Select whether the report is to be run for a specific agreement, or on availability or downtime in the *Agreement* drop-down list.
 - 5b If reporting on an agreement, do the following:



- 5b1 Select *All* or select a specific objective from the *Objective* drop-down list.
- 5b2 Select the *Display objective's Threshold column* check box to a threshold reference value in the report.
Define the desired threshold value that must be reached for the selected objective, in the *Objective Threshold* text box. This value is displayed in the Threshold column as a reference only.
- 5b3 If a specific objective is selected, define reporting and calculation rules with the following options:
 - ◆ Select the *Calculate health using time indicators as objective interval* check box to have the specified time indicators used as the interval over which the objective is evaluated to determine compliance.
 - ◆ Select the *Display key metric values* check box to use any of the following sub-options:
 - ◆ Select *Show key metric as a percentage* check box to display the key metric as a percentage value.
 - ◆ Select *Show inverse of key metric* check box to display the inverse value of the key metric.
- 5c If reporting on availability or downtime (including child availability/downtime), do the following:

5c1 Click the *Calendar* drop-down list, then select a calendar.

5c2 Specify availability/downtime calculation rules by selecting one of the following radio button options:

- ◆ **Use Element Outages** to calculate outages in the report.
- ◆ **Specify Outage Definition** which requires specifying a minimum outage duration and threshold condition.

Specify the minimum duration (in seconds) for outages to include in this report in the *Minimum Outage Duration* field.

Specify the lowest severity level to include in this report in the *Outage Threshold Condition* list.

- ◆ **Apply Agreement Definition** which requires selecting an agreement and an objective. This option is unavailable for Child Availability and Child Downtime.

Select an agreement from the *Agreements* list. If the selected element has no associated agreements, then no agreement names display. Remote agreements are listed with the prefix "Remote."

Select an objective from the *Objective* list, or select *All* to display all objectives. If the selected agreement has no associated objectives, no objective names display.

5c3 (Child Availability and Child Downtime only) Specify the levels of children used in the availability and downtime calculation:

- ◆ **Children in hierarchical structure:** Select how many levels of children that naturally exist in the hierarchy, regardless of whether they contribute to the state of the parent element, that contribute to the calculation.
- ◆ **Children contributing to state:** Select how many levels of children that contribute to state but are not natural children of the element (have been matched or linked under the element), that contribute to the calculation.

6 Under *Time Categories*, indicate the time categories for the report to run against by selecting the associated check boxes.

- 7 Configure the report title by doing the following:
 - ◆ Specify the report title in the *Title* field.
 - ◆ Select the *Use Default Title* check box to use the default title for all displays.
 - ◆ Select the *Hide title* check box to not show a title in the report.
- 8 Click the *Report Time Zone* drop-down list, then select the time zone for the report to use in presenting data.
- 9 Configure the indicator values to show for each element using the options under *Status Indicators*:
 - ◆ Include *Real Time, Today, Yesterday, This Week, Last Week, This Month, Last Month, This Quarter, Last Quarter, This Year, and Last Year* values by leaving the *Hide indicator* check boxes unselected.
 - ◆ Select *None, Arrow* or *Status* from the *Indicator* drop-down lists to specify the type of indicator show with each value.
 - ◆ Select the *Do not show actual values within acceptable threshold limits. Display as "<100%"* check box to display availability that is slightly less than 100% as <100% (with a down arrow).
- 10 Select the *Show PDF/Excel export links* option to include options to export the report information.
- 11 Click the *Home Page* drop-down list, then select the tab for the report to use as the default report page when displaying a *SLA Compliance* report.
- 12 Select the *Open SLA Compliance information in new window* check box to open the related SLA Compliance report in a pop-up window. If this option is unselected, SLA Compliance reports open in the same page.
- 13 Select the following check boxes to enable various report features shown in the *SLA Compliance* views:
 - Show Header Information:** Displays the summary header information in the box at the top of each tab.
The header information includes calendar and time category selections, overall health or downtime or availability metrics, and the overall data available and data relevance indicators.
 - Show Root Cause:** Includes the *Root Cause* tab in the report. Only applies to health and compliance for Agreements.
 - Show Breaches:** Includes the *Breaches* tab in the report. Only applies to health and compliance for Agreements. Also, select from the following options:
 - ◆ **Show Objective Breaches:** Displays objective breaches in the *Breaches* tab.
 - ◆ **Show Major Breaches:** Displays major condition breaches, which are breach warning alarms, in the *Breaches* tab.
 - ◆ **Show Cleared Breaches:** Displays cleared breaches in the *Breaches* tab. Excluding cleared breach alarms eliminates all warning and violation breaches associated with a cleared breach alarm. Only applies to health and compliance reports.
 - ◆ **Show Breach List:** Displays a detailed list of all breaches in the *Breaches* tab. By default, shows breach violations (CRITICAL) only. Includes cleared and warning (MAJOR) breaches based on *Show Cleared Breaches* and *Show Major Breaches* selections. Only applies to health and compliance reports.
 - Show Details:** Includes the *Details* tab in the report. Only applies to health and compliance for Agreements.
 - Show Charts:** Includes the *Charts* tab in the report.

Show Outages: Displays the *Outages* tab. Also, select from the following options:

- ♦ **Show Outages Not Generated by Element Condition Changes:** Includes manually entered or imported outages, as well as system generated outages (for example, based on real-time state data) when reporting on downtime, availability, and agreement or objective health.
- ♦ **Show Outages List:** Displays a detailed list of outages in the *Outages* tab. Outages include only those outages that start in the report interval.

Show Options: Displays options for the user viewing the report to change the time intervals and time categories in the report.

- ♦ **Show Calendar:** Displays a calendar under *Options* that allows users to select to run the report using a different calendar than the one selected in Edit mode. *Show Options* must be selected for this option to have any effect.

14 Click *Save*.



If you exit *Preferences* without clicking *Save* first, your changes are lost.

15 If this report is to be run automatically on scheduled intervals, click *Advanced*, then click *Scheduling* to configure the report to run at regular intervals.

For more information about *Scheduling*, see [Section 7.8.5, “Scheduling Portlets,”](#) on page 126.

9.3.2 Using the SLA Status Portlet

While viewing the *SLA Status* portlet, do any of the following:

- ♦ Click *Refresh* to update the data in the view. Only real-time data is refreshed in the view. Scheduled reports update the next time the schedule job runs.
- ♦ To navigate between *SLA Status* views, do the following:
 - ♦ Click an element name to drill-in to an SLA Status report for child elements.
 - ♦ Click the *Up* link to return to the parent SLA Status report.
 - ♦ Click  to return to the default home view of the *SLA Status* report as defined in *Preferences*.
 - ♦ Click  to save the report as a PDF file.
- ♦ Click any metrics value to view the *SLA Compliance* report.

For more information on the *SLA Compliance* report, see [Section 9.2, “Configuring the SLA Compliance Portlet,”](#) on page 185.

9.3.3 Setting Up User Navigation to Drive an SLA Status Portlet

If you use the *SLA Status* portlet on a page, you can also add and configure a [Starter portlet](#), [Navigation portlet](#), [Search portlet](#), or [Status portlet](#) to dynamically control element selection for a *SLA Status* portlet implemented within the same portal page.

For *SLA* portlets, you’ll configure a default element(s) but in addition, you can set up a [Starter portlet](#), [Navigation portlet](#), [Search portlet](#), or [Status portlet](#) on the same page can also allow users the ability dynamically change the element selection that drives data in the *SLA* portlet.

These portlets can be used to create a single page to report on multiple services for a single user, or to create a single page for multiple role-based users, or to produce a single page that supports multiple end users who have different data access privileges. It eliminates the need to create multiple customers without having to create separate portal pages for everyone.

For more information, see [Section 7.4, “Using Navigation Mode to Drive Multiple Portlets,”](#) on [page 110](#) or the section on each portlet type:

- ◆ [Section 8.13, “Configuring the Starter Portlet,”](#) on page 176
- ◆ [Section 8.6, “Configuring the Navigation Portlet,”](#) on page 156
- ◆ [Section 8.11, “Search Portlet,”](#) on page 171
- ◆ [Section 8.14, “Configuring the Status Portlet,”](#) on page 178

10 Chart Builder Portlet

The Chart Builder portlet allows you to build and deploy charts containing data from Operations Center that meet the reporting needs of your organization.

The Chart Builder portlet is also available as a view from other Operations Center portlets including Alarms, Summary, Layout, Element Properties, Properties Table, Show Impacted, Tree Map Root Cause, Performance, and Summary. Click *Actions* and select *Go to > Chart Builder* from any of these portlets.

The Chart Builder functionality relies on the Image server for delivery of charts. For more information about the Image server settings in the Configuration Manager, see [Section 2.2.1, “Verifying Your Operations Center Server’s Default Accounts and Configuration Settings,”](#) on page 14 and [Section 2.2.5, “Configuring the Dashboard and Operations Center,”](#) on page 20. For more information about using and configuring the Image Server, see “Image Server Pane” and “Using the Image Server” in the *Novell Operations Center 5.0 Server Configuration Guide*.

The Chart Builder portlet also requires an SVG view to render properly in IE. For more information about the SVG Viewer, see [Section 7.9.1, “SVG Viewer,”](#) on page 132. Chart Builder does not support SVG rendering for Mozilla Firefox; users must select Flash, PNG, or JPG to view data through Chart Builder.

Charts use templates that leverage data from Operations Center. Templates are PCXML files that use the [Operations Center JSP tag libraries](#) to incorporate data from Operations Center. The Dashboard has predefined templates that are ready to use, or you can create your own custom templates.

- ♦ [Section 10.1, “Predefined Templates,”](#) on page 199
- ♦ [Section 10.2, “Custom Templates,”](#) on page 205

10.1 Predefined Templates

Predefined templates show the following types of data:

- ♦ Alarm counts in pie or bar charts
- ♦ SLA status in a dashboard
- ♦ Status and location of an element on a map chart
- ♦ Numeric element properties in a speedometer gauge

These templates can be added to a Web page by using the Chart Builder portlet.

All Chart Builder templates automatically contain a *d* link added to the bottom right corner of the portlet that allows the user to view the source data used to generate the chart. For more information about viewing source data, see [Section 7.7, “Viewing Source Data for Charts,” on page 122](#)

The following sections show examples of the predefined templates included with the Dashboard and provide steps for deploying charts and configuring the SLA Status Dashboard:

- ♦ [Section 10.1.1, “Chart Display Examples,” on page 200](#)
- ♦ [Section 10.1.2, “Deploying Charts,” on page 203](#)
- ♦ [Section 10.1.3, “Setting Up the SLA Status Dashboard,” on page 204](#)

10.1.1 Chart Display Examples

The following sections show examples of the different types of displays:

- ♦ [“Alarms Charts” on page 200](#)
- ♦ [“Map Chart” on page 202](#)
- ♦ [“Element Properties Gauge” on page 202](#)
- ♦ [“SLA Status Dashboard” on page 203](#)

Alarms Charts

By default, there are four types of charts that show alarm data.

- ♦ Element Alarms Pie Chart, as shown in [Figure 10-1 on page 200](#)
- ♦ Child Element Alarms Bar Chart, as shown in [Figure 10-2 on page 201](#)
- ♦ Element Alarms Bar Chart, as shown in [Figure 10-3 on page 201](#)
- ♦ Element Alarms Radar and Pie Chart, as shown in [Figure 10-4 on page 201](#)

The user can click the *d* link located in the bottom right corner of the portlet to view data used to generate the chart.

Figure 10-1 Element Alarms Pie Chart in the Chart Builder Portlet




Figure 10-2 Child Element Alarms Bar Chart in the Chart Builder Portlet




Figure 10-3 Element Alarms Bar Chart in ChartBuilder Portlet






Figure 10-4 Element Alarms Radar and Pie Chart in Chart Builder Portlet



Map Chart

The Map Chart template shows a map from the *Locations* hierarchy tree in Operations Center with drill-down to show alarm charts. The user can click the *d* link located in the bottom right corner of the portlet to view data used to generate the chart.


Figure 10-5 Maps with Drill-down URL in the Chart Builder Portlet



Element Properties Gauge

The Element Properties Gauge template shows element property information in a gauge speedometer. The user can click the *d* link located in the bottom right corner of the portlet to view data used to generate the chart.


Figure 10-6 Element Property Gauge in Chart Builder Portlet



SLA Status Dashboard

The SLA Status Dashboard template shows service level agreement status information including breach and outage counts overlaid with health, downtime, availability and cost impact levels. The user can click the *d* link located in the bottom right corner of the portlet to view data used to generate the chart.

Figure 10-7 SLA Status Dashboard in the Chart Builder Portlet



10.1.2 Deploying Charts

Charts are deployed and configured by using the Chart Builder portlet in the Dashboard.

If some of the chart elements overlap after you configure the chart, increase the chart width.

To configure the Chart Builder Portlet:

- 1 Add the Chart Builder portlet to a web page.
For more information on adding a portlet to a page, see [Section 6.2.1, “Adding a Portlet,”](#) on page 95.
- 2 Click the Configuration icon and select *Preferences*.

The configuration window shows the following settings:

- Selected element is: `childElementBarAlarms.jsp`
- Select Template File: `childElementBarAlarms.jsp`
- Chart Width: 540
- Chart Height: 330
- Chart Output: FLASH

Buttons: Save, Manage...

- 3 Select a .jsp template from the drop-down list to specify the chart type.
The PCXML files are samples, or templates, that administrators use to create a new chart. They are not fully coded to show custom static data or dynamic information from Operations Center. Click *Manage* to upload a new chart template from your file system.
- 4 Specify the chart width in the *Chart Width* field.
- 5 Specify the chart height in the *Chart Height* field.
- 6 Click the *Chart Output* drop-down list, then select the output type.
- 7 Specify other chart options as required, such as the chart title.
For specific information about running the SLA Status Dashboard template example, see [Section 10.1.3, “Setting Up the SLA Status Dashboard,” on page 204.](#)
- 8 Click *Save* to save the chart settings.
- 9 Click to open the *Elements* tab and select an element to drive the portlet.
- 10 Click *Save* to save the element selection.

10.1.3 Setting Up the SLA Status Dashboard

The SLA Status Dashboard uses data from the Service Level Manager (SLM) in Operations Center and has different configuration options. Using this chart requires a license for SLM. For more information about SLM and SLA data, see the [Novell Operations Center 5.0 Service Level Agreement Guide](#).

Cleared breaches can be included in the Dashboard, even if they are not included in the summary metrics and statistics. This can occur when a breach is cleared on a day that is not included in the reported interval.

To set up custom chart options for the SLA Status Dashboard template:

- 1 Follow the basic directions to setup the Chart Builder portlet and use the *Elements* tab to select an element to drive the portlet. See [Section 10.1.2, “Deploying Charts,” on page 203.](#)
- 2 Click *Select SLA Root Element* to select the element with the associated SLA.
- 3 Select the *Time Control* value by using one of the following time selectors:
 - Use Interval:** Use the options to select an interval range for running the report. Time intervals are always determined relative to the time that the report is run.
 - Use Date Range:** Use the options to select a specific start and end time to include in the report. Click the *(Calendar)* icon to select the date/time.
 - Use Real-Time:** Reports on real-time data.
- 4 To specify an agreement name in the *SLA* field, click *SLA* to browse, then select an applicable agreement:
 - ♦ **None:** Shows information for an element.
 - ♦ **Objective:** Shows information for an objective. First, select an option, then specify the objective in the *Objective* option.

If no agreement is selected, the health displays as 100 with 0 breaches existing (if breaches are selected to display).

- 5 To specify an objective in the *Objective* field, click *Objective* to browse and select an applicable objective:
 - ♦ To show information for an element, specify *None*.
 - ♦ To show information for an agreement, specify *None*, then specify the agreement in the *SLA* option.
- 6 Select the appropriate *Time Categories* check boxes.
- 7 Specify a title in the *Chart Title* field.
- 8 Select the *Show Overall Cost Calculation* check box to include a cost total amount in the portlet display.
- 9 Set the options to configure the cost calculation:
 - 9a Click *Calculate Cost Metric Using Each* drop-down list, then select the metric that drives the cost calculation.
 - 9b Specify a *Cost Impact Per Metric Instance Number* to facilitate cost calculations.
 - 9c Specify an *OverAll Cost Multiplier Number* to multiply the cost impact per metric instance.
- 10 Select one or more of the following check boxes to customize the display:
 - Show Costs in Chart:** Cost values.
 - Show Health in Chart:** Health indicators. If no agreement is selected, health displays as 100%.
 - Show Availability in Chart:** Availability data.
 - Show Downtime in Chart:** Downtime data. Click the *Show Downtime In* drop-down list, then select the interval display for downtime data.
 - Show Outages in Chart:** Outages.
 - Show Outages Not Generated by Element Condition Changes:** Manually created outages.
 - Show Breaches in Chart:** Breaches. If no agreement is selection, no breaches display.
 - Show Cleared Breaches:** Cleared breaches.
 - Show Warning Breaches:** Warning breaches.
 - Show the Last Updated Date/Time:** Date and time of the last data update.
- 11 Click *Save* to save the chart settings.

10.2 Custom Templates

Custom templates are made in the Corda Builder tool, then deployed by using Chart Builder portlet. You create a template by making a PCXML file, then incorporating data from Operations Center by using JSP tags. When a template is created, it can be uploaded to the Chart Builder portlet and configured to appear on a Web page.

- ♦ [Section 10.2.1, “Creating the Template File,” on page 206](#)
- ♦ [Section 10.2.2, “Integrating Operations Center Data,” on page 209](#)
- ♦ [Section 10.2.3, “Creating Drill-Down URLs for a Chart,” on page 211](#)
- ♦ [Section 10.2.4, “An Example: Modifying a PCXML File with JSP Tags,” on page 211](#)
- ♦ [Section 10.2.5, “Uploading New Templates,” on page 213](#)
- ♦ [Section 10.2.6, “Deleting Templates,” on page 213](#)

10.2.1 Creating the Template File

APCXML file is created using Corda Builder*, a wizard-based tool, which is later with JSP tags to leverage data from Operations Center.

Chart Builder templates use Velocity*, a templating mechanism. To learn more about Velocity, go to the [Apache Velocity Project \(http://velocity.apache.org/\)](http://velocity.apache.org/).

The following sections cover how to create a new chart for the Chart Builder portlet.


- ♦ “Creating a Chart” on page 206
- ♦ “Modifying Chart Settings and Properties” on page 208
- ♦ “Modifying Map Settings and Properties” on page 208

Creating a Chart

To create a chart by using the chart wizard:

- 1 In the Operations Center installation directory, browse to and launch the / *OperationsCenter_install_path/image/bin/CordaBuilder* executable.

The Corda Builder tool launches:



- 2 Do one of the following:
 - ♦ Click *Graph Wizard*, then continue with [Step 3](#).
 - ♦ To create a map, click *Map*, then skip to [Step 4](#).
 - ♦ Click *Close* to cancel the Fast Start options and open an existing template.
 - ♦ Click *Close* to work from scratch without using the wizard.
 - ♦ If creating a chart or graph, the easiest way is to work from a template, then customize a chart or graph as necessary.
- 3 Select *Create New Project from a Template*.

- 4 In the *Template Selection* tab, select template names in the *Template Selection* left pane to preview the various styles.
- 5 When you have found a chart style you want to use, click *Next* to continue.
- 6 In the *Graph Type Selection* tab, select the graph type, subtype, and style.
- 7 Click *Next* to continue.
- 8 In the *Data Selection* tab, do one of the following:
 - ♦ Use the Graph Data spreadsheet to specify valid data if you want to create a chart with static values.
 - ♦ Specify placeholder information to replace with JSP tags later to pull data from Operations Center.
- 9 Click *Next* to continue.
- 10 In the *General* tab, specify border, background, and color theme options.
- 11 In the *Title* tab, specify the chart title, and specify border, shadow, and font settings for the title.
- 12 Select *Continue Customizing Project*, then click *Finish*.

The chart template is displayed in the Corda Builder tool.
- 13 Continue to [“Modifying Chart Settings and Properties” on page 208](#), or [“Modifying Map Settings and Properties” on page 208](#) if creating a map.

Modifying Chart Settings and Properties

To modify chart settings and properties:

- 1 Double-click any of the objects in the *Object* drop-down list, or double-click any element directly on the map.
- 2 Click the *PCXML* tab to view the chart code directly.
To integrate Operations Center data, the file needs to be modified to include JSP tags to pull in dynamic data. See [Section 10.2.2, "Integrating Operations Center Data," on page 209](#)
- 3 To publish the chart with static data, verify that all data points are correct.
- 4 To publish the chart, click *File > Publish*.
- 5 Select image types to be created by selecting the appropriate check boxes.
- 6 Browse and save the file to a directory and with a file name that can be remembered later.
- 7 Continue to [Section 10.2.2, "Integrating Operations Center Data," on page 209](#).

Modifying Map Settings and Properties

To modify map settings and properties:

- 1 Double-click any of the objects (such as, *Graph*, *Legend_Graph*, *Title*) in the *Object* drop-down list, or double-click any element directly on the actual chart.
If creating a map the easiest way is to build it based on a template using a map from the map library, then customize further as necessary.
- 2 Click *Template*.
- 3 Click *Predefined*.
- 4 Browse the maps hierarchy tree, then select the PCXML file for the continent, country, region, US, or world.
- 5 Click *OK* to select the map.
The chart is displayed in the Corda Builder tool.
- 6 Continue to [Section 10.2.2, "Integrating Operations Center Data," on page 209](#).

10.2.2 Integrating Operations Center Data

After a chart has been created through the Corda Builder, the PCXML file must be customized to work with Operations Center data.

This is where you leverage the various tag libraries (see [Appendix C, “JSP Tag Library Reference,” on page 249](#)) and define user setup options that format or drive the chart. Depending on chart requirements, this can include:

- ◆ Operations Center element selection
- ◆ Date/time or date range selection
- ◆ Time category selection
- ◆ Performance Series (profile/expression) selectors
- ◆ SLA (agreement/objective) selectors
- ◆ A custom check box series option
- ◆ A custom field option (that is, a chart title)
- ◆ A custom drop-down list option

To customize a chart with Operations Center data:

- 1 To launch the Corda Builder if it is not already open, go to the Operations Center installation directory, then browse to and launch the `/OperationsCenter_install_path/image/bin/CordaBuilder` executable.
- 2 Open a template PCXML file. If one is not already open, then click the *PCXML* tab.
- 3 Select and copy all the code, then open a text/HTML editor and paste in the PCXML code.
- 4 Add the required UI Model code in the `.jsp` file header.

These are the options that form the editor portion of the chart and drive the generation of the chart at runtime. For an example, see [Section 10.2.4, “An Example: Modifying a PCXML File with JSP Tags,” on page 211](#).

Following are the available UI Model selectors:

Selector Type	Attributes	Fields ¹	Description
calendar	label		Provides a drop-down list to select a calendar. For example: <code><selector type="calendar" label="Select calendar:" /></code>
check box	label, name, checked		Provides a check box selection. label is the text displayed for the check box. For example: <code><var type="check box" label="Use Breaches for Cost Counts" name="useBreaches" checked="checked" /></code>
date	label		Provides options to run report for an interval, date range, or real-time data. For example: <code><selector type="date" label="Run report for:" /></code>

Selector Type	Attributes	Fields ¹	Description
element	label		Provides an element link to browse and select a root element to drive the chart/report. For example: <pre><selector type="element" label="Select element:" /></pre>
nativePerformance	label	profile, expression	Provides fields to specify the profile and expression. Also provides links to browse and select. For example: <pre><selector type="nativePerformance" label="Select Metric:"> <required name="profile" /> <required name="expression" /> </selector></pre>
select	label, name, options		Provides a drop-down list selection. options are the actual values of the drop-down list items. For example: <pre><var type="select" label="Select your favorite fruit" name="Fruit" options="Apples,Oranges,Blueberries" /></pre>
sla	label	sla, objective	Provides fields to specify the agreement and objective. Provides links to browse and select, as well. For example: <pre><selector type="sla" label="Select SLA:"> <required name="sla" /> <required name="objective" /> </selector></pre>
textbox	label, name, size		Provides a simple field option. For example: <pre><var type="textbox" label="Chart Title:" name="title" size="35" /></pre>
timeCategories	label		Provides a check box list for time categories selection. For example: <pre><selector type="timeCategories" label="Time Categories included:" /></pre>

¹If no required fields are specified, all available fields are applied. If one field is specified in the selector, only the specified field is used. All fields that are not specified are hidden and not used.

5 Add any necessary taglib references.

For more information about using the tag libraries, see [Appendix C, "JSP Tag Library Reference," on page 249](#).

For an example, see [Section 10.2.4, "An Example: Modifying a PCXML File with JSP Tags," on page 211](#).

- 6 Update any places where information is dynamic.
Instead of the placeholder static values, insert the code to pull the data from Operations Center where needed. For an example, see [Section 10.2.4, “An Example: Modifying a PCXML File with JSP Tags,” on page 211](#).
- 7 Add drill-down URL links, if desired. See [Section 10.2.3, “Creating Drill-Down URLs for a Chart,” on page 211](#)
- 8 Close all open tags.
- 9 Save the file as a .jsp file to a working directory.
- 10 Continue to [Section 10.2.5, “Uploading New Templates,” on page 213](#)

10.2.3 Creating Drill-Down URLs for a Chart

When you create a custom chart through the Chart Builder, it is possible to set up links (URLs) that allow for drill-down functionality.

The following parameters are required for the drill-down URLs in chart templates:

- ♦ **template parameter (+ id):** Specifies the location of the template to include.
- ♦ **goto parameter (+ id):** Sends the request to the holder include file.

An example of a link is:

```
<%= response.encodeUrl( request.getContextPath() + "/"
Controller?backLink"+id+"="+java.net.URLEncoder.encode(thisLink)+"&goto"+id+"="/
chartBuilderDrillDown.jsp&template"+id+"=/generated/templates/
radarAndPieAlarms.jsp&dname"+id+"="+java.net.URLEncoder.encode(dname) ) %>
```

The Dashboard ships with a Chart Builder example (see the Map Drill Down Example template) that shows a map with this drill-down functionality. Although the example is not intended for use out-of-the-box without further customization, it shows how Chart Builder can be used to build a custom map with drill-down support. The link can be configured to drill down to one element.

10.2.4 An Example: Modifying a PCXML File with JSP Tags

The example uses an example code snippet from the `ElementBarAlarms.jsp` file after it was edited to expose Operations Center information. Compare this to the `ElementBarAlarms.PCXML` file to view the raw file before it was updated. This is an example of how you might modify a PCXML file, actual edits depend on the chart you are building.

To modify a PCXML file with JSP Tags:

- 1 Add the UI Model code to the header for each chart setup option in the Dashboard:

```
<%--
<uimodel title="Element Alarm Counts as a Bar Chart">
  <variable prefix="graph1">
    <var type="textbox" label="Enter the title of this chart:" name="title"
size="35" />
    <selector label="Select the element for which to display alarm counts:"
type="element" />
    <var type="check box" label="Show the last updated date/time:"
name="datetime" />
  </variable>
</uimodel>
--%>
```

- 2 Get access to element info by using DName. Insert the DName code as follows below the xml version code but above the chart tag as shown in the first line below:

```
<element:exists name="$graph1.element.dname" id="element">
<Chart Version='4.40.00' BorderType='None' BorderColor='#99ccff'
BGGradientColor='#4d718e'>
```

- 3 Use value entered in edit options to set chart title.

```
<Textbox Name='Title' Top='6' Left='4' Width='121' Height='23'>
<Properties ShadowStyle='Fade' HJustification='Left' Font='Name:Lucida
Sans; Size:14.0; Style:Bold; Color:#003333;' />
<Text>$graph1.textbox.title.value</Text>
</Textbox>
```

- 4 Leverage Formula tag to get condition colors as shown in the bottom half of this section.

```
<Graph Name='graph' Top='49' Left='20' Width='503' Height='263' Type='Bar'
SubType='Basic'>
<Properties AnimateStyle='Default' Effect='2D'
SingleSeriesMulticolor='True' ShadowStyle='Fade' UseGridStripes='True'
GridStripeColor='#ccccff' PercentSpaceBetweenBars='30' />
<DataLabels Font='Size:11.0; Style:Bold; Color:White;' BGColor='Black'
FormatString='%_VALUE %_CATEGORY_NAME Alarms' ShowBarZeroValues='True'
ShadowStyle='Fade' />
<HTMLTable TableAttributes='border=&#x27;3&#x27; cellspacing=&#x27;0&#x27;
cellpadding=&#x27;3&#x27;' HeaderTR='align=&#x27;center&#x27;'
HeaderTR2='align=&#x27;center&#x27;' DataTR='align=&#x27;center&#x27;'
FooterTR='align=&#x27;center&#x27;' FooterTH='align=&#x27;center&#x27;' />
<formula:colors id="colors">
<ColorPalette Color1='<%=colors.getConditionColor("critical")%>'
Color2='<%=colors.getConditionColor("major")%>'
Color3='<%=colors.getConditionColor("minor")%>'
Color4='<%=colors.getConditionColor("informational")%>'
Color5='<%=colors.getConditionColor("ok")%>'
Color6='<%=colors.getConditionColor("unknown")%>' Color7='#66ccff'
Color8='#33cc99' Color9='#cc6666' Color10='#f0f066' Color11='#ffccaa'
Color12='#aaccff' Color13='#66ddaa' Color14='#f09999' Color15='#f0f0aa'
Color16='#ccf0aa' />
</formula:colors>
<ValueScale Position='Left' MinorGrid='Visible:False;'
MinorFont='Size:10.0;' />
<CategoryScale MinorFont='Size:10.0;' />
</Graph>
```

- 5 Use Element tag to get severity counts and plug into data values as shown in the bottom half of this section.

```
<GraphData Name='graph' Method='Replace'>
<Categories>
<Category Name='Critical' />
<Category Name='Major' />
<Category Name='Minor' />
<Category Name='Informational' />
<Category Name='OK' />
<Category Name='Unknown' />
</Categories>
<Series Name='Count'>
<Data Value='<%=element.getAlarmCount("(severity=critical)")%>' />
<Data Value='<%=element.getAlarmCount("(severity=major)")%>' />
<Data Value='<%=element.getAlarmCount("(severity=minor)")%>' />
<Data Value='<%=element.getAlarmCount("(severity=informational)")%>' />
<Data Value='<%=element.getAlarmCount("(severity=ok)")%>' />
<Data Value='<%=element.getAlarmCount("(severity=unknown)")%>' />
</Series>
</GraphData>
```

6 Print time data was last updated.

```
<%
  if ($graph1.check box.datetime.value) {
    java.text.DateFormat lu = java.text.DateFormat.getDateTimeInstance(
java.text.DateFormat.MEDIUM, java.text.DateFormat.MEDIUM );
    %>
    <Textbox Name='textbox3' Top='314' Left='1' Width='537' Height='19'>
    <Properties AutoWidth='False' AutoHeight='False' AutoSizeText='True'
BorderType='None' TransparentFill='True' Font='Size:11.0; Style:Italic;' />
    <Text>Last updated <%= lu.format( new java.util.Date() ) %></Text>
  </Textbox><%
  }
%>
```



7 Close the chart and element tag.

```
</Chart>
</element:exists>
```

10.2.5 Uploading New Templates

After creating a new template, use the Chart Builder portlet in the Dashboard to upload it to your Web page. After uploading it, you must configure it.



To upload a chart template:

- 1 From a Chart Builder portlet, click  *Options* and select  *Preferences*. The Chart Builder tab opens.
- 2 Click *Manage*.
- 3 Click *Browse* to browse and select a chart template file.
- 4 Click *Upload* to add the template.
- 5 The template is now available to use with the Chart Builder portlet.

10.2.6 Deleting Templates

You can remove templates that you uploaded by using the Chart Builder portlet in the Dashboard.

To delete a chart template:

- 1 From a Chart Builder portlet, click  *Options* and select  *Preferences*.. The Chart Builder tab opens.
- 2 Click *Manage*.
- 3 Select the check box for the chart template.
- 4 Click *Delete*.

11 Portal and Community Permissions

Permissions are granted to users to perform actions that on a set of resources. Permissions can be assigned either to individual users or to a group of users who share the same role.

The administrator can use permissions to delegate tasks to users. For example, assign a user the permissions needed to manage a specific community.

- ♦ [Section 11.1, “Assigning Permissions Using Roles,” on page 215](#)
- ♦ [Section 11.2, “Setting Individual Permissions,” on page 223](#)
- ♦ [Section 11.3, “Delegating Tasks with Roles,” on page 225](#)
- ♦ [Section 11.4, “Verifying User Permissions,” on page 225](#)

11.1 Assigning Permissions Using Roles

Roles are groupings of users that share a particular function within the portal, according to a particular scope. Roles can be granted permissions to various functions within portlet applications.

Roles are used to define permissions across their scope: across the portal, across an organization, or across a community. For example, consider a role which grants access to create a Service Management category. A Portal role would grant that access across the portal, wherever there was a Service Management portlet.

Roles are scoped by:

- ♦ Portal
- ♦ Organization
- ♦ Community

A Community role grants access only within a single community. An Organization role grants that access only within an Organization. Because Roles are used strictly for portal security, they also do not have pages, like Communities and Organizations.

Administrators can define roles through the Control Panel. Roles are assigned permissions and then are assigned users or user groups. Users, User Groups, Communities, or Organizations can be members of a role.

In the Dashboard, there are two types of roles that you are likely to require:

- ♦ Roles related to portal administration. For example, these roles might have rights to create new communities and maintain their pages.
- ♦ Roles that allow users to perform specific tasks within or for a community.

NOTE: While the following sections cover setting and assigning permissions for a community, these same features and steps apply for organizations.

The following sections cover roles and assigning permissions to them:

- ♦ [Section 11.1.1, “Community Roles,” on page 216](#)
- ♦ [Section 11.1.2, “Portal Administration Roles,” on page 219](#)
- ♦ [Section 11.1.3, “Configuring Roles,” on page 221](#)
- ♦ [Section 11.1.4, “Understanding the Power Users Role,” on page 222](#)
- ♦ [Section 11.1.5, “Granting Role Permissions for Other Roles,” on page 222](#)

11.1.1 Community Roles

When a community or organization is created, there are three default roles that are created:

- ♦ **Administrator:** are super users of their community and can assign community roles to users.
- ♦ **Owner:** are super users of their community and can assign community roles to users.
- ♦ **Member:** is the default role assigned to all users who belong the community or organization.

For information about assigning community users to these default roles, see [“Assigning Community Roles” on page 218](#).

In addition, you might want to create additional roles that grant specific administrative capabilities for the community or allow access to perform an action within the community. For example, you can create a role that can assign users, or a “Journal” role that is in charge of updating journal entries.

In the beginning, setting up community roles is a three step process. However, after the roles are defined for a community, you will just be assigning users to the roles.

- ♦ [“Creating Community Roles” on page 216](#)
- ♦ [“Granting Portlet Permissions” on page 217](#)
- ♦ [“Assigning Community Roles” on page 218](#)


Creating Community Roles

Community-type roles allow you to define permissions for specific functionality that you’ll want to grant to a subset of community members.

To create a community role:

- 1 Click *Welcome*, and select *Control Panel*.
- 2 Under *Portal*, select *Roles*.

3 Click *Add*.



The screenshot shows a web interface for creating a role. At the top is a green header with the word "Roles". Below it is a light blue bar with two buttons: "View All" with a person icon and "Add" with a plus icon. The form has three main sections: "Name" with a text input field containing "Alarms Portlet Administrator"; "Description" with a larger text area containing "Users that can administer alarms portlets."; and "Type" with a dropdown menu set to "Community". At the bottom are "Save" and "Cancel" buttons.


- 4 Specify the name of the role.
- 5 Specify a description for the role.
- 6 Select *Community* from the *Type* drop-down list.
- 7 Click *Save*.
- 8 Continue to [“Granting Portlet Permissions” on page 217](#).

Granting Portlet Permissions

After a role is defined, the next step is to define portlet permissions which cover permissions that are defined within various portlets.

To grant portlet permissions to a role:

- 1 Click *Welcome*, and select *Control Panel*.
- 2 Under *Portal*, select *Roles*.
- 3 Click *Actions* next to the desired role and select *Define Permissions*.
- 4 Click *Add Portlet Permissions*. A list of portlets displays.



The screenshot shows the "Define Permissions" page for the "Alarms Portlet Administrator" role. The breadcrumb trail is "Roles » Alarms Portlet Administrator » Define Permissions". There are three buttons: "Edit", "Define Permissions" (highlighted in blue), and "Assign Members". Below the buttons is a box containing the text "Step 1 of 2. Choose a portlet." Below that is a pagination bar showing "Showing 1 - 20 of 91 results." and "Items per Page 20" (dropdown), "Page 1" (dropdown), "of 5", and navigation links for "First", "Previous", "Next", and "Last". A table of portlets is displayed below, with the "Alarms" portlet highlighted in blue.

Portlet
37
6
Admin
Alarms
Alerts

5 Click the desired portlet link to define permissions for that portlet type.

[Roles](#) » [Alarms Portlet Administrator](#) » [Define Permissions](#) » [Alarms](#)

Step 2 of 2. Select the actions that this role can perform on each resource of the *Alarms* portlet.

All

Alarms

Action

Preferences

View

Configuration

6 Select the *All* check box to grant permissions to set preferences, view and configure the portlet, or select any of the following check boxes:

- ♦ **Preferences:** grant access to update preferences of the portlet.
- ♦ **View:** grant access to view the portlet.
- ♦ **Configuration:** grant access to update configuration settings for the portlet.

7 Click *Save*.

8 Continue to [“Assigning Community Roles” on page 218](#).

Assigning Community Roles

At a minimum, you’ll likely want to assign the Administrator and Owner roles to at least one community member. When more specialized community roles are defined, you’ll want to assign users to them.

For information about assigning default roles to users, see [Section 4.4.2, “Default Associations for User Accounts,” on page 62](#).

To assign community users to a role:

- 1 Click *Welcome*, and select *Control Panel*.
- 2 Under *Portal*, select *Communities*.

Name ▼	Type	Members	Online Now	Active	
Guest Public Pages - Live (12) Private Pages (0)	Restricted	1	0	Yes	<input type="button" value="Actions"/>
Business Service Management Public Pages - Live (6) Private Pages (0)	Restricted	1	0	Yes	<input type="button" value="Actions"/>
North America Community Public Pages - Live (3) Private Pages (0)	Open	1	0	Yes	<input type="button" value="Actions"/>

3 Click *Actions* next to the community and select *Assign User Roles*.

Name ▼	Type	Description
Alarms Portlet Administrator	Community	will administer alarms portlets.
Community 4354	Community	Autogenerated role from portal upgrade
Community Administrator	Community	Community Administrators are super users of their community but cannot make other users into Community Administrators.
Community Member	Community	All users who belong to a community have this role within that community.
Community Owner	Community	Community Owners are super users of their community and can assign community roles to users.
NA	Community	to assign standard roles over to the community.

4 Click the name of the desired role.

5 Click the *Available* tab.

<input type="checkbox"/>	Name	Screen Name
<input type="checkbox"/>	Default Administrator	admin
<input checked="" type="checkbox"/>	John Allen	jallen
<input type="checkbox"/>	Roth, Charlie	croth

6 Select the check box of each user to assign to the role.

7 Click *Update Associations*.

11.1.2 Portal Administration Roles

Portal scoped roles are related to portal administration. For example, these roles might have rights to create new communities and maintain their pages.

By default, there are four portal scoped roles:

- ♦ **Admin:** has administrative privileges.
- ♦ **Power User:** by default, all users are also assigned the Power User role. You can give this role certain permissions if you wish or disable it altogether
- ♦ **User:** is the most basic user.
- ♦ **Guest(Visitor):** is all non-logged in users.


Assign permissions for portal-wide activities that are in several categories, such as Community, Location, Organization, Password Policy, etc. This allows you to create a Role that, for example, can create new Communities in the portal. This would allow you to grant users that particular permission without making them overall portal administrators.

NOTE: Portal permissions can only be assigned to roles of *Regular* type.

For information about assigning default roles to users, see [Section 4.4.2, “Default Associations for User Accounts,”](#) on page 62.

To create a portal administration role:

- 1 Click *Welcome*, and select *Control Panel*.
- 2 Under *Portal*, select *Roles*.
- 3 Click *Add*.



The screenshot shows the 'Roles' management interface. At the top, there is a green header with the word 'Roles'. Below the header, there are two buttons: 'View All' with a person icon and 'Add' with a plus icon. The 'Add' button is highlighted. Below the buttons, there are three input fields: 'Name' with the text 'Portal Community Admin', 'Description' with the text 'Users that can create and maintain communities.', and 'Type' with a dropdown menu showing 'Regular'. At the bottom, there are two buttons: 'Save' and 'Cancel'.

- 4 Specify the name of the role.
- 5 Specify a description for the role.
- 6 Select *Regular* from the *Type* drop-down list.
- 7 Click *Save*. The role displays in the *Roles* page.
- 8 To define permissions for the role, do the following:
 - 8a Click *Actions* next to the role and select *Define Permissions*.
 - 8b Click *Add Portal Permissions*.
 - 8c Select *Portal* for each action you wish to grant to the role.

Edit	Define Permissions	Assign Members
------	---------------------------	----------------

Step 1 of 1. Select the scope of the action that this role can perform on the po

Portal	
Action	Scope
Add Community	Portal ▼
Add License	▼
Add Organization	Portal ▼
Add Password Policy	▼
Add Role	▼
Add User	Portal ▼
Add User Group	Portal ▼

- 8d Click *Save*.
- 9 To assign members to the role, do the following:
 - 9a Click *Assign Members*.
 - 9b Click the *Users, User Groups, Communities or Organizations* tab.
 - 9c Click the *Available* tab.
 - 9d Select the check box for the desired user(s), user group(s), community/Communities or Organization(s) to assign to the role.
 - 9e Click *Save*.

11.1.3 Configuring Roles

To configure or change a role:

- 1 Click *Welcome* and select *Control Panel*.
- 2 Under *Portal*, select *Roles*.
- 3 Click *Action* next to role and select from the available options to update and configure the role, which include:
 - ♦ **Edit:** Edit the role by changing its name or description.
 - ♦ **Permissions:** Define which Roles (and thereby users and user groups) have permissions to edit the Role.
 - ♦ **Define Permissions:** Define the permissions for this roles.
 - ♦ **Assign Members:** Search and select users in the portal to be assigned to this role. These users inherit any permissions given to the role.
 - ♦ **View Users:** View the users who are in the Role.
 - ♦ **Delete:** Deletes the Role.
- 4 Click *Save*.

11.1.4 Understanding the Power Users Role

By default, many portlets in the Dashboard are configured so that *Power Users* have access to them, but regular users do not. If you decide to remove the *Power Users* role from the default user associations, you will need to modify the permissions on certain portlets.

11.1.5 Granting Role Permissions for Other Roles

For all roles, you can give permissions to other roles for the maintenance of that role.

To assign permissions to another role:

- 1 Click *Welcome*, and select *Control Panel*. The Control Panel opens.
- 2 Under *Portal*, select *Roles*.
- 3 Click *Actions* next a role of Community or Organization type, and select *Permissions*.

Role	Assign Members	Define Permissions	Delete	Manage Announcements	Permissions	Update	View
Business Service Management	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Guest	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Owner	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Power User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Showing 5 results.

- 4 Grant permissions as necessary to the members of the selected role by selecting its associated check box.
 - ♦ **Assign Members:** Allows them to assign users as members of the role.
 - ♦ **Define Permissions:** Allows them to define permissions for the role.
 - ♦ **Delete:** Allows them to delete the role.
 - ♦ **Manage Announcements:** Allows them to maintain announcements.
 - ♦ **Permissions:** Allows them to view permissions on the role.
 - ♦ **Update:** Allows them to edit the role.

- ♦ **View:** Allows them to view role attributes.
- 5 Click *Submit*.

11.2 Setting Individual Permissions

Various individual permissions can be granted or denied for roles as the page or portlet level.

- ♦ [Section 11.2.1, “Assigning Individual Permissions to Pages,” on page 223](#)
- ♦ [Section 11.2.2, “Assigning Individual Permissions to a Portlet,” on page 224](#)

11.2.1 Assigning Individual Permissions to Pages

Page permissions are applicable only to the page for which they were configured.

To assign individual permissions for a single page:

- 1 Click *Welcome* and select *Manage Pages*.
- 2 Click the link for the desired page.
- 3 Click *Permissions*.

Permissions
« Back

Showing 13 results.

Role	Add Discussion	Update	View
Business Service Management	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
EMEA	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Guest	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
Journal	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
North America	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Owner	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Portal Community Admin	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Power User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Community 4354	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Community Member	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>

Showing 13 results.

- 4 For each entity, assign permissions by moving them from the Available to the Current table:
 - ♦ **Add Discussion:** to allow users assigned to the role to add and manage discussions for the page.
 - Update:** to allow users assigned to the role to update the page.

View: to allow users assigned to the role to view the page.


5 Click *Submit*.


11.2.2 Assigning Individual Permissions to a Portlet

You can configure permissions for individual portlets, but it is not the best way to implement permissions because you might need to repeat the process for many users.

Portlet permissions are applicable only to the portlet instance for which they were configured.

To configure permissions for a portlet instance:












- 1 Click  (*Configuration*) for the portlet.
- 2 Click the *Permissions* tab.



Alarms

Permissions Sharing

Showing 13 results.

Role	Preferences	View	Configuration
 Business Service Management	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
 EMEA	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 Guest	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
 Journal	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 North America	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 Owner	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
 Portal Community Admin	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 Power User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 User	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 Community 4354	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
 Community Member	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>

Showing 13 results.

Submit

- 3 For each role select any of the following check boxes as desired:
 - ♦ **Preferences:** to allow users assigned to the role to view and modify preferences for that portlet.
 - View:** to allow users assigned to the role to view that portlet.
 - Configuration:** to allow users assigned to the role to view and modify configuration settings for that portlet.
- 4 Click *Submit*.

11.3 Delegating Tasks with Roles

Use permissions to assign tasks to users to help with the administration of the Dashboard. For example, assign to a user some of the roles of an enterprise, organization, or location administrator. Assign users to manage communities and pages within communities. You can moderate content by distributing it among communities and delegate the responsibility for moderating communities to various users.

To delegate tasks using roles:

- 1 Assign permissions to a role that allow a user to perform a specific task.
- 2 Assign that role to the resource.
- 3 Then assign users to that role.

Roles can be assigned to any resource, regardless of scope.

11.4 Verifying User Permissions

The impersonate feature allows you to log in as a user and see exactly what the user sees. This is useful to verify that permissions are set correctly.

- 1 Click *Welcome* and select *Control Panel*.
- 2 Select *User Groups* under the *Portal* section.
- 3 Click *Action* for the user and select *Impersonate User*.

12 Advanced Administrative Topics

This section covers various administrative topics, such as:

- ♦ [Section 12.1, “Encrypting the Dashboard Database Password,” on page 227](#)
- ♦ [Section 12.2, “Configuring Dashboard Ports for RMI Callbacks,” on page 228](#)
- ♦ [Section 12.3, “Enabling the Dashboard for Section 508 Accessibility,” on page 228](#)
- ♦ [Section 12.4, “Moving a Dashboard Configuration,” on page 229](#)
- ♦ [Section 12.5, “Upgrading the Dashboard,” on page 230](#)
- ♦ [Section 12.6, “Performing System Recovery,” on page 236](#)

12.1 Encrypting the Dashboard Database Password

Database credentials are set in the `portal-ext.custom.properties` file, but the password can be encrypted to further secure your implementation.

To encrypt the database password:

- 1 To generate the encrypted password, run one of the following scripts:
 - ♦ **Windows:** `/OperationsCenter_Dashboard_install_path/bin/encrypt.bat`
 - ♦ **UNIX:** `/OperationsCenter_Dashboard_install_path/bin/encrypt.sh`
- 2 Copy and paste the encrypted password into the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file for the active database configuration.

If the database properties have not previously been added to the `portal-ext.custom.properties`, copy and paste the associated lines from the `portal-ext.properties` file in the same directory. Do not modify the `portal-ext.properties` file, as you might overwrite software upgrades that are already running.

Note that the copied encrypted password should begin with `X-TEAV` and must not contain any passwords on the end.

- 3 Restart the Dashboard.

For more information about starting and stopping the Dashboard, see [Section 2.3, “Starting and Stopping the Dashboard,” on page 26](#).

12.2 Configuring Dashboard Ports for RMI Callbacks

Traditionally, firewall communication is restricted from the Dashboard to the Operations Center server. For more information on these RMI port settings, see [Section 2.2.1, “Verifying Your Operations Center Server’s Default Accounts and Configuration Settings,”](#) on page 14. For information about port configuration, see “The Dashboard using RMI” in the *Novell Operations Center 5.0 Server Configuration Guide*.

In some environments, it might be necessary to specify the number of ports available to use for communication from the Operations Center server to the Dashboard.

To specify the RMI Callback Port:

- 1 Stop the Dashboard.

For information on stopping the Dashboard, see [Section 2.3.2, “Stopping the Dashboard,”](#) on page 27.

- 2 Edit the `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEB-INF/mo-settings.xml` file to add the following:

```
<entry>
  <string>rmi.callback.port</string>
  <string>PortNumber</string>
</entry>
```

Where *PortNumber* is the port number or a range of acceptable port numbers. For example, `<string>6050:6059</string>` sets 6050 as the lowest available port number and 6059 as the highest available port number.

- 3 Start the Dashboard.

For information on starting the Dashboard, see [Section 2.3.1, “Starting the Dashboard,”](#) on page 27.

12.3 Enabling the Dashboard for Section 508 Accessibility

Section 508 requires that Federal agencies’ electronic and information technology is accessible to people with disabilities. The Operations Center Dashboard provides Section 508 compliance and compatibility whenever possible.

The following technical considerations apply when using the Dashboard with Section 508 Accessibility enabled:

- ♦ Access the Dashboard using Internet Explorer 8 or Firefox when Section 508 Accessibility is enabled.
- ♦ Enabling 508 accessibility in Operations Center changes the default appearance of some portlet content to be compliant with Section 508 standards. For example, it might enable features to be compliant in color dependence.
- ♦ Alarm summary charts, in the Information portlet, are not 508 compliant. The Information portlet is not 508 compliant when CSS is disabled.

To enable the Dashboard for 508 accessible functionality:

- 1** To enable accessibility options in Operations Center for one or more users:
 - 1a** From the Operations Center console, expand *Administration > Security > Users*.
 - 1b** Right-click the user's account, and select *Properties*.
 - 1c** Click *User*.
 - 1d** Select the `Enable Accessibility Options` check box and *Apply*.
 - 1e** Repeat these steps for each user.
- 2** To enable accessibility options in Operations Center for your own account, do the following:
 - 2a** From the Operations Center console, click *File* and select `Enable Accessibility Options`.
- 3** Do the following to select the Dashboard 508 theme:
 - 3a** In the Dashboard, do one of the following:
 - ♦ Click *Welcome* (in the top right corner) and select *Manage Pages*.
From the list of pages on the left, select the desired page To change the theme for all pages, click the community name (top level page).
 - ♦ Navigate to the desired Dashboard page.
Click *Welcome* (in the top right corner) and select *Manage Pages*.
 - 3b** Click the *Look and Feel* tab.
 - 3c** Select the `508 Accessibility` theme.
 - 3d** Repeat for each page that needs to be 508 accessible.
Note that when a theme is selected for a page, it applies for all users.

12.4 Moving a Dashboard Configuration

After configuring the Dashboard, you might want to move the Dashboard configuration to another machine. For example, you can first deploy the Dashboard in a test or development environment, then later move it to a production environment for general use.

- ♦ [Section 12.4.1, "Preparing to Move a Dashboard Configuration," on page 229](#)
- ♦ [Section 12.4.2, "Moving a Dashboard Configuration," on page 230](#)

12.4.1 Preparing to Move a Dashboard Configuration

To successfully move a the Dashboard configuration, there are two prerequisites:

- ♦ Both the existing server and the target server must have the same version of the Dashboard, including the same patch bundles installed, and
- ♦ The configuration settings in the [Operations Center Dashboard Configuration Manager](#) must be the same on both servers.

12.4.2 Moving a Dashboard Configuration

To move a Dashboard configuration:

- 1 Shut down both the Dashboard servers.
- 2 Copy `/OperationsCenter_Dashboard_install_path/data/hsqldb/portal.script` from the existing server to the target server.
- 3 Modify the `server_profiles` section of the target server's `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEB-INF/data/serverprofiles-ext.xml` file for the server's properties.
- 4 Determine if any customizations were made to the existing server and if those customizations need to be made on the target server, as well.

Some files that might have been customized are:

- ♦ **portal-ext.custom.properties:** In `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/`, it is used for [auto-login](#), [persistent connection account](#), [disabling of portlets](#), [power user personal pages changes](#), or for overriding other liferay properties set in `portal.properties`.

Note that any settings in `portal-ext.custom.properties` file takes precedence over those in the `portal-ext.properties` file. Do not customize `portal-ext.properties` and `portal.properties` files, as you might overwrite the files.

- ♦ **system-ext.properties:** In `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/`, it is used for [proxy server configuration](#).
- ♦ **web.xml:** In `/OperationsCenter_Dashboard_install_path/server/conf/`, it is used for [session management](#).
- ♦ **globals.xml:** In `/OperationsCenter_Dashboard_install_path/server/webapps/ManagedObjectsPortlets/WEB-INF/data/`, it is used for [global defaults](#) for all Operations Center portlets.

- 5 Make the necessary customizations on the target server.

12.5 Upgrading the Dashboard

The following sections cover information about software patches as well as upgrading the Dashboard.

- ♦ [Section 12.5.1, "About Patches," on page 231](#)
- ♦ [Section 12.5.2, "Installing Patches," on page 231](#)
- ♦ [Section 12.5.3, "Rolling Back a Patch Installation," on page 233](#)
- ♦ [Section 12.5.4, "Upgrading myMO/the Dashboard," on page 233](#)
- ♦ [Section 12.5.5, "Upgrading from the Dashboard Embedded Database to Oracle or SQL Server," on page 235](#)

12.5.1 About Patches

Operations Center sends software updates for the Dashboard in patch bundles, which must be installed on the Dashboard server. Before installing a patch, read all correspondence sent along with the patch, including a Readme file or e-mail.

Patch files use the naming convention *nnn-yyyy-mm-ddCRiiiiii-Rxxxxx-META-DASH.jar*. [Table 12-1](#) describes the components of the patch file name.

Table 12-1 Naming Conventions

Patch File Name Component	Definition
nnn	Software version number (such as 500 for version 5.0.0).
yyyy	Current year.
mm	Current month (such as 03 for March).
dd	Current day (such as 01, 02, 03).
iiiiii	Issue number
xxxxx	Release number
META	If present, indicates the patch contains all interdependent patches.
DASH	Indicates that the patch is for the Dashboard. The name MO indicates that the patch is for Operations Center.

For more information on installing this patch, see the [Novell Operations Center 5.0 Server Installation Guide](#).

12.5.2 Installing Patches

The procedure for installing the patch is the same for UNIX and Windows. The type of file for a patch is `.jar`. If you receive the file with a different extension, rename it to `.jar` before installing it.

One or more patches can be applied at a time, but patches and rollbacks cannot be applied at the same time with the same command. When a patch has already been applied, but is a older version than what you are installing, it is necessary to rollback the patch before installing the newer version of the patch.

When a patch bundle is applied, all previously applied patches are removed before the patch is applied.

To install the patch:

- 1 Copy the patch bundle to the root of the Dashboard installation directory.

The installation directory in the file system should have a minimum free disk space of twice the size of the patch bundle file.

For example, if the `.jar` file is 50 MB, then the free disk space should be at least 100 MB.

- 2 At a command prompt, enter `Java` to verify that Java is installed.

Patch files are issued as `.jar` files. The patch bundle is a Java executable file so it is necessary to have Java (either 32-bit or 64-bit) running on the machine where the Dashboard is installed.

- 3 If you receive the patch file with a different extension than `.jar`, rename it to `.jar` before installing it.
- 4 At the command prompt in the Dashboard installation directory, enter `java -jar` and the file name of the patch bundle.

For example, if the Dashboard is installed in the `C:` directory and the name of the patch bundle is `500-20100328-DASH.jar`, then the command is:

```
C:/OperationsCenter_Dashboard_install_path>java -jar 500-20100328-DASH.jar
```

For additional options when running the installation, enter:

```
java -jar patch_bundle_filename(s) --help
```

Where, *patch_bundle_filename(s)* is a list of one or more patch files separated by a space.

This displays the following options:

- ♦ **-describe:** Prints patch manifest information.
- ♦ **-prompt:** Displays the Operations Center Dashboard Configuration Manager after the patch is installed.
- ♦ **-verbose:** Prints detailed information to the screen as the patch is installed.
- ♦ **--force:** Forces a patch to install even if it has already been applied. Never use the force command unless instructed to by Novell Support.

Add one of these commands at the end of the `java -jar patch_bundle_filename` command when installing the patch bundle (for example, `java -jar 500-20110328-DASH.jar --verbose`).

If installing on Windows and User Access Control (UAC) is enabled, you must run the command prompt as the Administrator.

- 5 During installation, the following occurs:
 - ♦ A back up is automatically created for all files that are overwritten. For more information about rollback files, see [Section 12.5.3, "Rolling Back a Patch Installation," on page 233](#).
 - ♦ Patches (of the same version) that have already been applied are skipped unless the `--force` option was set.
 - ♦ The Operations Center Configuration Manager always runs silently and applies the current settings.
 - ♦ The patch does not override the existing Operations Center Configuration Manager settings.

For more information regarding the Operations Center Configuration Manager, see the [Novell Operations Center 5.0 Server Configuration Guide](#).

- 6 Review the following chapter to configure and start the Dashboard.

After the patch has been installed and a rollback file is created, the patch cannot be installed again. If you attempt to run the patch bundle `.jar` file again, the following error messages are displayed:

```
ERROR: Unable to continue since rollback jar already exists
```

```
ERROR: unable to create rollback jar
```


12.5.3 Rolling Back a Patch Installation

As part of the patch installation process, Operations Center automatically backs up all files that are overwritten and places them in a file called `patch_filename-rollback.jar`, such as `500-201180723-DASH-rollback.jar`.

If you decide to remove the changes made by the patch to Operations Center, run this rollback JAR file from the Operations Center root installation directory. The command for running the rollback file is the same as when the patch is installed. For example:

```
C:/OperationsCenter_install_path>java -jar 500-20110723-DASH-rollback.jar
```

When multiple rollback patches are applied using the same command, they are applied in the reverse order.

12.5.4 Upgrading myMO/the Dashboard

The following notes apply when upgrading your version of the Dashboard:

- ♦ The `Dashboard_install_path/server/webapps/root/WEB-INF/portal-ext.xml` file, which might have been customized for various property settings, is overwritten during the upgrade process. A copy is automatically saved as `portal-ext.xml.previous` in the same directory. If you had modified this file as part of your installation, you will need to restore these changes after the upgrade installation.
- ♦ Custom theme content is not updated during upgrades and any static links to documentation must be changed manually.

For instructions on upgrading the dashboard:

- ♦ [“Upgrading to myMO 4.7” on page 233](#)
- ♦ [“Upgrading to Dashboard 5.0” on page 234](#)

Upgrading to myMO 4.7

Before upgrading to myMO v4.7, be sure to review the upgrade notes in [“myMO/Dashboard Upgrade Considerations”](#) in *Novell Operations Center 5.0 Release Notes*.

Liferay 5.x introduced a Role Based Access Control (RBAC) algorithm that assigns permissions using Roles, and other user grouping objects (groups, organizations, permissions) are assigned to roles.

For additional information from Liferay about the new permission algorithm and why it was implemented, see <http://www.liferay.com/web/raymond.auge/blog/-/blogs/1339340/maximized> (<http://www.liferay.com/web/raymond.auge/blog/-/blogs/1339340/maximized>).

The permission algorithm is set in the `permissions.user.check.algorithm` property in the `portal-ext.properties` file. Because myMO v4.7 employs this new RBAC algorithm for assigning permissions, upgrading to myMO v4.7 requires additional steps to convert existing permissions from Algorithm 2 to the new Algorithm 5.

To upgrade to myMO 4.7:

- 1 Install myMO 4.7 over the existing myMO 4.6 directory.
- 2 Start the myMO service.
myMO runs with algorithm 2 for backwards compatibility with existing permissions.

For more information about starting the myMO service, see [Section 2.3.1, “Starting the Dashboard,” on page 27](#).

- 3 Login to the Operations Center Dashboard.
- 4 Click *Welcome* and select *Control Panel*.
- 5 Under *Server*, select *Server Administration*.
- 6 Click the *Data Migration* tab.
- 7 Click *Execute* to start the permissions conversion process.
- 8 When the conversion process is complete, log out of myMO and stop the myMO service.

For more information about stopping the myMO service, see [Section 2.3.2, “Stopping the Dashboard,” on page 27](#).

- 9 Modify the `myMO_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.ccustom.properties` file to set the following:

```
permissions.user.check.algorithm = 5
```

- 10 Restart the myMO service.

For more information about starting the myMO service, see [Section 2.3.1, “Starting the Dashboard,” on page 27](#).

myMO now uses the latest permission algorithm with roles that were created during the permission conversion process.

- 11 New roles, created from existing permissions by the conversion process, can be accessed from the *Roles* page in the *Control Panel*. Rename these auto-generated roles with meaningful names, so that it is easy to identify them.

Upgrading to Dashboard 5.0

Before upgrading to Operations Center 5.0, be sure to review the upgrade notes in [“Upgrades from Managed Objects to Operations Center v5.0”](#) and [“myMO/Dashboard Upgrade Considerations”](#) in [Novell Operations Center 5.0 Release Notes](#).

To upgrade from myMO to Operations Center Dashboard 5.0:

- 1 Do one of the following:
 - ♦ If upgrading from myMO 4.6, follow the same steps as outlined in [“Upgrading to myMO 4.7” on page 233](#), where you are installing Dashboard 5.0 over the existing myMO 4.6 directory.
 - ♦ If upgrading from myMO 4.7, install the Dashboard over the existing myMO 4.7 directory.

12.5.5 Upgrading from the Dashboard Embedded Database to Oracle or SQL Server

If running an existing myMO/Dashboard implementation, you must switch from using the default Hypersonic SQL embedded database to upgrade to an Oracle or SQL Server database. If you have been using myMO/Dashboard with the embedded database, it is possible to upgrade your database and preserve existing data.

See “[Supported Versions and Hardware Requirements](#)” in the *Novell Operations Center 5.0 Getting Started Guide* for supported database versions.

You must be running v4.7 to use an Oracle or SQL Database. During the v4.7 and v5.0 installation, the upgrade process upgrades the Hypersonic SQL embedded database and stores the files in the new default location of `Dashboard_install_path/data/hsql`.

IMPORTANT: myMO/Dashboard must be started at least once using the Hypersonic SQL embedded database, so that it can run a critical database verification processes. If you are installing Dashboard for the first time or have just upgraded, you must start myMO/Dashboard once before implementing the following steps to migrate the database to Oracle or SQL Server.

To migrate myMO/Dashboard to use an Oracle or SQL Server database on an existing integration:

- 1 Stop myMO. See [Section 2.3.2, “Stopping the Dashboard,”](#) on page 27.
- 2 Do one of the following to create the schema for the new database:
 - ♦ **Oracle:** Use the Oracle SQL*Plus Client to run the `Dashboard_install_path/data/scripts/create-oracle.sql` file against your Oracle database.
Note that the schema creation script contains some PL/SQL code which other jdbc based clients cannot execute.
 - ♦ **SQL Server:** Run the `Dashboard_install_path/data/scripts/create-sql-server.sql` file against your SQL Server database.
- 3 Open the `Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/portal-ext.custom.properties` file and make the following changes in the *Database Support* section:
 - 3a Comment out any lines for the Hypersonic SQL embedded database.
 - 3b Copy and paste the lines for the desired database from the `portal-ext.properties` file in the same directory, and customize for your configuration. Note the following:
 - ♦ `jdbc.default.driverClassName` and `hibernate.dialect` property values should not be changed.
 - ♦ For the `jdbc.default.url` property, specify a valid url string for the given driver. (jtds for sql server and oracle for oracle).
 - ♦ For `jdbc.default.username` and `jdbc.default.password` properties, specify the credentials of a user that has valid access writes to the database.
 - ♦ The `jdbc.default.schema` property is only specified for oracle and required only when running the `dbmigrate` script.

Be sure the lines for the Oracle or SQL database are uncommented in the `portal-ext.custom.properties` file.

Optionally, you can encrypt the password. For more information about encrypting the database password, see [Section 12.1, “Encrypting the Dashboard Database Password,”](#) on page 227.

- 4 If needed, install the appropriate database drivers. Prepackaged JDBC drivers are available as part of the installation in the *Dashboard_install_path/server/lib/ext/* directory. Install one of the following drivers:
 - ♦ **Oracle:** ojdbc6.jar
 - ♦ **SQL Server:** jtds-1.2.2.jar
- 5 Using a command prompt, from *Dashboard_install_path/bin/*, do one of the following to migrate existing data from the database:
 - ♦ **Windows:** Run `dbmigrate.bat`
 - ♦ **UNIX:** Run `dbmigrate.sh`

The migration process copies all data from the Hypersonic SQL embedded database, located in the *Dashboard_install_path/data/hsqldb* directory, to the destination database as specified in step 3.
- 6 Restart myMO/Dashboard and verify that existing data is available. See [Section 2.3.1, “Starting the Dashboard,”](#) on page 27.

12.6 Performing System Recovery

If the Operations Center server stops, the following occurs:

- ♦ The Dashboard continues to function for users already logged in, but data from Operations Center is not available. Operations Center portlets display a message stating that the Operations Center server is not accessible. After the Operations Center server restarts, users must log out of the Dashboard and log in again in order to see Operations Center data.
- ♦ Users who were not logged in before the server stopped cannot log in to the Dashboard until the Operations Center server is back up.
- ♦ The [Access Control Synchronizer](#) stops and user accounts are not synchronized until the Operations Center server has come back up.

If the Dashboard Web server stops for any reason, when it restarts, it identifies all users who were logged in to the Dashboard at the time of stoppage and logs them out of the Operations Center server. It then begins working as usual. For errors that can be logged in the trace file if the Dashboard Web server stops while writing data, see [Section D.1.2, “Data Dispatcher Exception – Broken Pipe,”](#) on page 262.

A System Properties File

The `system.properties` file contains properties that relate to the Dashboard including the proxy server configuration, default language, and default time zone. This file is never modified at any time.

The following sections describe how to override `system.properties` file properties as well as view default system properties:

- ♦ [Section A.1, “Overriding System Settings in the Systems Properties File,” on page 237](#)
- ♦ [Section A.2, “Viewing the Default System Properties,” on page 238](#)

A.1 Overriding System Settings in the Systems Properties File

The `system.properties` file contains properties that relate to the Dashboard including the proxy server configuration, default language, and default time zone. This file is never modified at any time.

Instead, a `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/classes/system-ext.properties` file is used to override setting, when necessary.

WARNING: Exercise caution when modifying the `system-ext.properties` file. Do not change any properties unless you are fully aware of the consequences. Changing some properties could cause conflicts with the Operations Center server and can have unintended consequences.

To configure the systems property file:

- 1 For the Dashboard to recognize the `system-ext.properties` file, open the `\OperationsCenter_Dashboard_install_path\bin\catalina.bat` (Windows) or the `/OperationsCenter_Dashboard_install_path/bin/catalina.sh` (UNIX) file.
- 2 Add the following line to the set `JAVA_OPTS` property:

```
-Dsystem.properties.load=true
```

A.2 Viewing the Default System Properties

To view the default `system.properties` on your installation, open the copy of the `system.properties` file contained in the `/OperationsCenter_Dashboard_install_path/server/webapps/ROOT/WEB-INF/lib/portal-impl.jar` file.

The `system.properties` file cannot be edited.

The code for the default `system.properties` file is as follows:

```
##
## Java
##
#
# The file encoding must be set to UTF-8 in order for the
# internationalization to work correctly.
#
file.encoding=UTF-8
#
# Java uses the underlying operating system to generate images. If you are
# using UNIX and do not start the portal in a X Windows session, then Java
# will not know how to generate images and you'll get lots of nasty
# exceptions. Setting this property to true will fix that. Sometimes this
# property cannot be set dynamically when the server starts and you'll need
# to edit your start script to include this as a system property.
#
java.awt.headless=true
#
# Set the default language.
#
user.country=US
user.language=en
#
# The time zone must be set GMT so that the portal knows how to properly
# translate time across time zones.
#
user.timezone=GMT
##
## Servlet Filters
##
#
# If the user can unzip compressed HTTP content, the compression filter will
# zip up the HTTP content before sending it to the user. This will speed up
# page rendering for users that are on dial up.
#
com.liferay.filters.compression.CompressionFilter=true
com.liferay.filters.compression.CompressionFilter.encoding=UTF-8
#
# The strip filter will remove blank lines from the outputted content. This
# will speed up page rendering for users that are on dial up.
#
com.liferay.filters.strip.StripFilter=true
com.liferay.filters.strip.StripFilter.encoding=UTF-8
#
# The layout cache filter will cache pages to speed up page rendering for
# guest users. Set the refresh time in milliseconds on how often the cache
# should refresh. Set it to 0 if the cache never times out. Default time
out
# is set to one hour.
#
com.liferay.portal.servlet.filters.layoutcache.LayoutCacheFilter=true
com.liferay.portal.servlet.filters.layoutcache.LayoutCacheFilter.encoding=UTF-8
com.liferay.portal.servlet.filters.layoutcache.LayoutCacheFilter.refresh.time=360000
#
```

```

# The virtual host filter maps hosts to public and private pages. For
# example, if the public virtual host is www.helloworld.com and the friendly
# URL is /helloworld, then http://www.helloworld.com is mapped to
# http://localhost:8080/web/helloworld.
#
com.liferay.portal.servlet.filters.virtualhost.VirtualHostFilter=true
#
# The CAS filter will redirect the user to the CAS login page for SSO. See
# http://www.ja-sig.org/products/cas for more information.
#
com.liferay.filters.sso.cas.CASFilter=false
##
## Logging
##
#
# Set any logger that implements org.apache.commons.logging.Log.
#
#org.apache.commons.logging.Log=org.apache.commons.logging.impl.Log4JLogger
#
# Set the following to true if Log4j complains that it was not properly
# configured.
#
log4j.configure.on.startup=true
##
## Encryptor
##
#
# Set the security provider class.
#
com.liferay.util.Encryptor.provider.class=com.sun.crypto.provider.SunJCE
##
## HTTP
##
#
# Set the location of the HTTP proxy that the portal will use to fetch
# external content.
#
#http.proxyHost=192.168.0.200
#http.proxyPort=4480
#
# These are read for backwards compatibility and only used if the
# "http.proxyHost" and "http.proxyPort" settings are not specified.
#
#com.liferay.util.Http.proxy.host=192.168.0.200
#com.liferay.util.Http.proxy.port=4480
#
# Set the proxy authentication type.
#
#com.liferay.util.Http.proxy.auth.type=username-password
#com.liferay.util.Http.proxy.auth.type=ntlm
#
# Set user name and password used for HTTP proxy authentication.
#
#com.liferay.util.Http.proxy.username=
#com.liferay.util.Http.proxy.password=
#
# Set additional properties for NTLM authentication.
#
#com.liferay.util.Http.proxy.ntlm.domain=
#com.liferay.util.Http.proxy.ntlm.host=
#
# Set the connection timeout when fetching HTTP content.
#
com.liferay.util.Http.timeout=5000
##
## Format
##
#

```

```

# Set the location of the class that implements
# com.liferay.format.PhoneNumberFormat. This class will format phone
# numbers.
#

com.liferay.util.format.PhoneNumberFormat=com.liferay.util.format.USAPhoneNumberFo
rmat

#com.liferay.util.format.PhoneNumberFormat=com.liferay.util.format.IdenticalPhoneN
umberFormat
##
## Axis
##
#
# Urls that match the specified pattern will use the SimpleHTTTPSender. Urls
# that do not match the specified pattern will use Axis' default HTTTPSender.
#
com.liferay.util.axis.SimpleHTTTPSender.regexp.pattern=.*mappoint\.net.*

##
## XSS (Cross Site Scripting)
##
#
# Set the pattern to strip text of XSS hacks.
#
com.liferay.util.XSSUtil.regexp.pattern=(?i)<[\s]*/?script.*?>|<[\s]*/
?embed.*?>|<[\s]*/
?object.*?>|<[\s]*a[\s]*href[^>]*javascript[\s]*:[^(\^)*\[\]^>]*>[^<
]*(<[\s]*/[\s]*a[^>]*>)*
##
## Upload Servlet Request
##
#
# Set the maximum file size. Default is 1024 * 1024 * 1000.
#
com.liferay.util.servlet.UploadServletRequest.max.size=104857600
#
# Set the temp directory for uploaded files.
#
com.liferay.util.servlet.UploadServletRequest.temp.dir=C:/Temp
##
## Session Parameters
##
#
# Encrypt session parameters so that browsers cannot remember them.
#
com.liferay.util.servlet.SessionParameters=true
##
## Lucene
##
#
# Set a timeout to avoid lock errors.
#
org.apache.lucene.writeLockTimeout=30000
##
## Quartz
##
#
# Make threads daemon so the JVM exits cleanly.
#

```



```
    org.quartz.threadPool.makeThreadsDaemons=true
##
## Velocity Engine
##
#
# Input a list of comma delimited class names that extend
# com.liferay.util.velocity.VelocityResourceListener. These classes will
# run in sequence to allow you to find the applicable ResourceLoader
# to load a Velocity template.
#
com.liferay.util.velocity.VelocityResourceListener=com.liferay.portal.velocity.Ser
vletVelocityResourceListener,\
com.liferay.portal.velocity.JournalTemplateVelocityResourceListener,\
com.liferay.portal.velocity.DefaultVelocityResourceListener
```

B Running a Console or Unattended Installation

Alternative methods for installing Operations Center software are provided in the following sections:

- ♦ [Section B.1, “Console Installation,” on page 243](#)
- ♦ [Section B.2, “Unattended Installation,” on page 244](#)

B.1 Console Installation

The console installation runs a text-based version of the Dashboard installation wizard. In a console installation:

- ♦ The options are the same as the Windows-based version, except that you must type the responses.
- ♦ There are no *Choose* buttons to open directories to locate files. Instead, you must provide the path names for the files.
- ♦ There is no option to open the Configuration Manager at the end of the installation. The default settings for the Configuration Manager are automatically applied.
- ♦ You can run a console installation on a Unix machine without having an X Window system set to display graphical (X client) applications on the local X server display. However, you will still need the local X server display to open the Configuration Manager on that machine, if you opt to do so after installing Operations Center.

To run a console installation:

- 1 Do one of the following:
 - ♦ **Windows:** Insert the Operations Center Installation CD and from the directory where the installation executable file resides, type `install.bat -i console` at a command prompt.
 - ♦ **Unix:** Create a home directory for the installation, mount the Operations Center Installation CD, then from the directory where the installation executable file resides, type `install.sh -i console` at a command prompt.
- 2 Follow the prompts in the script to provide the information required to install the product. For more information about installer prompts, see [Section 2.2.2, “Installing the Dashboard,” on page 16](#).
- 3 Continue with [Section 2.2.3, “Configuring the Dashboard Database,” on page 18](#).

B.2 Unattended Installation

This method installs Operations Center without opening the Installation Wizard. It takes all of the default values and runs silently in the background. A [response file](#) can be used to supply predefined values including:

- ◆ Options from the installation wizard
- ◆ Licensing information from the license file
- ◆ Configuration Manager settings
- ◆ A configuration stored in the Configuration Storage data source

This method is intended for when you need to rerun the installation often, such as in a test environment.

You can run a silent installation on a Unix machine without having an X Window system set to display graphical (X client) applications on the local X server display. However, you will still need the local X server display to open the Configuration Manager on that machine.

For more information about the Configuration Manager and configurations and the Configuration Storage data source, see the [Novell Operations Center 5.0 Server Configuration Guide](#).

Use the following sections to run an unattended installation:

- ◆ [Section B.2.1, “Running an Unattended Installation,” on page 244](#)
- ◆ [Section B.2.2, “Using a Response File,” on page 246](#)
- ◆ [Section B.2.3, “Sample Response File,” on page 246](#)

B.2.1 Running an Unattended Installation

To run an unattended installation:

- 1 To install Operations Center, do one of the following:
 - ◆ **Windows:** Insert the Operations Center Dashboard Installation CD and from the directory where the installation executable file resides, type `install.bat -i silent` at a command prompt.
 - ◆ **Unix:** Create a home directory for the installation, mount the Operations Center Dashboard Installation CD, then from the directory where the installation executable file resides, type `install.sh -i silent` at a command prompt.

Default install options are used to complete the installation.

- 2 After the unattended installation has completed, continue with [Section 2.2.3, “Configuring the Dashboard Database,” on page 18](#).

To run an unattended installation:

- 1 To install Operations Center, do one of the following:
 - ◆ **Windows:** Insert the Operations Center Installation CD and from the directory where the installation executable file resides, type `install.bat -i silent` at a command prompt.

- ◆ **Unix:** Create a home directory for the installation, mount the Operations Center Installation CD, then from the directory where the installation executable file resides, type `install.sh -i silent` at a command prompt.

Default install options are used to complete the installation.

- 2 After the unattended installation has completed, continue with [Section 2.2.3, “Configuring the Dashboard Database,”](#) on page 18.

Using a Response File to Customize Installation Options

To run an unattended installation with a response file:

- 1 Because there are multiple ways to create a [response file](#), depending on the content you want to include, do one of the following:

- ◆ To create a response file that includes the options from the installation wizard, licensing information, configuration manager settings, and a configuration stored in the Configuration storage data source, at a command prompt on the machine that has the existing the Dashboard installation that you want to use, enter the following:

```
mosjava com.mosol.install.myMOInstallerResponseFile responsefile.rsp
installdir
```

replacing *responsefile* with the name of the response file to be created and *installdir* with the installation directory for the existing the Dashboard installation.

For example, type:

```
mosjava com.mosol.install.myMOInstallerResponseFile C:/moresponse.rps C:/
OperationsCenter_Dashboard_install_path/
```

to create a response file called `moresponse.rps` that uses the Dashboard installation located in the `C:/` directory.

- ◆ To create a response file that includes installation wizard options only, run a [wizard-based](#) or [console](#) installation by typing the following at a command prompt:

`install.bat -i install method -r filename` for Windows where *install method* is the installation method (either GUI or console) and *filename* is the name of the response file, such as `myinstall.rsp`.

`install.sh -i install method -r filename` for Unix where *install method* is the installation method (either GUI or console) and *filename* is the name of the response file, such as `myinstall.rsp`.

When a response file is created, it is saved in the Dashboard installation directory.

- 2 Copy the response file to the server where want to install the Dashboard.

If necessary, edit the file using a text editor. Some changes that you can make include:

- ◆ Adding licensing information
- ◆ Changing configuration settings
- ◆ Modifying the configuration from the Configuration Storage data source

- 3 To use the response file to install the Dashboard, do one of the following:

- ◆ **Windows:** Insert the Dashboard Installation CD and from the directory where the installation executable file resides, type `install.bat -i silent -f filename.rsp` at a command prompt replacing *filename* with the name of the response file.

- ♦ **Unix:** Create a home directory for the installation, mount the Dashboard Installation CD, then from the directory where the installation executable file resides, type `install.sh -i silent -f filename.rsp` at a command prompt replacing *filename* with the name of the response file.

The options in the response file are used to automatically complete the installation.

- 4 After the unattended installation has completed, continue with [Section 2.2.3, “Configuring the Dashboard Database,”](#) on page 18.

B.2.2 Using a Response File

Use the response file during the process of performing a silent installation of the Dashboard on a different machine. The installation uses the options in the response file to automatically complete the installation wizard.

To install the Dashboard using the response file:

- 1 Copy the response file to the machine where you want to install the Dashboard.

If necessary, edit the response file using a text editor.

- 2 Perform a silent installation, enter the following at a command prompt:

- ♦ **Windows:** `install.bat -i silent -f filename.rsp`
where *filename* is the name of the response file (such as `myinstall.rsp`).
- ♦ **UNIX:** `install.sh -i silent -f filename.rsp`
where *filename* is the name of the response file (such as `myinstall.rsp`).

B.2.3 Sample Response File

This section contains a sample response file for a the Dashboard installation, which is a standard ASCII text file. Response files are created from an actual installation of the product, giving you default values that are determined by that installation.

Because a response file’s content contains very few carriage returns, the following sample’s content is word-wrapped automatically where the documentation program can break a long string, such as at spaces, forward slashes, or certain characters. For example, in a text editor with word-wrap turned off, this sample response file contains 5 lines, one of which contains most of the content.

```
#Thu Feb 07 10:46:06 EST 2008
LICENSE_CONTENTS=
CONFIGURATIONS_CONTENTS=
USER_INSTALL_DIR=C:\myMOFeb7_Clone0
CUSTOMIZE_PROPERTIES_CONTENTS=<config>\n <properties>\n <entry>\n
<string>MOCommunicationsMode</string>\n <string>https</string>\n </entry>\n
<entry>\n <string>MyMORMICache</string>\n <string>>false</string>\n </
entry>\n <entry>\n <string>MOServerHost</string>\n
<string>dhendricks</string>\n </entry>\n <entry>\n <string>JavaHome</
string>\n <string>C:\Documents and Settings\sshetty\Local
Settings\Temp\I1202399004\Windows\resource\jre</string>\n </entry>\n
<entry>\n <string>MymoLogLevel</string>\n <string>WARN</string>\n </
entry>\n <entry>\n <string>MOSqlServerPort</string>\n <string>7560</
string>\n </entry>\n <entry>\n <string>MymoLogInfo</string>\n
<string>FILE "C:\myMOFeb7\logs\dashboards.trc" SIZE 5000000 RENAME
"C:\myMOFeb7\logs\mymo.%36datetime.trc"</string>\n </entry>\n <entry>\n
<string>MOImageServerPort</string>\n <string>7002</string>\n </entry>\n
<entry>\n <string>LocalDomain</string>\n <string>localdomain</string>\n
</entry>\n <entry>\n <string>MyMOWebServerPort</string>\n
<string>7081</string>\n </entry>\n <entry>\n <string>HttpsCommentEnd</
string>\n <string></string>\n </entry>\n <entry>\n <entry>\n
```

```

<string>MyMOWebServerShutdownPort</string>\n      <string>7006</string>\n    </
entry>\n      <entry>\n        <string>jvm.home</string>\n          <string>C:\\Program
Files\\Java\\jre1.5.0_13</string>\n        </entry>\n      <entry>\n
<string>MyMOCcommunicationsMode</string>\n        <string>bidirSSL</string>\n      </
entry>\n      <entry>\n        <string>UserName</string>\n          <string>sjones</
string>\n        </entry>\n        <string>MOWebServerPort</string>\n
<string>7080</string>\n        </entry>\n      <entry>\n
<string>MyMOServerPushEnabled</string>\n        <string>>false</string>\n      </
entry>\n      <entry>\n        <string>MORMIServerPort</string>\n          <string>7099</
string>\n      </entry>\n      <entry>\n
<string>MyMOServerAlarmOperationsEnabled</string>\n        <string>>false</string>\n
</entry>\n      <entry>\n        <string>InstallDir</string>\n
<string>C:\\myMOFeb7</string>\n      </entry>\n      <entry>\n        <string>HostName</
string>\n          <string>djones</string>\n        </entry>\n      <entry>\n
<string>HttpCommentEnd</string>\n        <string>--&gt;</string>\n      </entry>\n
<entry>\n      <string>HttpCommentHead</string>\n        <string>&lt;!--</string>\n
</entry>\n      <entry>\n        <string>IpAddress</string>\n
<string>192.168.10.228</string>\n      </entry>\n      <entry>\n
<string>MyMOWebServerSSLPort</string>\n        <string>7443</string>\n      </entry>\n
<entry>\n      <string>MyMORMICacheTimeout</string>\n        <string>75</string>\n
</entry>\n      <entry>\n        <string>HttpsCommentHead</string>\n          <string></
string></
string>\n      </entry>\n    </properties>\n</config>

```


C JSP Tag Library Reference

The Operations Center custom tag libraries can expose server component information and functions. Custom tag libraries extend the basic set of tags that can be defined within a JSP (JavaServer Pages) page.

- ♦ [Section C.1, “Understanding JSP Tag Libraries in Operations Center,” on page 249](#)
- ♦ [Section C.2, “Query Tag Library,” on page 250](#)
- ♦ [Section C.3, “Constrain Tag Library,” on page 251](#)
- ♦ [Section C.4, “Expand Tag Library,” on page 253](#)
- ♦ [Section C.5, “Request Tag Library,” on page 253](#)
- ♦ [Section C.6, “Element Tag Library,” on page 256](#)
- ♦ [Section C.7, “Result Tag Library,” on page 257](#)


C.1 Understanding JSP Tag Libraries in Operations Center

Operations Center custom tag libraries are an integral part of JSP. Tag libraries allow Web developers to create new tags for inclusion in JSP pages that perform custom actions within a Web page.

Operations Center provides several custom tag libraries for obtaining information from Operations Center server components. These custom tags provide the JSP programmer with an easy way to access Operations Center server information, including SLA performance, user authentication, alarms, and element conditions.

The following figure shows how custom tags fit into the Operations Center architecture:

Figure C-1 Architecture of JSP Custom Tags and Operations Center



The requirements for placing custom tag libraries are:

- ◆ Specify a tag library name at the top of the JSP page. For example, the following line appears at the top of the JSP file, before the `<html>` tag:

```
<%@ taglib uri="http://www.managedobjects.com/taglibs/query" prefix="query" %>
```

This refers to the custom tags in the Query Custom tag library.

- ◆ The Web deployment descriptor file (`WEB-INF/web.xml`) must specify the location of the tag library. For example:

```
<taglib>
<tagliburi>http://www.managedobjects.com/taglibs/query</tagliburi>
<taglib-location>/WEB-INF/query.tld</taglib-location>
</taglib>
```

C.2 Query Tag Library

The Query tag library contains functionality specific to the Operations Center application for querying against the performance engine. This tag library contains two tags: `createQuery` and `performQuery`. Use both tags together to retrieve information from Operations Center.

To reference this custom tags in the Operations Center tag library, add the following code to the top of the JSP file before the `<html>` tag:

```
<%@ taglib uri="http://www.managedobjects.com/taglibs/remote/query" prefix="query" %>
```

The following sections explain the tags:

- ◆ [Section C.2.1, “createQuery,” on page 250](#)
- ◆ [Section C.2.2, “performQuery,” on page 251](#)

C.2.1 createQuery

The `createQuery` tag creates a query to obtain information from Operations Center.

This tag is necessary to provide some constraints, requests, and expansions within the body of `createQuery` tag. Use the tags belonging to `Constrain`, `Request`, and `Expand` tag libraries.

The `createQuery` tag can be nested, if required, in order to create subqueries. It has the option of placing conditional code within the body of the tag.

For example:

```
<query:createQuery>
  [provide constraints]
  [provide expansion]
  [provide requests]
  [perform query]
</query:createQuery>
```

The `createQuery` tag alone cannot generate any required result. Use it to begin a query. This tag creates a `HyperQuery` object, which maintains `java.util.Set` objects for storing/queuing unique constraints, requests, and expansions. When any tags belonging to the `Constrain`, `Request`, and `Expand` tag libraries are inside the `createQuery` tag, objects pertaining to them are stored in the respective `java.util.Set` objects. A `HyperQuery` object is later used within the `performQuery` tag to obtain information from the performance engine.

C.2.2 performQuery

The `performQuery` tag performs or executes a query.

After performing a query against the performance engine, the `performQuery` tag internally maintains a list of HyperCube objects. Tags belonging to the `Result` tag libraries use these objects to manipulate information. Place the `Result` library tags within the body of the `performQuery` tag to obtain information. For example, the `iterator` tag iterates information provided by the performance engine.

Place any conditional code within the body of the tag. For example:

```
<query:createQuery>
  <constrain:element name="<%=dname%>" />
  <constrain:time from="<%=>"+start%>' to="<%=>"+end%>' />
    <request:summaryState />
    <request:availability />
  <query:performQuery>
    <result:iterator id="test" >
      </result:iterator>
    </query:performQuery>
</query:createQuery>
```

C.3 Constrain Tag Library

The `Constrain` tag library contains functionality specific to the Operations Center application for filtering data using a query. Constraints are similar to the `WHERE` clause in SQL. A constraint reduces the amount of data returned by the query by applying the filter to the results. This tag library contains many tags used inside a `createQuery` tag. All the tags belonging to this library are empty; they do not contain body content.

The following sections explain the tags:

- [Section C.3.1, “category,” on page 251](#)
- [Section C.3.2, “element,” on page 252](#)
- [Section C.3.3, “excludeManual,” on page 252](#)
- [Section C.3.4, “local,” on page 252](#)
- [Section C.3.5, “offering,” on page 252](#)
- [Section C.3.6, “objective,” on page 252](#)
- [Section C.3.7, “time,” on page 252](#)
- [Section C.3.8, “timeZone,” on page 253](#)

C.3.1 category

The `category` tag provides constraints on time categories, such as `Off`, `Non-Peak`, `On`, `Peak`, `Critical`, and so on:

```
<% String[] catsAsArray = new String[] {"On", "Peak", "Critical"}; %>
  <constrain:category timeCategoryIds="<%= catsAsArray %>"/>
```

This tag has one mandatory attribute, `timeCategoryIds`, which provides time category names. The `timeCategoryIds` tag accepts an array of time category names to include in the calculations. For example, use this tag to query for downtime during `Peak` times only.

C.3.2 element

The `element` tag provides a constraint on a given Operations Center element:

```
<constrain:element name="element_to_constrain" />
```

It has one mandatory attribute, `name`, which provides the name of the element to constrain. To obtain performance information about an Operations Center element, it is necessary to specify the `element` tag within the `createQuery` tag. The following code snippet constrains a query by instructing it to fetch information about the *Organizations > Check Your Bill* element that displays in the Explorer pane in the Operations Center console:

```
<query:createQuery>  
  <constrain:element name="org=Check+Your+Bill/root=Organizations" />  
</query:createQuery>
```

C.3.3 excludeManual

The `excludeManual` tag manually excludes created outages when computing results:

```
<constrain:excludeManual/>
```

This tag has no attribute and is used like a parameter for the `createQuery` tag.

C.3.4 local

The `local` tag constrains all SLA calculations to data that are relevant for the current element only, and not its children:

```
<constrain:local/>
```

This tag has no attribute and is used like a parameter for the `createQuery` tag.

C.3.5 offering

The `offering` tag provides constraints on an SLA (offering):

```
<constrain:offering name="SLA name" />
```

This tag has one mandatory attribute, `name`, which provides the SLA name

C.3.6 objective

The `offering` tag provides constraints on a given SLA objective:

```
<constrain:objective name="objective name" />
```

This tag has one mandatory attribute, `name`, which provides the SLA objective name.

C.3.7 time

The `time` tag provides constraints on a time period:

```
<constrain:time from = "<%= start %>" to = "<%= end %>" />
```

The attributes of this tag are: `from`, `to`, and `interval`. The `from` and `to` attributes provide the time frame value to use in obtaining performance information.

C.3.8 timeZone

The `timeZone` tag provides constraints on a given time zone specified by an ID:

```
<constrain:timeZone name ="Zone ID" />
```

This tag has one mandatory attribute, `name`, which identifies the time zone.

C.4 Expand Tag Library

The Expand tag library contains functionalities specific to the Operations Center application for expanding a query against the performance engine.

To reference this custom tags in the Operations Center tag library, add the following code to the top of the JSP file before the `<html>` tag:

```
URL = <%@ taglib uri="http://www.managedobjects.com/taglibs/remote/query/expand"
prefix="expand" %>
```

An expansion increases the amount of the data returned by the query by adding all data that matches the expansion criteria. For example, to produce a result set containing a cube of data for each hour of the day since yesterday, use the time expansion with an hour interval. The query result is 24 cubes of data.

As with the `constrain` tags, the `expand` tags must be used within the `createQuery` tag. All of the tags belonging to this tag library have no attributes, except for the time tag:

- ♦ [Section C.4.1, "time," on page 253](#)

C.4.1 time

Expands the result cubes based on a time interval:

```
<% String end = "" + System.currentTimeMillis(); %>
  <expand:time from='<%=start%>' to='<%=end%>' interval="months"/>
```

For example, to obtain a result set containing a cube for each day of the last month, use the time expansion with a day's interval. This returns 30 cubes of data in the query result, if the month has 30 days. This tag has three attributes: `from`, `to`, and `interval`. The `from` and `to` attributes specify the start and end dates of a period as a long value. The mandatory `interval` attribute provides time intervals, such as: "seconds", "minutes", "hours", "days", "weeks", "months", "years", "milliseconds".

C.5 Request Tag Library

The Request custom tag library contains tags that can access information in the Operations Center performance engine.

To reference this custom tags in the Operations Center tag library, add the following code to the top of the JSP file before the `<html>` tag:

```
URL = <%@ taglib uri="http://www.managedobjects.com/taglibs/remote/query/request"
prefix="request" %>
```

To obtain results using the `performQuery` tag, it is necessary to use request tags to obtain any type of information from the Operations Center performance engine. Use the request tag within a `createQuery` tag as you might use `constrain` and `expand` tags. All the tags belonging to this library

have no body content. It is possible to provide any number of unique requests within a query. When a request is provided within a createQuery tag, it adds the requested value into the query result set. When the performQuery starts executing the tag, it takes the requests from the query and creates results containing the value.

The syntax for using the request tag is:

```
<query:createQuery>
  <constrain:element name="<%=dname%>">
  <request:availability>
  <query:performQuery>
  [result manipulation]
  </query:performQuery>
</query:createQuery>
```

- ♦ [Section C.5.1, "summaryState," on page 254](#)
- ♦ [Section C.5.2, "compliance," on page 254](#)
- ♦ [Section C.5.3, "availability," on page 255](#)
- ♦ [Section C.5.4, "outageCount," on page 255](#)
- ♦ [Section C.5.5, "breachCount," on page 255](#)
- ♦ [Section C.5.6, "outageDuration," on page 256](#)
- ♦ [Section C.5.7, "objectiveInstance," on page 256](#)

C.5.1 summaryState

Obtains the condition or state of a given Operations Center element:

```
<request:summaryState/>
```

C.5.2 compliance

Requests compliance from an element's agreement/objectives for a specified period of time:

```
<request:compliance/>
```

A time constrain tag must be provided within the createQuery tag to provide a time window to obtain compliance from the performance engine.

It is necessary to provide the element, time and offering constrain tags and a compliance request tag within the createQuery tag to obtain compliance from an element's agreement (SLA):

```
<constrain:time from="start time" to="end time"/>
<constrain:element name=" org=Check+Bill/root=Organizations"/>
<constrain:offering name="SLA Name"/>
<request:compliance/>
```

C.5.3 availability

Requests availability of an element's agreement (SLA) or of an objective of an agreement, for a specified period of time:

```
<request:availability/>
```

A time constrain tag must be provided within the createQuery tag to use a time window to obtain availability from the performance engine.

In order to make available an element's agreement, provide the element and offering constraints and request availability within the createQuery tag, as shown in the following code:

```
<constrain:time from="<%= ""+start%>" to="<%= ""+end%>" />
```

```
<constrain:element name=" org=Check+Bill/root=Organizations">
```

```
<constrain:offering name="<%=SLA%>">
```

```
<request:availability>
```

C.5.4 outageCount

Requests the outage count (the number of times an outage occurred) for an element's agreement or objective:

```
<request:outageCount/>
```

To obtain the outage count, a time constrain tag must be provided.

C.5.5 breachCount

Requests the breach count (the number of times a breach occurred) from an element's agreement/objectives for a specified period of time.

```
<request:breachCount/>
```

```
<request:breachCount filter="(severity=major)" />
```

```
<request:breachCount filter="(severity=major)&(alarm.status=closed)" />
```

A time constrain tag is required within the createQuery tag to provide a time window to obtain a breach count from the performance engine. The optional attribute filter selects the type of alarms to consider when counting the breach.

To obtain a breach count for an element agreement, provide the element and offering constrain tags and request a breach count within the createQuery tag:

```
<constrain:time from="start time" to="end time" />
```

```
<constrain:element name=" org=Check+Bill/root=Organizations" />
```

```
<constrain:offering name="SLA Name" />
```

```
<request:breachCount/>
```

C.5.6 outageDuration

Requests the outage duration (how long an outage occurred) for an element's agreement or objective:

```
<request:outageDuration/>
```

The time constrain tag must provide the time span to use for obtaining the outage count from the performance engine.

C.5.7 objectiveInstance

Requests an instance of an objective of a given Operations Center element:

```
<request:objectiveInstance/>
```

The results returned are the name, description, and other information about the objective. To obtain the instance of an objective, the element, offering, and objective constrain tags must be provided within the createQuery tag.

C.6 Element Tag Library

The Element tag library contains custom tags that can access information and functions within elements in Operations Center. An element is any managed object, such as a router, server, organization, or site.

To reference this custom tags in the Operations Center tag library, add the following code to the top of the JSP file before the <html> tag:

```
<%@ taglib uri="http://www.managedobjects.com/taglibs/remote/element"
prefix="element" %>
```

The following sections provide an overview of all tags available in the Element tag library:

C.6.1 exists

A parent tag of the other tags in Elements tag library. Other element tags contained within the exists tag use the element specified by the name attribute of the exists tag. Therefore, the child tags do not need to specify a name attribute themselves. This can improve both clarity and performance in the JSP. If an element named in the name attribute is not found, the body of the exists tag is not evaluated. This is shown in the following example:

```
<element:exists name="root=Elements" id="element">
  The element named <%= element.getName() %> exists!
</element:exists>
```

ElementTagSupport class is the class which supports the element tag library. The methods available on this tag allow you to retrieve:

- ♦ ["getName\(\)" on page 257](#)
- ♦ ["getCondition\(\)" on page 257](#)
- ♦ ["getTotalAlarmCount\(\)" on page 257](#)
- ♦ ["getAlarmCount\(\)" on page 257](#)
- ♦ ["Alarm Severity Counts" on page 257](#)

getName()

This method returns the name of the element. The declaration of the method is:

```
public String getName()
```

getCondition()

This method returns a String object that describes the state or condition (OK, CRITICAL, MAJOR, and so on) of an element. The declaration of this method is:

```
public String getCondition()
```

getTotalAlarmCount()

This method return a total count of alarms for this element. The declaration of the method is:

```
public int getTotalAlarmCount()
```

getAlarmCount(s)

Gives the count of alarms with the specified element condition.

```
public int getAlarmCount(com.mosol.ORB.Formula.ElementCondition condition)
```

Allowed values are:

- ◆ com.mosol.ORB.Formula.ElementCondition.UNKNOWN
- ◆ com.mosol.ORB.Formula.ElementCondition.CRITICAL
- ◆ com.mosol.ORB.Formula.ElementCondition.MAJOR
- ◆ com.mosol.ORB.Formula.ElementCondition.MINOR
- ◆ com.mosol.ORB.Formula.ElementCondition.MINOR
- ◆ com.mosol.ORB.Formula.ElementCondition.INFORMATIONAL
- ◆ com.mosol.ORB.Formula.ElementCondition.OK
- ◆ com.mosol.ORB.Formula.ElementCondition.INITIAL

Alarm Severity Counts

Execute one call to get all the alarm severity counts - return the individual counts in the return array. The declaration of the method is:

```
public Map<String, Integer> getTotalAlarmCountAndSeverityCount()
```

C.7 Result Tag Library

The Result tag library contains functionalities specific to the Operations Center application for iterating through data returned by the performance engine.

To reference custom tags in the Operations Center Results tag library, add the following code to the top of the JSP file before the <html> tag:

URL = <%@ taglib uri="http://www.managedobjects.com/taglibs/remote/query/result" prefix="result" %>

When a request is performed within the createQuery tag, the result cubes contain the requested information. Iterate these result cubes using the tags belonging to the Result tag library.

The following sections explain the tags:

- ♦ [Section C.7.1, “iterator,” on page 258](#)
- ♦ [Section C.7.2, “ResultTagSupport Class,” on page 258](#)

C.7.1 iterator

Cycles through the result cubes returned by the performance engine:

```
<result:iterator id="identifier">
    [JSP Body Content]
</result:iterator>
```

To cycle through the result cubes, the iterator tag must be provided within the performQuery tag. All other specific iteration tags, such as alarms and metrics, must also be used within the iterator tag. In order to iterate through the results properly, it is necessary to understand the structure of the query and the resulting cubes. Iteration through the results could become complex if the structure of the query is complex, such as when using nested queries and expansion. Thus, the resulting iteration must analyze the structure of the query and resulting cubes.

C.7.2 ResultTagSupport Class

Acts as a super class for all the tags belonging to result iteration. The methods available in this class retrieve information while iterating the result. Tags that belong to result iteration inherit the functionalities of ResultTagSupport, either directly or indirectly.

The following sections provide the methods for the ResultTagSupport class:

- ♦ [“getCompliance\(\)” on page 258](#)
- ♦ [“getAvailability\(\)” on page 259](#)
- ♦ [“getElementCondition\(\)” on page 259](#)
- ♦ [“getCondition\(\)” on page 259](#)
- ♦ [“getBreachCount\(\)” on page 259](#)
- ♦ [“getOutageCount\(\)” on page 259](#)
- ♦ [“getDowntime\(\)” on page 259](#)

getCompliance()

This method obtains the compliance of an element’s agreement or its objective. This method returns availability as a double value.

```
public double getCompliance()
```

getAvailability()

This method obtains the availability of an element's agreement or its objective. Availability is the amount of time when the condition of an element is below the selected threshold condition. This method returns availability as a double value

```
public double getAvailability()
```

getElementCondition()

This method returns a String object that describes the state or condition (OK, CRITICAL, MAJOR, and so on) of an Operations Center element.

```
public String getElementCondition()
```

getCondition()

This method returns a String object that describes the state or condition (OK, CRITICAL, MAJOR, and so on) of an element's objective or an agreement.

```
public String getCondition()
```

getBreachCount()

This method returns a breach count as an integer (int) value. A breach count is the number of breaches that occur in a Service Level Agreement or its objective.

```
public int getBreachCount()
```

getOutageCount()

This method returns an outage count as an integer (int) value. An outage count is the number of outages that occur in an agreement.

```
public int getOutageCount()
```

getDowntime()

This method returns the downtime of an element's objective as a long value. Downtime is the total time that elapsed during an outage (such as the duration of an outage) when an element condition is above the selected threshold condition

```
public long getDowntime()
```

D Troubleshooting Trace Logs

The `/OperationsCenter_Dashboard_install_path/server/logs/dashboard.trc` file contains error and warning messages related to the Dashboard server.

- ◆ [Section D.1, “Errors,” on page 261](#)
- ◆ [Section D.2, “Warnings,” on page 264](#)

D.1 Errors

- ◆ [Section D.1.1, “User ID Exception – Unable to Synchronize User,” on page 261](#)
- ◆ [Section D.1.2, “Data Dispatcher Exception – Broken Pipe,” on page 262](#)

D.1.1 User ID Exception – Unable to Synchronize User

The Dashboard uses the `managedobjects.com` domain name for a reserved user account. If any Dashboard user account has the user name containing “`managedobjects.com`”, the following error occurs:

```
2007-05-02 10:13:02,670 ERROR com.mosol.liferay.authenticator.MOAuth - Unable to
synchronize user managedobjects.com.1001
com.liferay.portal.UserIdException
    at
com.liferay.portal.service.impl.UserLocalServiceImpl.validate(UserLocalServiceImpl
.java:1460)
    at
com.liferay.portal.service.impl.UserLocalServiceImpl.addUser(UserLocalServiceImpl.
java:194)
    at sun.reflect.GeneratedMethodAccessor513.invoke(Unknown Source)
    at
sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:
25)
    at java.lang.reflect.Method.invoke(Method.java:585)
    at
org.springframework.aop.support.AopUtils.invokeJoinpointUsingReflection(AopUtils.j
ava:280)
    at
org.springframework.aop.framework.ReflectiveMethodInvocation.invokeJoinpoint(Refle
ctiveMethodInvocation.java:187)
    at
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMet
```

```

hodInvocation.java:154)
    at
org.springframework.transaction.interceptor.TransactionInterceptor.invoke(Transact
ionInterceptor.java:107)
    at
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMet
hodInvocation.java:176)
    at
org.springframework.aop.framework.JdkDynamicAopProxy.invoke(JdkDynamicAopProxy.jav
a:210)
    at $Proxy7.addUser(Unknown Source)
    at
com.liferay.portal.service.UserLocalServiceUtil.addUser(UserLocalServiceUtil.java:
94)

```

For more information, see [Section 4.2.1, “Understanding User Name Restriction,”](#) on page 52.

D.1.2 Data Dispatcher Exception – Broken Pipe

If the Dashboard Web server stops while writing data, an exception can be thrown that appears as a `SocketException` or broken pipe error. This exception is not a true error because no data was lost and the Dashboard will recover itself and resume normal operations.

For more information, see [Section 12.6, “Performing System Recovery,”](#) on page 236.

The following is a sample of the code that might appear for this type of exception:

```

2007-02-23 15:44:13,555 ERROR Web.Server - StandardWrapperValve[DataDispatcher]:
Servlet.service() for servlet DataDispatcher threw exception
java.net.SocketException: Broken pipe
    at java.net.SocketOutputStream.socketWrite0(Native Method)
    at java.net.SocketOutputStream.socketWrite(SocketOutputStream.java:92)
    at java.net.SocketOutputStream.write(SocketOutputStream.java:136)
    at
org.apache.coyote.http11.InternalOutputBuffer$OutputStreamOutputBuffer.doWrite(Int
ernalOutputBuffer.java:652)
    at
org.apache.coyote.http11.filters.ChunkedOutputFilter.doWrite(ChunkedOutputFilter.j
ava:166)
    at
org.apache.coyote.http11.InternalOutputBuffer.doWrite(InternalOutputBuffer.java:52
3)
    at org.apache.coyote.Response.doWrite(Response.java:513)
    at
org.apache.coyote.tomcat4.OutputBuffer.realWriteBytes(OutputBuffer.java:380)
    at org.apache.tomcat.util.buf.ByteChunk.append(ByteChunk.java:348)
    at
org.apache.coyote.tomcat4.OutputBuffer.writeBytes(OutputBuffer.java:407)
    at org.apache.coyote.tomcat4.OutputBuffer.write(OutputBuffer.java:394)
    at
org.apache.coyote.tomcat4.CoyoteOutputStream.write(CoyoteOutputStream.java:110)
    at
org.apache.coyote.tomcat4.CoyoteOutputStream.write(CoyoteOutputStream.java:104)
    at
org.jahia.bin.AbstractDispatchingServlet.service(AbstractDispatchingServlet.java:1
71)
    at javax.servlet.http.HttpServlet.service(HttpServlet.java:853)
    at
org.apache.catalina.core.ApplicationFilterChain.internalDoFilter(ApplicationFilter
Chain.java:247)
    at
org.apache.catalina.core.ApplicationFilterChain.access$000(ApplicationFilterChain.
java:98)
    at
org.apache.catalina.core.ApplicationFilterChain$1.run(ApplicationFilterChain.java:
176)
    at java.security.AccessController.doPrivileged(Native Method)

```

```

        at
org.apache.catalina.core.ApplicationFilterChain.doFilter(ApplicationFilterChain.java:172)
        at
org.apache.catalina.core.StandardWrapperValve.invoke(StandardWrapperValve.java:260)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:643)
        at
org.apache.catalina.core.StandardPipeline.invoke(StandardPipeline.java:480)
        at
org.apache.catalina.core.ContainerBase.invoke(ContainerBase.java:995)
        at
org.apache.catalina.core.StandardContextValve.invoke(StandardContextValve.java:191)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:643)
        at
org.apache.catalina.core.StandardPipeline.invoke(StandardPipeline.java:480)
        at
org.apache.catalina.core.ContainerBase.invoke(ContainerBase.java:995)
        at
org.apache.catalina.core.StandardContext.invoke(StandardContext.java:2396)
        at
org.apache.catalina.core.StandardHostValve.invoke(StandardHostValve.java:180)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:643)
        at
org.apache.catalina.valves.ErrorDispatcherValve.invoke(ErrorDispatcherValve.java:170)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:641)
        at
com.mosol.Formula.Server.WebServerErrorReportValve.invoke(WebServerErrorReportValve.java:73)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:641)
        at
org.apache.catalina.core.StandardPipeline.invoke(StandardPipeline.java:480)
        at
org.apache.catalina.core.ContainerBase.invoke(ContainerBase.java:995)
        at
org.apache.catalina.core.StandardEngineValve.invoke(StandardEngineValve.java:174)
        at
org.apache.catalina.core.StandardPipeline$StandardPipelineValveContext.invokeNext(StandardPipeline.java:643)
        at
org.apache.catalina.core.StandardPipeline.invoke(StandardPipeline.java:480)
        at
org.apache.catalina.core.ContainerBase.invoke(ContainerBase.java:995)
        at
org.apache.coyote.tomcat4.CoyoteAdapter.service(CoyoteAdapter.java:223)
        at
org.apache.coyote.http11.Http11Processor.process(Http11Processor.java:405)
        at
org.apache.coyote.http11.Http11Protocol$Http11ConnectionHandler.processConnection(Http11Protocol.java:380)
        at
org.apache.tomcat.util.net.TcpWorkerThread.runIt(PoolTcpEndpoint.java:508)
        at
org.apache.tomcat.util.threads.ThreadPool$ControlRunnable.run(ThreadPool.java:533)
        at java.lang.Thread.run(Thread.java:595)

```

D.2 Warnings

- ♦ [Section D.2.1, “No Such LayoutSet Exception,” on page 264](#)

D.2.1 No Such LayoutSet Exception

If no Portal URL and Home URL have been specified in [Section 3.2, “Updating Dashboard Administrative Configurations,” on page 31](#), warnings similar to the following can appear:

```
2007-04-20 17:09:44,520 WARN
com.liferay.portal.servlet.filters.virtualhost.VirtualHostFilter -
com.liferay.portal.NoSuchLayoutSetException: No LayoutSet exists
with the key {companyId=managedobjects.com,virtualHost=qaredhat40}
```

This warning has no impact on the functioning of the Dashboard.

E Documentation Updates

This section contains information on documentation content changes that were made in the *Dashboard Guide* after the initial release of Operations Center 5.0. The changes are listed according to the date they were published.

If you need to know where a copy of the PDF documentation you are using is the most recent, the PDF document includes a publication date on the title page.

- ◆ [Section E.1, “March 2014 Patch Release,” on page 265](#)
- ◆ [Section E.2, “November 2013 Patch Release,” on page 265](#)
- ◆ [Section E.3, “September 2013 Patch Release,” on page 266](#)
- ◆ [Section E.4, “April 2013 Patch Release,” on page 266](#)
- ◆ [Section E.5, “December 2012 Patch Release,” on page 267](#)
- ◆ [Section E.6, “June 2012 Patch Release,” on page 269](#)
- ◆ [Section E.7, “February 2012 Patch Release,” on page 269](#)
- ◆ [Section E.8, “September 2011 Patch Release,” on page 270](#)

E.1 March 2014 Patch Release

In addition, updates were made to the following sections:

Location	Update
“Configuring Default Home for User Groups, Communities and Organizations” on page 86	New configuration properties let you specify landing pages by community and organization memberships.
“Viewing Source Data for Charts” on page 122	The Charting portlet has options to allow you to view source data for charts.
“Understanding Data Types in Operations Center” on page 104 and “Configuring the Charting Portlet” on page 144	New Charting portlet.
“Configuring a Performance Portlet” on page 157	The Performance portlet respects the user's time zone, versus using the time zone of the Operations Center server.

E.2 November 2013 Patch Release

In addition, updates were made to the following sections:

Location	Update
"Configuring the Dashboard Database" on page 18	Update to the version of SQL Server .jar file that is provided.
Section 3.2.2, "Updating the Dashboard Site Name & Logo," on page 33	Additional instructions for updating the Dashboard site name.
Section 8.9, "Configuring the Public End User View Portlet," on page 169	Update illustration to show actual condition status colors.

E.3 September 2013 Patch Release

In addition, updates were made to the following sections:

Location	Update
Section 2.2.3, "Configuring the Dashboard Database," on page 18	New subsection describes how to configure for SSO with Microsoft SQL databases.
Section 2.2.4, "Verifying the Dashboard Default Time Zone for User Accounts," on page 20	Default time zone for Dashboard users is UTC.
Section 2.2.5, "Configuring the Dashboard and Operations Center," on page 20	New option allows you to change the location setting for the JDK used by the Dashboard, and configure Java settings.
Section 7.6, "Configuring URL Linking for the Layout Portlet," on page 121	Define a fully-qualified URL for an element. Clicking the element in the Layout view opens the Web page instead of drilling into the hierarchy.
Section 8.5.2, "Configuring the Layout Portlet," on page 154	Starting point link has been changed to a home icon. A back/history option now allows navigation to previously viewed parent elements.
Section 7.1.2, "Understanding Custom Colors in Portlets," on page 106	New section to describe support for custom condition and severity colors.
Section 7.4, "Using Navigation Mode to Drive Multiple Portlets," on page 110	The Navigation portlet cannot be driven.
Previous Section 12.1, "Setting the JBVM Memory"	This section has been removed. JDK and memory settings can now be configured in the Configuration Manager. For more information, see Section 2.2.5, "Configuring the Dashboard and Operations Center," on page 20 .

E.4 April 2013 Patch Release

Global updates were made to installation and file path references for Operations Center and Operations Center features, as follows:

- ♦ **Operations Center:** The location of the main Operations Center installation is shown as `OperationsCenter_install_path`
- ♦ **Operations Center Dashboard:** The location of the Dashboard is shown as `OperationsCenter_Dashboard_install_path`

- ♦ **Operations Center Configuration Management System (CMS):** The location of the CMS is shown as `OperationsCenter_CMS_install_path`
- ♦ **Operations Center Experience Manager:** The location of the Experience Manager is shown as `OperationsCenter_ExperienceManager_install_path`

In addition, updates were made to the following sections:

Location	Update
Chapter 2, “Dashboard Installation,” on page 13	The section detailing hardware and deployment requirements has been removed. For this information, see “ Supported Versions and Hardware Requirements ” in the <i>Novell Operations Center 5.0 Getting Started Guide</i> .
Section 2.2.1, “Verifying Your Operations Center Server’s Default Accounts and Configuration Settings,” on page 14	The X11 Display Name must be specified for Dashboards running on Unix systems.
Section 2.2.2, “Installing the Dashboard,” on page 16	If installing on Solaris x64, modifications to the <code>ApacheSetclasspath.sh</code> file are required in order for the Dashboard to start successfully.
Section 3.2.2, “Updating the Dashboard Site Name & Logo,” on page 33	Fixed incorrect paths given for files or directories.
Section 3.11, “Default Portlet Settings,” on page 45	
Section 7.8.2, “Configuring Performance Data Point Retrieval from the Operations Center Server,” on page 124	
Section 7.8.3, “Configuring Regular Expression Look Up for the Performance Portlet,” on page 125	
Section 4.1.1, “Understanding User and Group Synchronization,” on page 50	After the initial synchronization of user accounts, give the Admin group administrative permissions in the Dashboard.
Section 5.7.1, “The Default Themes Library,” on page 79	A new default theme, called <i>Sleek</i> , is available in the December 2012 patch release.
Section 5.7.3, “Installing Additional Themes,” on page 85	Browsing and installing Liferay themes via the dashboard page is no longer supported by Liferay. Instead new themes can be downloaded from the Liferay Marketplace.
Section 8.4, “Configuring the Information Portlet,” on page 147	New charting feature available for the Information portlet.
Section 8.11, “Search Portlet,” on page 171	The Search portlets finds only native instances of an element in the Operations Center hierarchy and will not return any linked instances of an element..

E.5 December 2012 Patch Release

Updates were made to the following sections:

Location	Update
Section 2.2.4, "Verifying the Dashboard Default Time Zone for User Accounts," on page 20	Regardless of time zone settings customized for Dashboard users, data in the Layout portlet displays based on the time zone of the Operations Center server.
Section 3.4.4, "Configuring the "Remember Me" Feature and Setting Browser Cookie Lifespan," on page 37	Settings to disable the Remember Me feature or configure the length of browser cookie lifespan.
Section 5.7.3, "Installing Additional Themes," on page 85	Added instructions on uploading and installing a custom theme.
Section 7.1, "Understanding the Operations Center Portlets," on page 103	The matrix showing various data types has been updated to include the new Information portlet.
Section 7.2, "Configuring Portlet View Links," on page 107	You can select whether to hide or show the Actions menu on portlets.
Section 7.3, "Configuring Home and Starting Elements," on page 108	You can select a starting element when configuring the Information portlet.
Section 7.8.4, "Selecting an Alternate Operations Center Server Connection," on page 126	An alternate Operations Center server can be configured for the new Information portlet.
Section 7.8.6, "Automatic Data Updates with Push Technology," on page 131	The new Information portlet uses push technology to update portlet information.
Section 8.1, "Configuring the Alarms Portlet," on page 134	Export alarms data to PDF. The Alarm portlet does not support push updates for SLA alarms
Section 8.4, "Configuring the Information Portlet," on page 147	The new Information portlet gives you a summary view of element information including a tabular views of properties, alarms, root cause and impacted, and layout diagrams. Configurations allow you to customize the portlet for your needs. Regardless of time zone settings customized for Dashboard users, data in the Layout tab of the Information portlet displays based on the time zone of the Operations Center server.
Section 8.5, "Configuring the Layout Portlet," on page 153	Regardless of time zone settings customized for Dashboard users, data in the Layout portlet displays based on the time zone of the Operations Center server.
Section 8.7, "Configuring a Performance Portlet," on page 157	Regardless of time zone settings customized for Dashboard users, data in the Performance portlet displays based on the time zone of the Operations Center server.
Section 12.3, "Enabling the Dashboard for Section 508 Accessibility," on page 228	Alarm summary charts (Information portlet) are not Section 508 compliant. Access the Dashboard using Internet Explorer 8 or Firefox when Section 508 Accessibility is enabled.

E.6 June 2012 Patch Release

Updates were made to the following sections:

Location	Update
Section 7.3.2, "Configuring Starting Elements for Portlets," on page 110	Additional detail has been added for portlet "drive" configurations (also referred to as Navigation mode).
Section 7.5, "Creating Custom Right-Click Menus," on page 112	Custom menu options have been reconfigured for increased usability and comprehension. All options remain but most labels have been changed.
Section 7.8.3, "Configuring Regular Expression Look Up for the Performance Portlet," on page 125	New sections explains how to create a custom look up list for regular expression when configuring the Performance Portlet.
Chapter 8, "Configuring Operations Center Portlets," on page 133	Portlet configurations (Preferences) have been reconfigured for increased usability and comprehension. All options remain but most labels have been changed. For example, in the Alarms portlet, the <i>Show Alarm Options</i> option has been renamed to <i>Enable alarm selectors and filter options</i> . Some options have been reordered in the page.
Section 8.1.2, "Performing Alarms General Configuration," on page 137	New configuration options added for enabling Navigation mode and configuring alarm updates when alarms are selected.
Section 8.5.2, "Configuring the Layout Portlet," on page 154	New refresh options allows you to configure portlet refresh on timed interval. Using the Layout portlet in Flash output does not render custom background colors.
Section 8.7, "Configuring a Performance Portlet," on page 157	New preview feature allows you to see a dynamic list of profile expressions matches as you type a regular expression. New feature to view data point details on NetIQ AppManager elements.

E.7 February 2012 Patch Release

Updates were made to the following sections:

Location	Update
Section 3.9, "Understanding Portal Properties Files," on page 43	Settings can now allow configuration of a home page based on user group.
Section 4.1.1, "Understanding User and Group Synchronization," on page 50	Groups should be created and maintained in the Operations Center console. Any groups created in the Dashboard are not maintained and are automatically deleted.
Section 5.8, "Configuring Default Home for User Groups, Communities and Organizations," on page 86	Instructions on to configure a custom home page based on user group.

Location	Update
Section 8.6, "Configuring the Navigation Portlet," on page 156	The Navigation portlet can now be configured to use automatic refresh in the portlet preferences.
Section 8.7.2, "Configuring the Performance Portlet," on page 159	Added information regarding maximum data points displayed when not using the <i>Show Raw Data</i> option in Step 6 on page 165 .

E.8 September 2011 Patch Release

Updates were made to the following sections:

Location	Update
Section 6.2, "Adding Portlets," on page 94	Operations Center portlet are no longer located under the Novell structure. The are found under Operations Center when adding a new application/portlet.
Section 8.1.2, "Performing Alarms General Configuration," on page 137	<p>New feature in Alarms portlet preferences allows you to select alarm columns based on a list sampled from the current alarms. You can also now define multiple configurations for use when the portlet is dynamically updated via a selection in another portlet.</p> <p>The alarm pagination configuration option is no longer available for the Alarms portlet because of performance issues.</p>
Section 8.7.2, "Configuring the Performance Portlet," on page 159	Regular expressions can now be used when charting performance profile expressions.
Section B.2.1, "Running an Unattended Installation," on page 244	Correction made to the command used to create a response file.