



NetIQ Advanced Authentication Framework - Group Policy Templates

Administrator's Guide

Version 5.1.0

Table of Contents

	1
Table of Contents	2
Introduction	4
About This Document	4
Group Policies	5
Adding Group Policies	8
Security Policies	9
Authenticator Life Period	10
Credential Providers Filter Settings	11
Default Method for Other User	13
Disabled PIN Host List	15
Disable Random Password Generation by Default	17
Do not Allow Administrators to Remove User Credentials	19
Enable Caching	21
Enable PIN Caching	23
Hide Password Mode from Logon UI	25
Lock Account on Failed Logon	27
Number of Cached Users	29
Password Length	30
PIN Restrictions	32
Use Domain Password as PIN	34
Event Log Policies	36
Freeze Communication If Log Server Is Unavailable	37
Log Servers	39
Register All Password Management Events	40
Register All User Authentication Events	42
Network Policies	43
Always resolve client name	43
Enable 802.11 pre logon authentication	44
Force to use NTLM authentication during logon	46
RPC dynamic port selection allowed	48
RPC static port selection allowed	49
Runtime Environment	51
Show Enrolled Card Owner	51
Users and Groups	53
Customize Users and Group Settings	53
Workstation Policies	56
Alternative Logo for Credential Provider	57
Alternative Logo for GINA and Wizard	59
Deny to Specify Authenticator Comment at Enrollment	61
Deny to Start Client Tray When User Logs on to Windows	62
Disable First Logon Enroll Wizard	63
Disable "Use Dial-up Connection" Option	65

Do Not Allow to Skip Welcome Window	66
Enable Device Detection for All	68
Enhanced Reaction on Device Events	70
Last Used Server Timeout	71
Lifetime of Notification about Password Reset	73
Linked Logon Behavior	75
Master Server	76
Tap and Go	80
"Use Current Settings as Defaults" Option Management for PC Unlocking	82
"Use Current Settings as Defaults" Option Management	84
Web Service Client Timeouts	86
Repository Policies	88
ADAM Settings	89
Enable Novell Support	91
Repository	92
UI Look & Feel Policies	94
Show Cache Messages	95
Show OSD Num Pad	97
Index	99

Introduction


About This Document


Purpose of the Document


This Group Policy Templates Guide is intended for system administrators and describes how to control the working environment of user and computer accounts using NetIQ Advanced Authentication Framework Group Policy Templates.


Document Conventions

This document uses the following conventions:

 **Warning.** This sign indicates requirements or restrictions that should be observed to prevent undesirable effects.

 **Important notes.** This sign indicates important information you need to know to use the product successfully.

 **Notes.** This sign indicates supplementary information you may need in some cases.

 **Tips.** This sign indicates recommendations.

- Terms are italicized, e.g.: ***Authenticator***.
- Names of GUI elements such as dialogs, menu items, and buttons are put in bold type, e.g.: the **Logon** window.

Group Policies

NetIQ Advanced Authentication Framework solution has 45 group policies of its own. The policies are divided into sections depending on their application:

The **Security** section includes security policies allowing the enhancement of data protection:

- [Authenticator life period](#) – allows you to specify the “life time” of an authenticator.
- [Credential providers filter settings](#) – allows you to create a list of credential providers you want to turn off.
- [Default method for Other user](#) - allows you to specify the authentication method that will be used by default on the logon screen for the “Other user”.
- [Disabled PIN host list](#) - allows you to logon just by a device.
- [Disable random password generation by default](#) – defines the default state of the Generate random password for account setting.
- [Do not allow administrators to remove user credentials](#) - disables the ability for administrator to remove individual enrollments for a user.
- [Enable caching](#) - allows you to enable authenticators caching.
- [Enable PIN caching](#) – allows you to enable a user to only type in PIN once every 8 hours.
- [Hide password mode from logon UI](#) - disables the Password mode in authentication methods menu on workstations with NetIQ Client installed.
- [Lock account on failed logon](#) - allows you to lock the user account after invalid logon attempts.
- [Number of cached users](#) - allows you to define the number of cached users.
- [Password length](#) – allows you to define the length of the automatically generated password.
- [PIN restrictions](#) – allows you to define the minimum length of PIN code for PIN code devices.
- [Use domain password as PIN](#) - allows you to use the domain password together with a card.

The **Event Log** section includes policies allowing to determine logging settings:

- [Freeze communication if log server is unavailable](#) – defines the rules for resolving conflicts should the remote log server be unavailable at the moment of writing an event onto it.
- [Log servers](#) – allows you to define the list of log servers.
- [Register all password management events](#) – allows you to define the accuracy with which the event log is kept concerning passwords change.
- [Register all user authentication events](#) – allows you to define the accuracy with which the event log is kept concerning users authentication.

The **Network** section includes policies allowing to enable or disable dynamic/static port.

- [Always resolve client name](#) - allows you to resolve the name of the client.
- [Enable 802.11 pre logon authentication](#) - allows you to enable the detection of network connections during logon.
- [Force to use NTLM authentication during logon](#) - allows you to use automatically NTLM authentication during logon.
- [RPC dynamic port selection allowed](#) - allows you to use a dynamic port for client-server interaction.
- [RPC static port selection allowed](#) - allows you to use static port for client-server interaction.

The **Runtime Environment** section includes a policy allowing to enable or disable showing of the user who has enrolled card when other user attempts to enroll the same card.

- [Show enrolled card owner](#) - allows you to enable or disable showing of the user who has enrolled card when other user attempts to enroll the same card.

The **Users and Groups** section includes a policy allowing to specify users and groups settings manually.

- [Customize users and groups settings](#) - allows you to specify users and groups settings manually.

The **Workstation** section includes policies allowing to modify GINA behavior:

- [Alternative Logo for Credential Provider](#) – allows you to define the location of an alternative logo displayed in Client (Credential Provider) windows.
- [Alternative Logo for GINA and Wizard](#) – allows you to define the location of an alternative logo displayed in Client (GINA) windows.
- [Deny to specify an authenticator comment at enrollment](#) – allows you to disable user comments at authenticator enrollment/re-enrollment.
- [Deny to start Client Tray when user logs on to Windows](#) – allows you to define whether NetIQ Advanced Authentication Framework Client Tray is started automatically when a user logs on to Windows or not.
- [Disable first logon enroll wizard](#) - allows to disable the NetIQ first logon wizard autostart.
- [Disable "Use Dial-up connection" option](#) – allows you to manage the Use Dial-up connection option in the Logon window.
- [Do not allow to skip Welcome window](#) – allows you to define whether to skip the Welcome window or not.

- [Enable device detection for all](#) - allows to perform a device detection when logged in with card or flash drive.
- [Enhanced reaction on device events](#) – allows custom actions during device in and out events.
- [Last used server timeout](#) - allows you to specify time during which the last Authenticore Server can be used for authentication.
- [Lifetime of notification about password reset](#) – allows you to setup lifetime of user's notification about user's password reset by administrator.
- [Linked logon behavior](#) - determines the behavior of a linked logon.
- [Master server](#) - allows you to specify the list of Master servers.
- [Tap and Go](#) – enables you to turn on the Tap and Go function.
- ["Use current settings as defaults" option management for PC unlocking](#) – allows you to manage the Use current settings as defaults option in the Unlock Computer window.
- ["Use current settings as defaults" option management](#) – allows you to manage the Use current settings as defaults option in the Logon window.
- [Web service client timeout](#) - allows you to set duration of authentication timeout for non-domain joined clients.


The **Repository** section includes policies allowing to edit NetIQ repository.

- [ADAM settings](#) – allows you to configure whether ADAM/AD-LDS is used as a repository.
- [Enable Novell support](#) - allows you to activate the support mode of Novell Domain Services for Windows for the case if you are using Active Directory Lightweight Directory Services for NetIQ data storage in domain based on Novell eDirectory.
- [Repository](#) – allows you to choose whether to use native Active Directory or ADAM/AD-LDS as NetIQ repository.

The **UI Look & Feel** section includes policies designed for terminal clients.

- [Show Cache Messages](#) - allows not to show the message on a workstation that caching is enabled or disabled.
- [Show OSD Num Pad](#) - provides an On Screen Keyboard option during logging on.

Adding Group Policies

 It is required to have at least Microsoft Windows Server 2008 or Microsoft Windows 7 with RSAT to manage group policy settings.

The main policy templates (Security, Event Log, and Workstation) are stored locally in **NAAF.admx** file in **C:\Windows\PolicyDefinitions** folder. The **NAAF.adml** file is stored in **C:\Windows\PolicyDefinitions\en-US** folder. After the unattended installation, policies appear in **Group Policy Management Editor** under **Computer Configuration > Policies > Administrative Templates: Policy definitions**.

Security Policies

The **Security** section includes security policies allowing the enhancement of data protection.


It includes:

- [Authenticator life period](#)
- [Credential providers filter settings](#)
- [Default method for Other user](#)
- [Disabled PIN host List](#)
- [Disable random password generation by default](#)
- [Enable caching](#)
- [Enable PIN caching](#)
- [Hide password mode from logon UI](#)
- [Lock account on failed logon](#)
- [Number of cached users](#)
- [Password length](#)
- [PIN restrictions](#)
- [Use domain password as PIN](#)

Authenticator Life Period

The **Authenticator life period** policy allows you to specify the 'life time' of an authenticator.

This policy is used to counteract all possible attempts to intercept IP-packages and crack the system.



The screenshot shows the 'Authenticator life period' configuration dialog box. It features a title bar with the text 'Authenticator life period' and standard window controls. Below the title bar are two buttons: 'Previous Setting' and 'Next Setting'. The main area contains three radio buttons: 'Not Configured', 'Enabled' (which is selected), and 'Disabled'. To the right of these buttons is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' section with two dropdown menus. At the bottom left, there is an 'Options:' section with a label 'Authenticator validity period (in minutes):' and a spin box containing the number '5'. To the right of the spin box is a 'Help:' section with a text area containing the following text: 'The policy determines the length of a current authenticator "life period". The "Authenticator validity period (in minutes)" setting allows you to specify how long a current authenticator remains "valid". In case the time period between authenticator submission and authenticator verification exceeds the specified value, the authenticator is considered "invalid". This is a protective measure in case someone attempts to intercept IP-packages and gain unauthorized access to the system. In case the policy is not configured or disabled, default authenticator "life time" equals to 5 minutes.' At the bottom right of the dialog box are three buttons: 'OK', 'Cancel', and 'Apply'.

The **Authenticator validity period** setting allows you to define how long an authenticator obtained from the user remains "valid" before it is checked on Authenticore server.

If the time interval between the moment the authenticator is received and the moment it is checked on Authenticore server exceeds the specified value, the authenticator is considered invalid.


To access the **Authenticator life period** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework


AuthenticatorLifePeriod:

- value type: REG_DWORD
- value data: 0x00000005 (5)
- description: 5 displays the authenticator validity period (in minutes)

 If the policy is not defined or is disabled, the "life time" of an authenticator is 5 minutes.

Credential Providers Filter Settings

The **Credential providers filter settings** policy allows the system administrator to enable third party credential providers. The citrix credential provider can be unfiltered using the checkbox. For any other third party Credential Provider, please, lookup the GUID in the following registry location: HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential Providers.



To turn off some of the CP, **Filter out 3-rd party credential providers** option should be checked.

The list of allowed credential providers is shown in the **Show Contents** window, that appears after clicking the **Show** button.

In order to set a policy for listing all the important CPs, clear the **Filter out 3-rd party credential providers** checkbox.

If the **Deny loading Credential Provider to the MSTSC process** checkbox is selected, the standard authentication by password will be required in Remote Desktop Connection (RDC) application. Authentication with NetIQ Advanced Authentication Framework will be required only if the checkbox is cleared.

To configure the **Deny loading Credential Provider to the MSTSC process** policy correctly, the **Prompt for credentials on client side** setting should be enabled. For more information, follow the [link](#).

To access the **Credential providers filter settings** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework\Filter\AllowedCPs


1:

- value type: REG_SZ
- value data: 5
- description: 5 displays the configured number of the allowed credential providers

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework\Filter

MsTscException:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 Only NetIQ CP is listed by default, however some applications may substitute it with their CPs.

Default Method for Other User

The **Default method for Other user** policy allows you to specify the authentication method that will be used by default on the logon screen for the "Other user".

The screenshot shows a Windows dialog box titled "Default method for Other user". At the top, there are "Previous Setting" and "Next Setting" buttons. Below these are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of the radio buttons is a "Comment:" text box. Below the radio buttons is a "Supported on:" section with a dropdown menu. Underneath, there are "Options:" and "Help:" sections. The "Options:" section contains a "Default method GUID" text box. The "Help:" section contains a text area with the following text: "The policy allows you to specify the authentication method that will be used by default on the logon screen for the 'Other User'. To configure the authentication method that will be used by default on the logon screen for the 'Other User', specify the BSP GUID in the format {the required BSP GUID}. For example, 9D5D01EF-76B0-1749-838B-C1441F7E23B3 means that Security Questions method of authentication is used by default for the 'Other User'." At the bottom of the dialog box are "OK", "Cancel", and "Apply" buttons.

To configure the authentication method that will be used by default on the logon screen for the "Other user", specify the BSP GUID in the format {the required BSP GUID}.


To access the **Default method for Other user** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

OtherUserDefMethod:


- value type: REG_SZ
- value data: {9D5D01EF-76B0-1749-838B-C1441F7E23B3}
- description: {9D5D01EF-76B0-1749-838B-C1441F7E23B3} means that Security Questions method of authentication is used by default for the "Other user"

 To get the required value of BSP GUID, check the following registry key: HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\BSP. It contains subkeys with GUIDs of all installed authentication providers. Check subkeys to find the required authentication method. The subkey name is the required BSP GUID.

 The **Default method for Other user** policy works only with version 4.10 and newer.

Disabled PIN Host List

The **Disabled PIN Host List** policy allows you to logon just by a device. This policy guarantees fast access to the system as PIN is not needed for logon.



To access the **Disabled pin hosts list** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authntas Advanced Authentication - > Security**.

Registry settings:

HKEY_ LOCAL_ MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\DisabledPinHostList

Host1 (the specified host name is displayed in the registry parameter):


- value type: (REG_SZ)
- value data: 1

- description: 1 displays the value that was added to the Show Contents window

 The **Disabled PIN Host List** policy requires to have

1. The enabled **Enable PIN Caching** policy,
2. Reverse lookup zones must be configured on DNS server.

 The **Disabled PIN Host list** policy is not supported by FIDO U2F authentication provider.

 If the policy is enabled, adding comments to authenticator enrollment is not allowed. If the policy is not defined or is disabled, adding comments to authenticator enrollment is allowed.


Click the **Enabled** radio button and the **Show** button. The window with the opportunity of adding computers and IP addresses will appear. On each line you may add either an IP address (e.g. 10.2.0.56), or a DNS name (e.g. wks045.companyname.com).

After all computers and IP addresses that will not need to enter PIN to logon are added, click the **OK** button to save changes. Then click the **Apply** button to save all the changes.

When the changes are saved, PIN will not be required for the specified list of computers during the authentication.

Disable Random Password Generation by Default

The **Disable random password generation by default** policy defines the default state of the **Generate random password** for account setting.



To access the **Disable random password generation by default** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework


DisableRandomPassword:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

- ✱ If you enable this policy, the **Generate random password for account** setting will be unchecked by default when you create user or edit user's properties.
- ✱ If you disable this setting or do not configure it, the **Generate random password for account** setting will be checked by default when you create user or edit user's properties.

Do not Allow Administrators to Remove User Credentials

The **Do not allow administrators to remove user credentials** policy disables the ability for administrator to remove individual enrollments for a user. The policy is disabled by default.



To access the **Do not allow administrators to remove user credentials** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> AuthnAs Advanced Authentication -> Security**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

DisableRemoveTemplatesByAdmin:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled


Enable Caching

The **Enable caching** policy allows you to disable local authenticators caching on workstations with the installed Client.



The **Enable caching** policy is enabled by default.

To disable caching, click the **Disabled** radio button. To save changes, click the **Apply** button.

 The changes take effect only after group policy refresh.

To access the **Enable caching** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.


Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
IsCacheEnabled:


- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the caching is enabled


Enable PIN Caching

The **Enable PIN caching** policy is applicable for a second factor (PIN or Password). The **Enable PIN caching** enables the user to only type in his/her PIN (or Password) once during the specified time period (8 hours by default). Within the PIN cache expiration period the user uses only one factor (e.g. just tap their card) for authentication. After the PIN cache expiration period the user needs to provide the second factor (PIN or Password) again.

 If the policy is not defined or is disabled, the user should type in his/her PIN during every authentication process.

The policy **Do not clear PIN cache when switching to a new server** allows to enable usage of the PIN cache synchronization between Authenticore Servers. When the policy is not enabled we reset a PIN cache if a Client goes to a new Authenticore Server. In this case user will need to provide the both authentication factors. We use this behavior, because the PIN cache sync may work not stable in networks with large number of Active Directory sites, which are located in different countries and continents. Therefore it's recommended to have the policy disabled for such companies. Because finally usage of the policy may cause authentication failures in case of PIN cache state is out of sync, when PIN is not asking on a Client, but a Server is awaiting for it. The policy may be used in small local companies. The policy is presented from v4.12.

 If you had the option **Do not clear PIN cache when switching to a new server** enabled and you disabled it, the PIN cache will not be reset when changing the Authenticore Server, the changes will be affected only when the current PIN cache is expired.



To access the **Enable PIN caching** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authasas Advanced Authentication - > Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

LastLogonDBEnabled:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the Enable PIN caching policy is enabled

LastLogonDBExpirePeriod:

- value type: REG_DWORD
- value data: 0x000001e0 (480)
- description: 480 displays the configured PIN cache expiration period (in minutes)

PreservePinCacheBetweenServers:

- value type: REG_DWORD
- value data: 0x00000001 (1)

- description: 1 means that the policy Do not clear PIN cache when switching to a new server is enabled

* The **Enable PIN caching** policy is not supported by FIDO U2F authentication provider.

* If **Enable PIN caching** policy may be used together with **Disabled PIN Host List** policy, then it will be possible to configure a list of workstations that will not require PIN code.


* PIN caching is updated:

- once per 5 minutes in the background in case when Authenticore Server and Client are within one AD site;
- once per 60 minutes in the background in case when Authenticore Server and Client are not within one AD site.

It may be required to enter PIN/password once again during cache synchronization after the authentication when both tapping the card and entering the PIN/password were used.

Hide Password Mode from Logon UI

If you enable this setting, the "**Password**" mode will not be shown in authentication methods menu on workstations with NetIQ Client installed. If you disable this setting or do not configure it, the "**Password**" mode will be shown in authentication methods menu.




To access the **Hide password mode from logon UI** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

HidePasswordMode:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- 1 means that the policy is enabled


 Ensure that all users of workstation on which you want to enable this policy have at least one enrolled authenticator. Otherwise, you will have problems with user logon.

Lock Account on Failed Logon

If this policy is enabled, the **user account will be locked after invalid logon attempts** (depending on number configured in the [Account lockout threshold](#) policy) regardless of authentication mode. In this case, the user will get an authorization error "*The referenced account is currently locked out and may not be logged on to*".

If this policy is disabled or not configured, the user account will be locked after invalid logon attempts by password only (depending on number configured in the [Account lockout threshold](#) policy).

You also can configure [Account lockout duration](#).



To access the **Lock account on failed logon** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

LockAccountOnFailedLogon:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Number of Cached Users

The **Number of cached users** policy allows you to define the number of user accounts that can be stored in the computer cache. When the number of cached user accounts reaches the number that is specified in the **Number of cached users** policy, then the latest user account is deleted from the computer cache after adding the new user account to it.



To access the **Number of cached users** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

NumberOfCachedUsers:

- value type: REG_DWORD
- value data: 0x0000001e (30)
- description: 30 displays the number of user accounts that can be stored in the computer cache

Password Length

The **Password length** policy allows you to define the length of the automatically generated password.




The **Generated password length** setting allows you to specify the length of automatically generated random passwords (in symbols).

To access the **Password length** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authasas Advanced Authentication - > Security**.


Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
GeneratePasswordLength:

- value type: REG_DWORD
- value data: 0x00000003f (63)
- description: 63 displays the generated password length

 The specified value and the frequency of passwords change must not conflict with the values defined by the standard policies of the Account Policy/Password Policy section:

- Password must meet complexity requirements
- Minimum password length
- Enforce password history

 If the policy is not defined or is disabled, the password length equals to the maximum of 63 symbols.

PIN Restrictions

The **PIN restrictions** policy allows you to define the minimum length of the PIN code for PIN code devices (for Universal Card authentication provider, Flash+PIN authentication provider).

The screenshot shows the 'PIN restrictions' configuration window. It features a title bar with the text 'PIN restrictions' and standard window controls. Below the title bar, there are two buttons: 'Previous Setting' and 'Next Setting'. The main area contains three radio buttons: 'Not Configured', 'Enabled' (which is selected), and 'Disabled'. To the right of these buttons is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' section with two dropdown menus. Underneath, there are two sections: 'Options:' and 'Help:'. The 'Options:' section contains a 'Minimum PIN length:' label followed by a dropdown menu showing the value '4'. The 'Help:' section contains a text box with the following text: 'PIN restrictions policy allows you to define minimum PIN code length for corresponding BSP types (Flash PIN, Universal Card, etc). To specify the minimum PIN code length, use the "Minimum PIN length" setting. In case the policy is not configured or is disabled, the minimum PIN length is 4 characters.' At the bottom of the window, there are three buttons: 'OK', 'Cancel', and 'Apply'.

The **Minimum PIN length** setting allows you to specify the minimum length of PIN code (in symbols).


To access the **PIN restrictions** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authasas Advanced Authentication - > Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\BSP\PINRestrictions

MinLength:

- value type: REG_DWORD
- value data: 0x00000004 (4)
- description: 4 displays the configured minimum PIN length

 If the policy is not defined or is disabled, the minimum length of PIN code is 4 symbols.

Use Domain Password as PIN

When this policy is enabled, a user should use the domain password together with a card. This will replace the use of a PIN code.


The screenshot shows a dialog box titled "Use domain password as PIN". At the top, there are "Previous Setting" and "Next Setting" buttons. Below these, there are three radio button options: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these options is a "Comment:" text box. Below the radio buttons is a "Supported on:" section with a list box. At the bottom left, there is an "Options:" section with an empty text box. At the bottom right, there is a "Help:" section with a text box containing the text: "When this policy is enabled a user should use the domain password together with a card. This will replace the use of a PIN code." At the very bottom of the dialog box are "OK", "Cancel", and "Apply" buttons.


To access the **Use domain password as PIN** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Security**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
DomainPasswordAsPin:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 It is not allowed to change this policy after cards have been enrolled. You need to re-enroll the authenticators or disable the policy.

 To enable the **Use domain password as PIN** policy, it is required to install Password Filter on all Domain Controllers. Otherwise if the password is reset, changed or generated automatically, the password will be desynchronized and it will be required to re-enroll authenticators.

Event Log Policies

The **Event Log** section includes policies allowing you to determine logging settings.

It includes:

- [Freeze communication if log server is unavailable](#)
- [Log Servers](#)
- [Register all password management events](#)
- [Register all user authentication events](#)

Freeze Communication If Log Server Is Unavailable

The **Freeze communication if log server is unavailable** policy defines the rules for resolving conflicts in case the remote log server was unavailable at the moment of writing an event onto it. The “freezing” of the communication with the faulty log server minimizes attempts to connect to the remote log server while it is unavailable and increases log service fault tolerance.

The screenshot shows a Windows-style dialog box titled "Freeze communication if log server is unavailable". At the top, there are "Previous Setting" and "Next Setting" buttons. Below the title bar, there are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these is a "Comment:" text area. Below the radio buttons is a "Supported on:" text area. Underneath, there are "Options:" and "Help:" sections. The "Options:" section contains four spinners: "Max time-out period (in minutes):" set to 120, "Normal time-out period (in minutes):" set to 30, "Time interval to restore communication (in minutes):" set to 5, and "Increasing time interval for the next time-out period (in minutes):" set to 5. The "Help:" section contains a text area with the following text: "The policy determines logic according to which communication with unavailable remote event log server is suspended/restored. If a remote event log server proves unavailable and an event cannot be received and recorded, communication with this server is 'frozen' (suspended). This measure is intended to minimize the number of connection setup attempts when remote event log server is unavailable and to increase fault tolerance of the log server. Duration of the suspense period is modified by means of the 'Time interval to restore communication' setting. When the suspense period is over and a new event occurs, the event log Client attempts to restore communication with the event log server. Duration of communication recovery period is modified by means of the 'Normal time-out period' setting." At the bottom right, there are "OK", "Cancel", and "Apply" buttons.

If the remote event log server becomes unavailable in the moment of recording an event, the communication with this remote log server is “frozen” for the time period specified by the **Time interval to restore communication (in minutes)** setting. After the period elapses, and a new event occurs, a new attempt will be made to establish connection with the remote log server. The attempts continue during the time period specified by the **Normal time out period (in minutes)** setting. In case the connection to the faulty log server is not restored within this time period, the connection “freezes” for a longer period. The increase in “freeze” duration is

specified by the **Increasing time interval for the next time-out period (in minutes)** setting. The “freeze” duration increases until it reaches the value specified by the **Max time-out period (in minutes)** setting. After that, the “freezing” time is reset to its initial state specified by the setting.

To access the **Freeze communication if log server is unavailable** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies -> Administrative Templates -> Authasas Advanced Authentication -> Event Log**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

MaxTimeoutPeriod:

- value type: REG_DWORD
- value data: 0x00000078 (120)
- description: 120 displays the max time-out period (in minutes)

ReconnectPause:

- value type: REG_DWORD
- value data: 0x00000005 (5)
- description: 5 displays time interval to restore communication (in minutes)

ReconnectPauseIncrement:

- value type: REG_DWORD
- value data: 0x00000005 (5)
- description: 5 displays increasing time interval for the next time-out period (in minutes)

TimeoutPeriod:

- value type: REG_DWORD
- value data: 0x0000001e (30)
- description: 30 displays normal time-out period (in minutes)



If the policy is not defined or disabled, then its parameters have the following default values:

Time interval to restore communication (in minutes): 5;


Normal time-out period (in minutes): 30;

Increasing time interval for the next time-out period (in minutes): 5;

Max time-out period (in minutes): 120.

Log Servers

The **Log servers** policy allows you to define the list of the Log Servers, which will collect the NetIQ Advanced Authentication Framework logs from all machines where the policy is applied.



This **Log servers** box should contain the list of log server names. Put the names in one line in UPN or NetBIOS format and separate them with semicolon. Do not use spaces. *Example:* Computer1; Computer2.domainname.com; Computer3.

To access the **Log servers** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Event Log.**


Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

LoggingServers:


- value type: REG_SZ
- value data: Computer1, Computer2, Computer3
- description: Computer1, Computer2, Computer3 is the list of the defined log servers

These settings do not disable registering events in the local log of the computer. If the policy is not defined or is disabled, NetIQ Advanced Authentication Framework events are recorded in the local log of the computer.

 You may need to enable the policy on Domain Controllers to collect the password management events on the Log Servers.

Register All Password Management Events

The **Register all password management events** policy allows you to define whether successful password change events are recorded into the event log.



To access the **Register all password management events** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies -> Administrative Templates -> Authasas Advanced Authentication -> Event Log.**


Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

PasswordManagement_AllEvents:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled


 The policy requires the pre-installed Password Filter. Otherwise the policy will not work.

 If the policy is enabled, all password change events including successful ones are recorded in the event log.

 If the policy is not defined or is disabled, only unsuccessful password change events are recorded in the event log.

Register All User Authentication Events

The **Register all user authentication events** policy allows you to define whether successful user authentication events are recorded into the event log.





To access the **Register all user authentication events** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Event Log**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
UserAuthentication_AllEvents:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 If the policy is enabled, all user authentication events including successful ones are recorded in the event log.

 If the policy is not defined or is disabled, only unsuccessful user authentication events are recorded in the event log.

Network Policies

The **Network** section includes network policies allowing you to enable or disable dynamic/static port.


It includes:

- [Always resolve client name](#)
- [Enable 802.11 pre logon authentication](#)
- [Force to use NTLM authentication during logon](#)
- [RPC dynamic port selection allowed](#)
- [RPC static port selection allowed](#)

Always resolve client name

If the **Always resolve client name** policy is disabled or not defined, the Authenticore Server doesn't resolve the name of client by IP-address if the **Enable PIN caching** policy is disabled or the **Disabled PIN host list** policy is not defined.

If the **Always resolve client name** policy is enabled, the Authenticore Server will always resolve the name of client.



To access the **Always resolve client name** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Network**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework


AlwaysResolveClientName:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

! Enabling of the policy can affect the performance during authentication.

Enable 802.11 pre logon authentication

The **Enable 802.11 pre logon authentication** policy allows you to enable the detection of network connections during logon. It should be enabled in case EAP is used during logon.



To access the **Enable 802.11 pre logon authentication** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies -> Administrative Templates -> Authasas Advanced Authentication -> Network**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\ (Wow6432Node\) Policies\ NetIQ \ NetIQ Advanced Authentication Framework

802X1Enabled:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Force to use NTLM authentication during logon

If the **Force to use NTLM authentication during logon** policy is enabled, NTLM authentication will be automatically used during logon.



To access the **Force to use NTLM authentication during logon** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authsas Advanced Authentication - > Network**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

RpcForceNtlmAtLogon:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

RPC dynamic port selection allowed

If the **RPC dynamic port selection allowed** policy is enabled, the Authenticore Server uses a dynamic port for client-server interaction. By default the policy is enabled.



To access the **RPC dynamic port selection allowed** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Network**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

RpcDynamicPortAllowed:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled


 If both **RPC dynamic port selection allowed** and **RPC static port selection allowed** policies are enabled then:

- Server will register both endpoints.
- Client will first try to use static port endpoint and then switch to dynamic if static bind failed.

 The server should be restarted after applying the policy.

RPC static port selection allowed

If the **RPC static port selection allowed** policy is enabled, the Authenticore Server uses a static port for client-server interaction. By default the policy is disabled.



The screenshot shows a Windows-style dialog box titled "RPC static port selection allowed". At the top right are "Previous Setting" and "Next Setting" buttons. Below the title bar, there are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these is a "Comment:" text area. Below the radio buttons is a "Supported on:" dropdown menu. Under the "Options:" section, there is a text box labeled "RPC static port:" containing the value "28214". To the right of this is a "Help:" section with a text area containing the text: "If the policy is enabled the Authenticore Server uses a static port for client-server interaction. By default the policy is disabled." At the bottom right of the dialog are "OK", "Cancel", and "Apply" buttons.

To access the **RPC static port selection allowed** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Network**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

RpcStaticPort:

- value type: REG_DWORD
- value data: 0x00006e36 (28214)
- description: 28214 is the port number in case of using static port for client-server interaction (the default port number is 28214)

RpcStaticPortAllowed:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 If both **RPC dynamic port selection allowed** and **RPC static port selection allowed** policies are enabled then:

- Server will register both endpoints;
- Client will first try to use static port endpoint and then switch to dynamic if static bind failed.

 The server should be restarted after applying the policy.

Runtime Environment


The **Runtime Environment** section includes a policy allowing to enable or disable showing of the user who has enrolled card.

It includes:

- [Show enrolled card owner](#)

Show Enrolled Card Owner

The **Show enrolled Card Owner** policy allows you to enable or disable showing of the user who has enrolled card when other user attempts to enroll the same card.



The screenshot shows a Windows-style dialog box titled "Show enrolled card owner". At the top right, there are "Previous Setting" and "Next Setting" buttons. On the left, there are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these is a "Comment:" text box. Below the radio buttons is a "Supported on:" text box. At the bottom left, there is an "Options:" section with a large empty text area. At the bottom right, there is a "Help:" section with a text area containing the text: "Enable or Disable the showing of the user which has enrolled card when other user attempts to enroll the same card". At the bottom center, there are "OK", "Cancel", and "Apply" buttons.

To access the **Show enrolled card owner** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Runtime.**

Registry settings:

HKEY_ LOCAL_ MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\ RTE

RTEShowEnrolledCardOwner:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Users and Groups

The **Users and Groups** section includes a policy allowing to specify users and groups settings manually.

It includes:

- [Customize users and groups settings](#)

Customize Users and Group Settings

The **Customize users and group settings** policy allows you to specify NetIQ service account and groups settings manually. If this policy is enabled and configured, Authenticore Server will use the specified service accounts and groups names.

Customize users and groups settings

Previous Setting Next Setting

Not Configured Comment:

Enabled

Disabled

Supported on:

Options: Help:

Username for Authenticore Service

Groupname for Authenticore Servers

Groupname for Authenticore Admins

Groupname for ADAM Servers

Groupname for Product Admins

This policy provide users and groups settings. If this policy enabled and configured, Authenticore Server will be use custom users and groups

OK Cancel Apply

To access the **Customize users and groups settings** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Users and Groups**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\UsersAndGroups

ADAMServersGroups:

- value type: REG_SZ
- value data: NetIQ Advanced Authentication Framework ADAM Servers
- description: NetIQ Advanced Authentication Framework ADAM Servers displays the specified groupname for ADAM Servers

AuthenticoreAdminsGroup:

- value type: REG_SZ
- value data: Authenticore Admins
- description: Authenticore Admins displays the specified groupname for Authenticore Admins

AuthenticoreServersGroup:

- value type: REG_SZ
- value data: Authenticore Servers
- description: Authenticore Servers displays the specified groupname for Authenticore Servers

AuthenticoreServiceUser:


- value type: REG_SZ
- value data: AuthenticoreService
- description: AuthenticoreService displays the specified username for Authenticore Service



ProductAdminsGroup:

- value type: REG_SZ
- value data: NetIQ Advanced Authentication Framework Admins
- description: NetIQ Advanced Authentication Framework Admins displays the specified groupname for Product Admins

UsersAndGroups:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 Please, take into consideration that user account cannot contain periods or spaces, or end in a period. Any leading periods or spaces are cropped.

-  Use of the @ symbol is not supported with the logon format for Windows NT 4.0 and earlier.
-  During schema extension batch file cannot find registry key, if the [Customize users and group settings](#) policy is disabled. In this case only default values can be found by batch file.

Workstation Policies

The **Workstation** section includes policies allowing you to modify GINA behavior.

It includes:

- [Alternative Logo for Credential Provider](#)
- [Alternative Logo for GINA and Wizard](#)
- [Deny to specify authenticator comment at enrollment](#)
- [Deny to start Client Tray when user logs on to Windows](#)
- [Disable first logon enroll wizard](#)
- [Disable "Use Dial-up connection" option](#)
- [Do not allow to skip welcome window](#)
- [Enable device detection for all](#)
- [Enhanced reaction on device events](#)
- [Last used server timeout](#)
- [Lifetime of notification about password reset](#)
- [Linked logon behavior](#)
- [Tap and Go](#)
- ["Use current settings as defaults" option management for PC unlocking](#)
- ["Use current settings as defaults" option management](#)
- [Web service client timeout](#)

Alternative Logo for Credential Provider

The **Alternative logo for Credential Provider** policy defines the location of an alternative logo displayed by Credential Provider.

*** Credential Provider** is a component of Microsoft Windows Vista/Microsoft Windows 7/Microsoft Windows Server 2008/Microsoft Windows Server 2008 R2 operation systems; it is responsible for user authentication and credentials verification.

*** Alternative logo** is applied for user selection screen, UAC and all authentication methods except for fingerprint.

Alternative Logo for Credential Provider

Alternative Logo for Credential Provider

Previous Setting Next Setting

Not Configured Comment:

Enabled

Disabled

Supported on:

Options: Help:

Logo version

Path to (125x125 pixels) logo image (*.bmp):

The policy determines the location of an alternative logo displayed by NetIQ Advanced Authentication Framework Workstation (Credential Provider).

To make NetIQ Advanced Authentication Framework Workstation display an alternative logo correctly, you should specify the location of this logo in the network or on the local computer.

The size of the logo must be 125x125 pixels.

In case the policy is not configured or disabled, an alternative logo is not displayed.

Note: To optimize the traffic, NetIQ Advanced Authentication Framework Workstation loads an alternative logo from the specified location only once assuming the Logo version or path has been changed.

OK Cancel Apply

To ensure that an alternative logo is displayed in an appropriate way, you need to specify where the logo is stored (this can be a network drive or a local storage).

The size of the logo must be 125x125 pixels.

To access the **Alternative Logo for Credential Provider** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authasas Advanced Authentication - > Workstation.**

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\Brand


CPLogo:

- value type: REG_SZ
- value data: 1
- description: 1 displays the configured logo version

CPLoVersion:

- value type: REG_SZ
- value data: \\netiq\logos\cplogo.bmp
- description: \\netiq\logos\cplogo.bmp displays the configured path to logo image


 To specify the path to the logo file, you should use the server name, NOT its IP-address.


 To optimize the traffic, NetIQ Advanced Authentication Framework Client loads an alternative logo from the specified location only once assuming the Logo version or any of the paths have been changed.

 If the policy is not configured or is disabled, an alternative logo is not displayed.

Alternative Logo for GINA and Wizard

The **Alternative logo for GINA and Wizard** policy allows you to define the location of an alternative logo displayed in NetIQ Advanced Authentication Framework Client (GINA) windows. This logo is also used in the **Enrollment wizard**.

 **GINA (Graphical Identification and Authentication)** is a component of Microsoft Windows 2000/ Microsoft Windows Server 2003 operation systems; it is responsible for user authentication and credentials verification.



The screenshot shows the 'Alternative Logo for GINA and Wizard' dialog box. It features a title bar with the text 'Alternative Logo for GINA and Wizard' and standard window controls. Below the title bar are 'Previous Setting' and 'Next Setting' buttons. The main area contains three radio buttons: 'Not Configured' (selected), 'Enabled', and 'Disabled'. To the right of these buttons is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' text box. The 'Options:' section on the left contains four text boxes for specifying logo paths: 'Logo version', 'Path to small-size (407x85 pixels) logo (*.bmp):', 'Path to medium-size (452x85 pixels) logo (*.bmp):', and 'Path to large-size (497x85 pixels) logo (*.bmp):'. The 'Help:' section on the right contains a scrollable text area with the following text: 'The policy determines the location of an alternative logo displayed by NetIQ Advanced Authentication Framework Workstation (GINA). To make NetIQ Advanced Authentication Framework Workstation display an alternative logo correctly, you should specify the location of this logo in the network or on the local computer. There should be three different-sized logos, prepared according to the following requirements: small-size logo: 407x85 pixels medium-size logo: 452x85 pixels large-size logo: 497x85 pixels In case the policy is not configured or disabled, an alternative logo is not displayed. Note: To optimize the traffic, NetIQ Advanced Authentication'. At the bottom of the dialog are 'OK', 'Cancel', and 'Apply' buttons.

To display an alternative logo in NetIQ Advanced Authentication Framework Client windows correctly, it is necessary to specify the location of this logo in the network or on the local computer.

To access the **Alternative Logo for GINA and Wizard** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Auththasas Advanced Authentication - > Workstation**.

Registry settings:

HKEY_ LOCAL_ MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\Brand

LargeLogo:

- value type: REG_SZ
- value data: \\netiq\logos\cplogolarge.bmp
- description: \\netiq\logos\cplogolarge.bmp displays the path to large-size logo

LogoVersion:


- value type: REG_SZ
- value data: 1
- description: 1 specifies the configured logo version


MediumLogo:

- value type: REG_SZ
- value data: \\netiq\logos\cplogomedium.bmp
- description: \\netiq\logos\cplogomedium.bmp displays the path to medium-size logo

SmallLogo:


- value type: REG_SZ
- value data: \\netiq\logos\cplogosmall.bmp
- description: \\netiq\logos\cplogosmall.bmp displays the path to small-size logo

 Shared folders you use must be accessible (read-only) for **Domain Computers** group. Other access configurations are optional.

 To specify the path to the logo file, you should use the server name, NOT its IP-address.

There must be three logos of different sizes corresponding to the following parameters:


- small-size logo: 406x85 pixels;
- medium-size logo: 451x85 pixels;
- large-size logo: 495x85 pixels.

 To optimize the traffic, NetIQ Advanced Authentication Framework Client loads an alternative logo from the specified location only once assuming the Logo version or path has been changed.

 If the policy is not defined or is disabled, an alternative logo is not displayed.

Deny to Specify Authenticator Comment at Enrollment

The **Deny to specify authenticator comment at enrollment** policy defines whether an NetIQ Advanced Authentication Framework user is allowed to add a comment at authenticator enrollment or not.





To access the **Deny to specify authenticator comment at enrollment** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
DenyAuthenticatorComment:


- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 If the policy is enabled, adding comments at authenticator enrollment is not allowed.

 If the policy is not defined or is disabled, adding comments at authenticator enrollment is allowed.

Deny to Start Client Tray When User Logs on to Windows

The **Deny to start Client Tray when user logs on to Windows** policy allows you to define whether NetIQ Advanced Authentication Framework Client Tray is started automatically at Windows logon or manually.



Deny to start Client Tray when user logs on to Windows

Previous Setting Next Setting

Not Configured Comment:

Enabled

Disabled

Supported on:

Options:

Help:

The policy determines NetIQ Advanced Authentication Framework Settings Tray behaviour.

In case the policy is enabled, NetIQ Advanced Authentication Framework Settings Tray is not launched when NetIQ Advanced Authentication Framework users log on to Windows.

In case the policy is not configured or disabled, NetIQ Advanced Authentication Framework Settings Tray is launched when NetIQ Advanced Authentication Framework users log on to Windows (unless the "Launch at startup" option has been disabled).

OK Cancel Apply


To access the **Deny to start Client Tray when user logs on to Windows** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.


Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

DenyClientTrayAutoStart:


- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 If the policy is enabled, NetIQ Advanced Authentication Framework Client Tray is started manually through **Start > Programs > NetIQ Advanced Authentication Framework > NetIQ Advanced Authentication Framework Settings Tray**.

 If the policy is not defined or is disabled, NetIQ Advanced Authentication Framework Client Tray is started automatically when a user logs on to Windows.

Disable First Logon Enroll Wizard

The **Disable first logon enroll wizard** policy allows to disable the NetIQ first logon wizard autostart. This application appears automatically after the NetIQ user without enrolled authenticators has been logged on.



Please enable the policy if you want to disable first logon wizard autostart. The first logon wizard is enabled by default.

To access the **Disable first logon enroll wizard** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

DisableFirstLogonEnrollWizard:


- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Disable "Use Dial-up Connection" Option

The **Disable "Use Dial-up connection" option** policy allows you to manage the **Use Dial-up connection option** in the **Logon** window.

The policy provides you with the following options:

- a. disable the **Use Dial-up connection option**;
- b. let users select the option if they wish to.



If the policy is enabled, the **Use Dial-up connection option** is always disabled and cannot be selected by users.

To access the **Disable "Use Dial-up connection" option** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration** - >

Policies - > Administrative Templates - > Authasas Advanced Authentication - > Workstation.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

GinaDisableDialUp:


- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled



If the policy is not configured or is disabled, the dial-up connection can be set up at logon. The **Use Dial-up connection option** in the **Logon** window can be selected by users.

Do Not Allow to Skip Welcome Window

The **Do not allow to skip Welcome window** policy, if enabled, doesn't allow users to skip the **Welcome to NetIQ Advanced Authentication Framework System** at the first logon without enrolling at least one authenticator.



To access the **Do not allow to skip Welcome window** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > Authasas Advanced Authentication - > Workstation**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

ShowFirstLogonWizardAlways:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled




If the policy is enabled, the **Welcome to NetIQ Advanced Authentication Framework System** window will be shown every time a user logs on to Windows until he/she enrolls his/her first authenticator.

 If the policy is not defined or is disabled, a user can skip the **Welcome to NetIQ Advanced Authentication Framework System** window at the first logon and the window will not be shown again.

Enable Device Detection for All

The **Enable device detection for all** policy, if enabled, allows to perform a device detection when logged in with card or flash drive (not only when logged in with the same card or flash drive, but also when logged in with another card or flash drive, other method of authentication or domain password). *For example*, when using autologon feature and using cards to logon to applications.



The screenshot shows a Windows-style dialog box titled "Enable device detection for all". At the top right are "Previous Setting" and "Next Setting" buttons. On the left, there are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these is a "Comment:" text box. Below the radio buttons is a "Supported on:" dropdown menu. At the bottom left is an "Options:" section with an empty text area. At the bottom right is a "Help:" section with a text area containing the text: "When this policy is enabled device detection will work when logged in without device. For example when using autologon feature and using cards to logon to applications". At the very bottom are "OK", "Cancel", and "Apply" buttons.

To access the **Enable device detection for all** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

IsDeviceDetectionForAllEnabled:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled



The **Enable device detection for all** policy is supported only by card and flash drive authentication providers.

Enhanced Reaction on Device Events

The **Enhanced reaction on device events** policy allows custom actions during device in and out events. For example, on a thin client the system administrator can configure the plugged out events as follows to disconnect the Citrix session "{PATH}\pnagent.exe / disconnect".

The **Enhanced reaction on device events** policy works when **NetIQ Client** or **NetIQ RTE** is installed. The policy works only when the user was logged on by the device.

The screenshot shows a Windows-style dialog box titled "Enhanced reaction on device events". At the top, there are "Previous Setting" and "Next Setting" buttons. Below these are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of these is a "Comment:" text box. Below the radio buttons is a "Supported on:" dropdown menu. Underneath, there are two sections: "Options:" and "Help:". The "Options:" section contains two text input fields: "Command line for plugged in event" and "Command line for plugged out event". The "Help:" section contains a text area with the following text: "When configured this GPO allows for custom actions on device in and out events. For example: On a thin client you can configure the plugged out event as follows to disconnect the Citrix session \"{PATH}\pnagent.exe / disconnect\"." At the bottom right of the dialog are "OK", "Cancel", and "Apply" buttons.

In the **Command line for plugged out event** line, you should write the command that will be performed when the device is being plugged out.

To access the **Enhanced reaction on device events** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework


PluggedInCommand:


- value type: REG_SZ
- value data: cmd /c C:\!\OnStart.cmd
- description: cmd /c C:\!\OnStart.cmd displays the command line for plugged in event


PluggedOutCommand:


- value type: REG_SZ
- value data: cmd /c C:\!\OnEnd.cmd
- description: cmd /c C:\!\OnEnd.cmd displays the command line for plugged out event

 The **Enhanced reaction on device events** policy is supported only by card and flash drive authentication providers.

 If the policy is not configured or is disabled, no action is set for device plug in and out event.


 If the **Enable device detection for all** policy is enabled, then the **Enhanced reaction on device events** policy works also when the user was logged on by password or by other device.

 The **Enhanced reaction on device events** policy for plugged-out events may conflict with **Interactive logon: Smart card removal behavior** system policy.

 Environment variables are not supported.

Last Used Server Timeout

The **Last used server timeout** policy allows you to specify time (in hours) during which a last used Authenticore Server will be always used on Client. After the specified time, [search for another Authenticore Server](#) will be started.



To access the **Last used server timeout** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

LastUsedServerTimeout:

- value type: REG_DWORD
- value data: 0x00000008 (8)
- description: 8 displays time during which the last Authenticore Server can be used (in hours)

Lifetime of Notification about Password Reset

The **Lifetime of notification about password reset** policy allows the administrator to setup lifetime of user's notification about user's password reset by administrator.

The screenshot shows a Windows-style dialog box titled "Lifetime of notification about password reset". At the top, there are "Previous Setting" and "Next Setting" buttons. Below these are three radio buttons: "Not Configured", "Enabled" (which is selected), and "Disabled". To the right of the radio buttons is a "Comment:" text box. Below the radio buttons is a "Supported on:" dropdown menu. In the "Options:" section, there is a label "Lifetime of notification about password reset (in days):" followed by a spin box containing the number "14". To the right of the spin box is a "Help:" section with a text area containing the text: "The policy allows the administrator to setup lifetime of user's notification about user's password reset by administrator." At the bottom of the dialog box are "OK", "Cancel", and "Apply" buttons.

To access the **Lifetime of notification about password reset** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration** - > **Policies** - > **Administrative Templates** - > **Authasas Advanced Authentication** - > **Workstation**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework
ResetPasswordNotificationLifeTime:

- value type: REG_DWORD
- value data: 0x0000000e (14)
- description: 14 displays lifetime of notification about password reset (in days)

Linked Logon Behavior

The **Linked logon behavior** policy determines the behavior of a linked logon. The following options are possible:

- Only do linked logon, when the **Next** button is pressed (default). If this option is selected, the system will only try to do a linked logon when a username is entered and the **Next** button is pressed. When pressing a card at any other moment, it will do a normal logon.
- When username is entered, do a linked account logon and if account is not linked, do a normal logon. With this option the system will first try to do a linked logon with the username that is entered and if this fails, it will do a normal logon.
- When username is entered, do a linked logon account logon and if account is not linked fail. With this option the system will first try to do a linked logon with the username that is entered and if this fails, it will fail the authentication. Normal logon is only possible when the username field is empty or the username that belongs to the device is entered.



To access the **Linked logon behavior** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates -> Authasas Advanced Authentication -> Workstation.**

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

LinkedLogonBehavior:


- value type: REG_DWORD
- value data: 0x00000000 (0)
- description: 0 means that the policy is enabled

Master Server

The **Master server** policy allows you to specify the list of Master servers to which the Client will connect if there are no Authenticore Servers in the same AD site with the Client or they are not available.

The search for Authenticore Server is performed in the following way:


1. Client goes to the last Authenticore Server, if:
 - Client is in the same AD site as the Authenticore Server
 - Client has authenticated not less than 8 hours ago (it is configured using the [Last used server timeout](#) policy)
2. Otherwise Client connects to the random Authenticore Server from its AD site.
3. If there are no Authenticore Servers in the Client's AD Site or they are not available, Client goes to the Authenticore Server from the Master server list (if the **Master server** is enabled and Authenticore Servers are added to the **Master server list**). Master servers can be used no matter in which AD site they are located.
4. If Master servers are not available, Client goes to other servers outside its AD site (if the **Forbid the client to go outside its AD site checkbox** is not selected).

 It is recommended to configure the policy only for the AD sites with the installed NetIQ Client, but without available Authenticore Servers. Otherwise the Client will try to connect to the random Authenticore Server which can be located geographically far from the Client (in another country, on another continent). It may cause long authentication delay.


The **Forbid the client to go outside its AD site** checkbox can be selected when Master servers are not specified in the policy or are not available:


- If the checkbox is selected, the Client will not try to connect to any other random server.
- If the checkbox is cleared, the Client will go to a random server.

This option can prevent the delays when there is no cache and no connection to any server.



To add an applicable Master server, click the **Show** button. Specify its name and click **OK** to save changes.



 It is required to specify the DNS name of an applicable server, not its IP address.

To access the **Master server** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation.**

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

MasterServers:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework\MasterServerList

1:


- value type: REG_SZ
- value data: name.domain.local
- description: name.domain.local displays the name of the first Master server on the list

2:

- value type: REG_SZ
- value data: name2.domain.local
- description: name.domain.local displays the name of the second Master server on the list

Tap and Go

The **Tap and Go** policy allows the user just to tap the card on the reader and provide the PIN instead of leaving the card on the reader. When tapping the card for the second time, the action configured in the "Interactive Logon Smart card removal behavior" group policy object will be used.



To access the **Tap and Go** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> Authasas Advanced Authentication -> Workstation.**


Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

TapAndGo:

- value type: REG_DWORD
- value data: 0x00000001 (1)

- description: 1 means that the policy is enabled


 If the policy is not configured or is disabled, user cannot take the card from the reader until the Logon process is finished.

"Use Current Settings as Defaults" Option Management for PC Unlocking

The "**Use current settings as defaults**" option management for PC unlocking policy allows you to manage the **Use current settings as defaults** option in the **Unlock Computer** window.

The policy provides you with the following options:

- force current logon settings as defaults regardless of users' wishes;
- disable the **Use current settings as defaults** option regardless of users' wishes;
- let users set the current logon settings as defaults if they wish to.



If the policy is enabled, the **Use current settings as defaults** option is always enabled and cannot be canceled by users.

To access the "**Use current settings as defaults**" option management for PC unlocking policy in the **Group Policy Management Editor** console, expand the following path:

Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Workstation.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

GinaCurrentAsDefaultUnlock:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

 If the policy is disabled, the **Use current settings as defaults** option is always disabled and cannot be selected by users.


 If the policy is not configured, the **Use current settings as defaults** option is enabled and can be selected or canceled by users.

“Use Current Settings as Defaults” Option Management

The “**Use current settings as defaults**” option management policy allows you to manage the **Use current settings as defaults** option in the **Logon** window.

The policy provides you with the following options:

- force current logon settings as defaults regardless of users’ wishes
- disable the **Use current settings as defaults** option regardless of users’ wishes
- let users set the current logon settings as defaults if they wish to



To access the “**Use current settings as defaults**” option management policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

GinaCurrentAsDefault:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

If the policy is enabled, the **Use current settings as defaults** option is always enabled and cannot be canceled by users.


 If the policy is disabled, the **Use current settings as defaults** option is always disabled and cannot be selected by users.

 If the policy is not configured, the **Use current settings as defaults** option is enabled and can be selected or canceled by users.

Web Service Client Timeouts

The **Web service client timeouts** policy allows you to set the timeout value for Web Service(s).

The screenshot shows the 'Web service client timeouts' dialog box. It has a title bar with the text 'Web service client timeouts' and standard window controls. Below the title bar, there are two buttons: 'Previous Setting' and 'Next Setting'. The main area contains three radio buttons: 'Not Configured', 'Enabled' (which is selected), and 'Disabled'. To the right of these is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' section with a list box. Underneath, there are two sections: 'Options:' and 'Help:'. The 'Options:' section contains two spinners: 'Web service client timeout:' set to 60 and 'Web service client connection timeout:' set to 5. The 'Help:' section contains a large empty text box. At the bottom right, there are three buttons: 'OK', 'Cancel', and 'Apply'.

 It is recommended to install Web Service on every Authenticore Server. If several Web Services are installed, the timeout should be set on the basis of 30 seconds of timeout per Web Service (it means that 90 seconds of timeout should be set for 3 Web Services) but not less than 60 seconds.

To access the **Web service client timeouts** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Workstation**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

WebServiceClientConnectionTimeout:

- value type: REG_DWORD
- value data: 0x00000005 (5)
- description: 5 displays duration of connection timeout to one Web Service (in seconds). If Web Service does not respond within 5 seconds, connection to another Web Service in the queue will be established.

WebServiceClientTimeout:

- value type: REG_DWORD
- value data: 0x0000003c (60)
- description: 60 displays duration of general connection timeout to Web Service(s) (in seconds).

Repository Policies

The **Repository** section includes policies that allow you not to extend Active Directory Scheme.

It includes:

- [ADAM settings](#)
- [Enable Novell support](#)
- [Repository](#)

ADAM Settings

The **ADAM settings** policy allows you to configure if ADAM/AD-LDS is used as repository.

The screenshot shows the 'ADAM Settings' dialog box. It features a title bar with the text 'ADAM Settings' and standard window controls. Below the title bar, there are two buttons: 'Previous Setting' and 'Next Setting'. The main area contains three radio buttons: 'Not Configured', 'Enabled' (which is selected), and 'Disabled'. To the right of these radio buttons is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' dropdown menu. The 'Options:' section is divided into two panes. The left pane contains two fields: 'LDAP path to root element' with the value 'CN=NAAF' and 'ADAM servers port number' with a spinner box set to '50000'. The right pane is titled 'Help:' and contains the text 'Configure if ADAM / AD-LDS is used as repository.'. At the bottom of the dialog are three buttons: 'OK', 'Cancel', and 'Apply'.

To access the **ADAM Settings** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Repository**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\NetIQ\NetIQ Advanced Authentication Framework

Port:

- value type: REG_DWORD
- value data: 0x0000c350 (50000)
- description: 50000 displays ADAM server port number

RootPath:

- value type: REG_SZ
- value data: CN=NAAF
- description: CN=NAAF is a LDAP path to root element

Enable Novell Support

The **Enable Novell Support** policy allows you to activate the support mode of Novell Domain Services for Windows for the case if you are using Active Directory Lightweight Directory Services for NetIQ data storage in domain based on Novell eDirectory.

After applying the policy the domain root binds to the NetIQ settings.

If you decide not to apply this policy, the NetIQ will not work properly, - you will have a problem with 1-N authentication.

To access the **Enable Novell Support** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates -> NetIQ Advanced Authentication Framework -> Repository**.

Registry settings:


HKEY_LOCAL_MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication Framework\Repository

NovellSupportEnabled:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Repository

The **Repository** policy allows you to choose whether to use native Active Directory or ADAM/AD-LDS as NetIQ repository.



The screenshot shows the 'Repository' configuration dialog box. It has a title bar with 'Repository' and standard window controls. Below the title bar, there are two buttons: 'Previous Setting' and 'Next Setting'. The main area contains three radio buttons: 'Not Configured', 'Enabled' (which is selected), and 'Disabled'. To the right of these is a 'Comment:' text box. Below the radio buttons is a 'Supported on:' text box. Underneath, there are two sections: 'Options:' and 'Help:'. The 'Options:' section contains a 'Repository Type' dropdown menu with 'ADAM instance' selected. The 'Help:' section contains a text box with the following text: 'Choose to use native Active Directory or ADAM / AD-LDS as the NetIQ repository. When Native Directory is used and the schema is not extended please configure the AD Settings GPO (AAA_REPOSITORY_AD.adm). If ADAM is chosen make sure the ADAM Settings GPO (AAA_REPOSITORY_ADAM.adm) is also configured.' At the bottom of the dialog are three buttons: 'OK', 'Cancel', and 'Apply'.

When **Native Directory** is used and the schema is not extended please configure the AD Settings GPO (**NAAM_REPOSITORY_AD.admx**).

If **ADAM** is chosen, make sure the ADAM Settings GPO (**NAAF_REPOSITORY_ADAM.admx**) is also configured.

To access the **Repository** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration -> Policies -> Administrative Templates -> NetIQ Advanced Authentication Framework -> Repository**.

Registry settings:

HKEY_LOCAL_MACHINE\SOFTWARE\Policies\ NetIQ \ NetIQ Advanced Authentication
Framework\Repository

Type:

- value type: REG_DWORD
- value data: 0x00000002 (2)
- description: 2 means that ADAM instance is chosen

UI Look & Feel Policies


The **UI Look & Feel** section includes policies designed for terminal clients. The **UI Look & Feel** section is located in **Group Policy Management Editor** under **User Configuration -> Policies -> Administrative Templates: Policy definitions -> NetIQ Advanced Authentication Framework**.

It includes:

- [Show cache messages](#)
- [Show OSD](#)

Show Cache Messages

When the **Show cache messages** policy is disabled, the message on a workstation that caching is enabled or disabled will not be shown.



By default this policy is enabled.

To access the **Show cache messages** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > NetIQ Advanced Authentication Framework - > UI Look & Feel**.

Registry settings:


HKEY_CURRENT_USER\Software\Policies\NetIQ\NetIQ Advanced Authentication

ShowCacheMessages:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Show OSD Num Pad

When enabled this policy provides an **On Screen Keyboard** option during logging on. It is designed for keyboard-less terminals.



To access the **Show OSD Num pad** policy in the **Group Policy Management Editor** console, expand the following path: **Computer Configuration - > Policies - > Administrative Templates - > NetIQ Advanced Authentication Framework - > UI Look & Feel**.

Registry settings:

HKEY_CURRENT_USER\Software\Policies\NetIQ\NetIQ Advanced Authentication Framework

OSDNumPadEnabled:

- value type: REG_DWORD
- value data: 0x00000001 (1)
- description: 1 means that the policy is enabled

Index

A

Account 27, 31
Active Directory 7, 88, 92
Administrator 1
Authentication 1, 4-5, 10, 12-13, 15, 17, 19, 21, 24, 26-27, 29-30, 32, 34, 38-39, 41-42, 44-46, 48, 50, 52, 54, 58-59, 61-62, 64-66, 69-70, 72-73, 76, 79-80, 83-84, 86, 89, 91-92, 94-95, 97
Authenticator 4-5, 9-10, 61
Authenticore server 10

C

Caching 16, 21
Card 32, 51
Client 5, 21, 23, 25, 49-50, 58-59, 70-71, 77, 86
Client Tray 6, 56, 62
Connection 65
Credential providers 5, 9, 11

D

Default 5, 9, 13
Device 68, 70
Dial-up 6, 56, 65
Domain 7, 34, 40, 60, 91

E

Event Log 5, 36, 39

G

Generate 5, 17
GINA 6, 56, 59

L

List 15, 25
Logo 6, 56-57, 59
Logon 4, 6, 63, 65, 75, 81, 84

M

Microsoft Windows Server 2008 8

N

Network 6, 43
Notification 73

P

Password 5, 9, 17, 23, 25, 30, 40
PIN 5, 9, 15, 23, 32, 34, 43, 80
Policy 1, 4, 10, 12-13, 15, 17, 19, 21, 24, 26-27, 29-30, 32, 34, 38-39, 41-42, 44-46, 48, 50, 52, 54, 58, 60-61, 63-65, 67, 69-70, 72-73, 76, 79-80, 82, 84, 86, 89, 91-92, 94-95, 97

R

Remote 12
Remove 19
RTE 52, 70

S

Screen 7, 97
Security 5, 8-9, 12-13
Server 7, 37, 43, 48-49, 53, 71, 76, 86
Settings 11, 53, 63, 82, 84, 89, 92
Software 95, 97
Support 91
System 66

U

User 42, 94

W

Window 66
Windows 6, 8, 11, 55, 59, 62, 67
Windows Vista 57
Workstation 6, 56, 60-61, 63, 67, 83-84, 86