



# PlateSpin® Protect 11.1

## Installation and Upgrade Guide

July 2015

## Legal Notice

THIS DOCUMENT AND THE SOFTWARE DESCRIBED IN THIS DOCUMENT ARE FURNISHED UNDER AND ARE SUBJECT TO THE TERMS OF A LICENSE AGREEMENT OR A NON-DISCLOSURE AGREEMENT. EXCEPT AS EXPRESSLY SET FORTH IN SUCH LICENSE AGREEMENT OR NON-DISCLOSURE AGREEMENT, NETIQ CORPORATION PROVIDES THIS DOCUMENT AND THE SOFTWARE DESCRIBED IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. SOME STATES DO NOT ALLOW DISCLAIMERS OF EXPRESS OR IMPLIED WARRANTIES IN CERTAIN TRANSACTIONS; THEREFORE, THIS STATEMENT MAY NOT APPLY TO YOU.

For purposes of clarity, any module, adapter or other similar material ("Module") is licensed under the terms and conditions of the End User License Agreement for the applicable version of the NetIQ product or software to which it relates or interoperates with, and by accessing, copying or using a Module you agree to be bound by such terms. If you do not agree to the terms of the End User License Agreement you are not authorized to use, access or copy a Module and you must destroy all copies of the Module and contact NetIQ for further instructions.

This document and the software described in this document may not be lent, sold, or given away without the prior written permission of NetIQ Corporation, except as otherwise permitted by law. Except as expressly set forth in such license agreement or non-disclosure agreement, no part of this document or the software described in this document may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, or otherwise, without the prior written consent of NetIQ Corporation. Some companies, names, and data in this document are used for illustration purposes and may not represent real companies, individuals, or data.

This document could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein. These changes may be incorporated in new editions of this document. NetIQ Corporation may make improvements in or changes to the software described in this document at any time.

U.S. Government Restricted Rights: If the software and documentation are being acquired by or on behalf of the U.S. Government or by a U.S. Government prime contractor or subcontractor (at any tier), in accordance with 48 C.F.R. 227.7202-4 (for Department of Defense (DOD) acquisitions) and 48 C.F.R. 2.101 and 12.212 (for non-DOD acquisitions), the government's rights in the software and documentation, including its rights to use, modify, reproduce, release, perform, display or disclose the software or documentation, will be subject in all respects to the commercial license rights and restrictions provided in the license agreement.

**© 2015 NetIQ Corporation. All Rights Reserved.**

For information about NetIQ trademarks, see <https://www.netiq.com/company/legal/>.

### License Grant

Licenses purchased for PlateSpin Protect 11 and later versions cannot be used for PlateSpin Protect 10.3 or prior versions.

### Third-Party Software

Please refer to the *PlateSpin Third-Party License Usage and Copyright* ([https://www.netiq.com/documentation/platespin\\_licensing/platespin\\_licensing\\_qs/data/platespin\\_licensing\\_qs.html](https://www.netiq.com/documentation/platespin_licensing/platespin_licensing_qs/data/platespin_licensing_qs.html)) page for information about third party software used in PlateSpin Protect.

---

# Contents

<b>About This Guide and the Library</b>	<b>5</b>
<b>About NetIQ Corporation</b>	<b>7</b>
<b>1 Installing PlateSpin Protect</b>	<b>9</b>
1.1 Preparing to Install PlateSpin Protect . . . . .	9
1.1.1 System Requirements . . . . .	9
1.1.2 General Guidelines . . . . .	11
1.2 Installing Prerequisite Software . . . . .	12
1.2.1 Installing Prerequisite Software on Windows Server 2012 R2 Systems . . . . .	12
1.2.2 Installing Prerequisite Software on Windows Server 2008 R2 Systems . . . . .	14
1.3 Installing PlateSpin Protect Software Components . . . . .	16
1.3.1 Starting the PlateSpin Protect Installation Launcher . . . . .	16
1.3.2 Installing the Database Server . . . . .	16
1.3.3 Installing the PlateSpin Server . . . . .	18
1.3.4 Post-Installation Tasks . . . . .	19
<b>2 Upgrading PlateSpin Protect</b>	<b>21</b>
2.1 Before Upgrading PlateSpin Protect . . . . .	21
2.1.1 Backing Up Your Database Files . . . . .	21
2.2 Upgrade Procedure . . . . .	22
2.2.1 Upgrade Procedure . . . . .	22
2.2.2 Post-Upgrade Tasks . . . . .	22
<b>A Documentation Updates</b>	<b>25</b>
A.1 July 2015 . . . . .	25
A.2 June 2015 . . . . .	25
A.3 May 2015 . . . . .	25
A.4 April 2015 . . . . .	26



---

# About This Guide and the Library

The *Installation and Upgrade Guide* provides detailed planning and installation information for the PlateSpin Protect software, as well as upgrade information.

## Intended Audience

This document is intended for IT staff, such as data center administrators and operators, who use PlateSpin Protect in their ongoing workload protection projects.

## Information in the Library

The library for this product is available in HTML and PDF formats on the [PlateSpin Protect Documentation](https://www.netiq.com/documentation/platespin-protect/) (<https://www.netiq.com/documentation/platespin-protect/>) website. In addition to the English language, online documentation is available in the Chinese Simplified, Chinese Traditional, French, German, Japanese, and Spanish languages.

The PlateSpin Protect library provides the following information resources:

### Release Notes

Provides information about new features and enhancements in the release, as well as any known issues.

### Installation and Upgrade Guide

Provides detailed planning and installation information for the software, as well as upgrade information.

### User Guide

Provides conceptual information, an overview of the user interface, and step-by-step guidance for common tasks.

### Help

Provides context-sensitive information and step-by-step guidance for common tasks as you work in the user interface.

## Additional Resources

We encourage you to use the following additional resources online:

- ♦ [PlateSpin Protect Forum](https://forums.netiq.com/forumdisplay.php?59-Platespin-Protect) (<https://forums.netiq.com/forumdisplay.php?59-Platespin-Protect>): A web-based community of product users where you can discuss product functionality and advice with other product users.
- ♦ [PlateSpin Protect Product page](https://www.netiq.com/products/protect/) (<https://www.netiq.com/products/protect/>): A web-based product brochure that provides information about features, how to buy, technical specifications, frequently asked questions, and a variety of resources such as videos and white papers.

- ♦ [NetIQ User Community \(https://www.netiq.com/communities/\)](https://www.netiq.com/communities/): A web-based community with a variety of discussion topics.
- ♦ [NetIQ Support Knowledgebase \(https://www.netiq.com/support/kb/\)](https://www.netiq.com/support/kb/): A collection of in-depth technical articles.
- ♦ [NetIQ Support Forums \(https://forums.netiq.com/forum.php\)](https://forums.netiq.com/forum.php): A web location where product users can discuss NetIQ product functionality and advice with other product users.
- ♦ [MyNetIQ \(https://www.netiq.com/f/mynetiq/\)](https://www.netiq.com/f/mynetiq/): A website offering product information and services, such as access to premium white papers, webcast registrations, and product trial downloads.

---

# About NetIQ Corporation

We are a global, enterprise software company, with a focus on the three persistent challenges in your environment: Change, complexity and risk—and how we can help you control them.

## Our Viewpoint

### **Adapting to change and managing complexity and risk are nothing new**

In fact, of all the challenges you face, these are perhaps the most prominent variables that deny you the control you need to securely measure, monitor, and manage your physical, virtual, and cloud computing environments.

### **Enabling critical business services, better and faster**

We believe that providing as much control as possible to IT organizations is the only way to enable timelier and cost effective delivery of services. Persistent pressures like change and complexity will only continue to increase as organizations continue to change and the technologies needed to manage them become inherently more complex.

## Our Philosophy

### **Selling intelligent solutions, not just software**

In order to provide reliable control, we first make sure we understand the real-world scenarios in which IT organizations like yours operate—day in and day out. That's the only way we can develop practical, intelligent IT solutions that successfully yield proven, measurable results. And that's so much more rewarding than simply selling software.

### **Driving your success is our passion**

We place your success at the heart of how we do business. From product inception to deployment, we understand that you need IT solutions that work well and integrate seamlessly with your existing investments; you need ongoing support and training post-deployment; and you need someone that is truly easy to work with—for a change. Ultimately, when you succeed, we all succeed.

## Our Solutions

- ♦ Identity & Access Governance
- ♦ Access Management
- ♦ Security Management
- ♦ Systems & Application Management
- ♦ Workload Management
- ♦ Service Management

## Contacting Sales Support

For questions about products, pricing, and capabilities, contact your local partner. If you cannot contact your partner, contact our Sales Support team.

<b>Worldwide:</b>	<a href="http://www.netiq.com/about_netiq/officelocations.asp">www.netiq.com/about_netiq/officelocations.asp</a>
<b>United States and Canada:</b>	1-888-323-6768
<b>Email:</b>	<a href="mailto:info@netiq.com">info@netiq.com</a>
<b>Website:</b>	<a href="http://www.netiq.com">www.netiq.com</a>

## Contacting Technical Support

For specific product issues, please contact our Technical Support team.

<b>Worldwide:</b>	<a href="http://www.netiq.com/support/contactinfo.asp">www.netiq.com/support/contactinfo.asp</a>
<b>North and South America:</b>	1-713-418-5555
<b>Europe, Middle East, and Africa:</b>	+353 (0) 91-782 677
<b>Email:</b>	<a href="mailto:support@netiq.com">support@netiq.com</a>
<b>Website:</b>	<a href="http://www.netiq.com/support">www.netiq.com/support</a>

To learn more about the services and procedures of NetIQ Technical Support, see the [Technical Support Guide](https://www.netiq.com/Support/process.asp#_Maintenance_Programs_and) ([https://www.netiq.com/Support/process.asp#\\_Maintenance\\_Programs\\_and](https://www.netiq.com/Support/process.asp#_Maintenance_Programs_and)).

## Contacting Documentation Support

Our goal is to provide documentation that meets your needs. The documentation for this product is available on the [PlateSpin Protect Documentation](https://www.netiq.com/documentation/platespin-protect/) (<https://www.netiq.com/documentation/platespin-protect/>) website in HTML and PDF formats.

If you have suggestions for documentation improvements, click **comment on this topic** at the bottom of any page in the HTML version of the documentation. You can also email [Documentation-Feedback@netiq.com](mailto:Documentation-Feedback@netiq.com). We value your input and look forward to hearing from you.

## Contacting the Online User Community

NetIQ Communities, the NetIQ online community, is a collaborative network connecting you to your peers and NetIQ experts. By providing more immediate information, useful links to helpful resources, and access to NetIQ experts, NetIQ Communities helps ensure you are mastering the knowledge you need to realize the full potential of IT investments upon which you rely. For more information, visit <http://community.netiq.com>.



---

# 1 Installing PlateSpin Protect

PlateSpin Protect is a Windows application that runs on server operating systems. Its functionality depends on several software components, including the Microsoft Internet Information Services (IIS) web server software along with its feature extension modules, the ASP.NET web application framework, the Microsoft .NET Framework library and runtime, as well as a dedicated Microsoft SQL Server database instance.

- ♦ [Section 1.1, “Preparing to Install PlateSpin Protect,” on page 9](#)
- ♦ [Section 1.2, “Installing Prerequisite Software,” on page 12](#)
- ♦ [Section 1.3, “Installing PlateSpin Protect Software Components,” on page 16](#)

## 1.1 Preparing to Install PlateSpin Protect

For trouble-free installation and operation of PlateSpin Protect, you should familiarize with system requirements and take time to plan your installation.

- ♦ [Section 1.1.1, “System Requirements,” on page 9](#)
- ♦ [Section 1.1.2, “General Guidelines,” on page 11](#)

### 1.1.1 System Requirements

PlateSpin Server hosts must meet the system requirements in [Table 1-1](#):

*Table 1-1 PlateSpin Server Host Requirements*

Requirement	Details
Operating System	<p>For new installations, PlateSpin Protect supports any of the following operating systems, running on dedicated hardware or in a virtual machine:</p> <ul style="list-style-type: none"><li>♦ Windows Server 2012 R2 (64-bit)</li><li>♦ Windows Server 2008 R2 (64-bit)</li></ul> <p><b>NOTE:</b> You must activate your Windows operating system prior to installing PlateSpin Protect.</p>
Processor	<p>Minimum 1 GHz</p> <p>Recommended: multi-core, 2 GHz or higher</p>
Memory (RAM)	Minimum 4 GB
Disk Space	<p>Minimum 15 GB</p> <p><b>NOTE:</b> Over time, space consumption will increase.</p>

Requirement	Details
Database Server	<p>A dedicated Microsoft SQL Server database instance, running one of the following supported versions of SQL Server:</p> <ul style="list-style-type: none"> <li>♦ <b>New database server:</b> Microsoft SQL Server 2014 Express Edition database server is included in your PlateSpin Protect software distribution.</li> </ul> <p>You can install this software during the PlateSpin Protect installation on the same server, or you can install this software separately on a different server before you install the product. For more information, see <a href="#">"Installing Microsoft SQL Server Express Edition" on page 16</a>.</p> <ul style="list-style-type: none"> <li>♦ <b>Your existing database server:</b> You can use your existing (that is, already installed) Microsoft SQL Server database server to host the database instance. Your existing database server resides on a different server than the PlateSpin Server.</li> </ul> <p>Supported software versions are:</p> <ul style="list-style-type: none"> <li>♦ Microsoft SQL Server 2014</li> <li>♦ Microsoft SQL Server 2012 Service Pack 2</li> <li>♦ Microsoft SQL Server 2008 R2 Service Pack 2</li> <li>♦ Microsoft SQL Server 2008 Service Pack 3</li> <li>♦ Microsoft SQL Server 2005 Service Pack 4</li> </ul> <p><b>NOTE:</b> Prior to installing the product, ensure that your existing SQL Server database server and named database instance meet the <a href="#">Database guidelines</a>. For configuration information, see <a href="#">"Configuring Your Remote Microsoft SQL Server Database Server" on page 17</a>.</p>
Software Prerequisites	<p>You must install the following components on the Windows server where you will install PlateSpin Protect:</p> <ul style="list-style-type: none"> <li>♦ <b>For Windows Server 2012 R2 systems:</b> <ul style="list-style-type: none"> <li>♦ Microsoft .NET Framework 3.5 Service Pack 1</li> <li>♦ Microsoft .NET Framework 4.0</li> <li>♦ Web Server (IIS 8.0), running in 32-bit mode</li> </ul> <p>For more information, see <a href="#">"Installing Prerequisite Software on Windows Server 2012 R2 Systems" on page 12</a>.</p> </li> <li>♦ <b>For Windows Server 2008 R2 systems:</b> <ul style="list-style-type: none"> <li>♦ Microsoft .NET Framework 3.5 Service Pack 1</li> <li>♦ Microsoft .NET Framework 4.0</li> <li>♦ Web Server (IIS 7.0), running in 32-bit mode</li> </ul> <p>For more information, see <a href="#">"Installing Prerequisite Software on Windows Server 2008 R2 Systems" on page 14</a>.</p> </li> </ul>
National Language Support	<p>In addition to the English language, PlateSpin Protect provides National Language Support (NLS) for installation and use on machines configured for the Chinese Simplified, Chinese Traditional, French, German, and Japanese languages.</p> <p>To use the PlateSpin Protect Web Interface and integrated help in one of these languages, see <a href="#">Configuring Language Settings for International Versions of PlateSpin Protect</a>. <a href="#">Localized online documentation</a> is available in these languages, as well as in Spanish.</p>

## 1.1.2 General Guidelines

Follow the installation guidelines in [Table 1-2](#) for trouble-free installation and operation of PlateSpin Protect.

**Table 1-2** *Pre-Installation Checklist*

Guideline	Remarks
<input type="checkbox"/> Dedicated Host	Install PlateSpin Protect on a dedicated physical machine or virtual machine. See also <a href="#">Colocation</a> .
<input type="checkbox"/> Credentials	Perform all installation procedures using an account with administrative privileges. Use the built-in Administrator account.
<input type="checkbox"/> IP Address	Assign a static IP address to the PlateSpin Server host.
<input type="checkbox"/> Colocation	Do not colocate the PlateSpin Server with: <ul style="list-style-type: none"><li>◆ Your domain controller</li><li>◆ Existing web servers with IIS applications</li><li>◆ A workload that you intend to protect by using the product</li><li>◆ Other PlateSpin software (PlateSpin Migrate and PlateSpin Recon)</li></ul>
<input type="checkbox"/> Database	<p>The <i>Microsoft SQL Server 2014 Express Edition</i> that is included with PlateSpin Protect Server cannot be installed on a domain controller, in accordance with <a href="#">Microsoft Developer Network recommendations</a>.</p> <p>If you intend to use your existing Microsoft SQL Server database server (instead of the Microsoft SQL Server 2014 Express Edition included in your software distribution), ensure that your system uses a <a href="#">supported version of SQL Server</a>. During the PlateSpin Protect software installation, you need to know the server name and name of the database instance.</p> <p>For more information about SQL Server settings and the firewall settings required for using a remote database server, see <a href="#">Section 1.3.2, "Installing the Database Server," on page 16</a>.</p>
<input type="checkbox"/> UAC	Disable the User Account Control (UAC) during the installation, removal, or upgrade.
<input type="checkbox"/> Installation Workflow	<p>Install the prerequisite software in the indicated order. Below is a high-level workflow for a typical PlateSpin Protect installation:</p> <ol style="list-style-type: none"><li>1. Supported operating system, followed by corresponding Windows Updates.</li><li>2. ASP.NET/IIS, followed by corresponding Windows Updates.<ol style="list-style-type: none"><li>a. Configure IIS to run in 32-bit mode.</li></ol></li><li>3. SQL Server database, followed by applicable Microsoft updates.</li><li>4. PlateSpin Server.</li></ol>

## 1.2 Installing Prerequisite Software

This section provides information about installing the required ASP.NET, IIS, and .NET Framework software components. Because the packaging and distribution of these software components varies among different versions of the supported Windows Server platforms, procedures vary slightly. Use the indicated order of installation and setup.

- ♦ [Section 1.2.1, “Installing Prerequisite Software on Windows Server 2012 R2 Systems,” on page 12](#)
- ♦ [Section 1.2.2, “Installing Prerequisite Software on Windows Server 2008 R2 Systems,” on page 14](#)

### 1.2.1 Installing Prerequisite Software on Windows Server 2012 R2 Systems

The following procedure applies to Microsoft Windows Server 2012 R2 (64-bit) servers where you plan to install PlateSpin Protect.

**To install required Microsoft software components:**

- 1 Ensure that you are familiar with the [System Requirements](#) and [General Guidelines](#).
- 2 Use the Local User Administrator (LUA) account to log in to your intended PlateSpin Server host.
- 3 Use Server Manager to install the Web Server (IIS) role and its role services. Keep the default set of role services for the Web Server, and add the following required role services along with their sub-role services as shown. (Select **Start > All Programs > Administrative Tools > Server Manager**, select **Manage > Add Roles and Features**, then proceed through the wizard to **Select Server Roles** and **Select Role Services** for the Web Server.)

- ☐ Web Server (IIS) (25 of 43 installed)
  - ☐ Web Server (19 of 34 installed)
    - ☐ Common HTTP Features (4 of 6 installed)
      - ♦ Default Document
      - ♦ Directory Browsing
      - ♦ HTTP Errors
      - ♦ Static Content
    - ☐ Health and Diagnostics (2 of 6 installed)
      - ♦ HTTP Logging
      - ♦ Request Monitor
    - ☐ Performance (1 of 2 installed)
      - ♦ Static Content Compression
    - ☐ Security (5 of 9 installed)
      - ♦ Requesting Filtering
      - ♦ Basic Authentication
      - ♦ IP and Domain Restrictions
      - ♦ URL Authorization
      - ♦ Windows Authentication

- ☐ Application Development (7 of 11 installed)
    - ♦ .NET Extensibility 3.5
    - ♦ .NET Extensibility 4.5
    - ♦ Application Initialization
    - ♦ ASP.NET 3.5
    - ♦ ASP.NET 4.5
    - ♦ ISAPI Extensions
    - ♦ ISAPI Filters
  - ☐ Management Tools (6 of 7 installed)
    - ♦ IIS Management Console
    - ♦ IIS 6 Management Compatibility
      - IIS 6 Metabase Compatibility
      - IIS 6 Management Console
      - IIS 6 Scripting Tools
      - IIS 6 WMI Compatibility
    - ♦ IIS Management Scripts and Tools
- 4 Use Server Manager to install the following required features and sub-features as shown. (In **Server Manager**, select **Manage > Add Roles and Features**, then proceed through the wizard to **Select Features**.)
- ☐ .NET Framework 3.5 Features (all)
  - ☐ NET Framework 4.5 Features (all)
  - ☐ Windows Process Activation Service (all)
  - ☐ XPS Viewer
- 5 Use the IIS Manager to configure IIS to run in 32-bit mode:
- 5a Open the IIS Manager. (On the Windows taskbar, select **Server Manager > Tools > Internet Information Services (IIS) Manager**.)
  - 5b In the Connections pane, expand the server name, then click **Application Pools** to display the list of available application pools in the center pane.
  - 5c In the list, right-click **DefaultAppPool**, then click **Advanced Settings**.
  - 5d In the Advanced Settings dialog, set **Enable 32-bit Applications** to **True**, then click **OK**.
  - 5e In the Actions pane on the right, click **Set application pool defaults**.
  - 5f In the Application Pools Defaults dialog, set **Enable 32-bit Applications** to **True**, then click **OK**.
  - 5g Restart the IIS service. (Select the IIS server name in the Connections pane, then click **Restart** under the Actions pane.)

## 1.2.2 Installing Prerequisite Software on Windows Server 2008 R2 Systems

The following procedure applies to Microsoft Windows Server 2008 R2 (64-bit) servers where you plan to install PlateSpin Protect.

### To install required Microsoft software components:

- 1 Ensure that you are familiar with the [System Requirements](#) and [General Guidelines](#).
- 2 Use the Local User Administrator (LUA) account to log in to your intended PlateSpin Server host.
- 3 Use Server Manager to add the Web Server (IIS) role and its role services. Keep the default set of role services for the Web Server, and add the following required role services along with their sub-role services as shown. (Select **Start > All Programs > Administrative Tools > Server Manager**, click **Add Roles**, then proceed through the wizard to **Select Server Roles** and **Select Role Services** for the Web Server.)
  - ☐ Web Server (IIS)
    - ☐ Web Server
      - ☐ Common HTTP Features (all installed)
        - ♦ Static Content
        - ♦ Default Document
        - ♦ Directory Browsing
        - ♦ HTTP Errors
        - ♦ HTTP Redirection
        - ♦ WebDAV Publishing
      - ☐ Application Development (4 of 7 installed)
        - ♦ ASP .NET
        - ♦ .NET Extensibility
        - ♦ ISAPI Extensions
        - ♦ ISAPI Filters
      - ☐ Health and Diagnostics (2 of 6 installed)
        - ♦ HTTP Logging
        - ♦ Request Monitor
      - ☐ Security (all installed)
        - ♦ Basic Authentication
        - ♦ Windows Authentication
        - ♦ Digest Authentication
        - ♦ Client Certificate Mapping
        - ♦ IIS Client Certificate Mapping
        - ♦ URL Authorization
        - ♦ Requesting Filtering
        - ♦ IP and Domain Restrictions

- ☐ Performance (1 of 2 installed)
    - ♦ Static Content Compression
  - ☐ Management Tools (all installed)
    - ♦ IIS Management Console
    - ♦ IIS Management Script and Tools
    - ♦ Management Service
    - ♦ IIS 6 Management Compatibility
      - IIS 6 Metabase Compatibility
      - IIS 6 WMI Compatibility
      - IIS 6 Scripting Tools
      - IIS 6 Management Console
- 4 Use Server Manager to install the following required features and sub-features as shown. (In **Server Manager**, click **Add Features**.)
- ☐ .NET Framework (all installed)
    - ☐ .NET Framework 3.5.1
    - ☐ WCF Activation
      - ☐ HTTP Activation
      - ☐ Non-HTTP Activation
  - ☐ Windows Process Activation Service (all installed)
    - ☐ Process Model
    - ☐ .NET Environment
    - ☐ Configuration APIs
  - ☐ XPS Viewer
- 5 Download and install the [Microsoft .NET Framework 4](#) package.
- 6 Use the IIS Manager to configure IIS to run in 32-bit mode:
- 6a Open the IIS Manager. (On the Windows taskbar, select **Start > Administrative Tools > Internet Information Services (IIS) Manager**.)
  - 6b In the Connections pane, expand the server name, then click **Application Pools** to display the list of available application pools in the center pane.
  - 6c In the list, right-click **DefaultAppPool**, then click **Advanced Settings**.
  - 6d In the Advanced Settings dialog, set **Enable 32-bit Applications** to **True**, then click **OK**.
  - 6e In the Actions pane on the right, click **Set application pool defaults**.
  - 6f In the Application Pools Defaults dialog, set **Enable 32-bit Applications** to **True**, then click **OK**.
  - 6g Restart the IIS service. (Select the IIS server name in the Connections pane, then click **Restart** under the Actions pane.)

## 1.3 Installing PlateSpin Protect Software Components

This section provides information on installing the required components included in the PlateSpin Protect software. In order to use a remote Microsoft SQL Server database server and environment (instead of installing the SQL Server software included with the product on the same server), you must configure settings for the SQL server and configure your environment to allow the remote connection.

- ♦ [Section 1.3.1, “Starting the PlateSpin Protect Installation Launcher,” on page 16](#)
- ♦ [Section 1.3.2, “Installing the Database Server,” on page 16](#)
- ♦ [Section 1.3.3, “Installing the PlateSpin Server,” on page 18](#)
- ♦ [Section 1.3.4, “Post-Installation Tasks,” on page 19](#)

### 1.3.1 Starting the PlateSpin Protect Installation Launcher

This section provides information about installing PlateSpin Protect software after you ensure that the intended host has been prepared with the required prerequisites.

- 1 From [NetIQ Downloads \(https://dl.netiq.com\)](https://dl.netiq.com), download the `PlateSpinProtectSetup-11.1.0.xxxx.exe` installation program and save it on your intended PlateSpin Server host.
- 2 Run the installation program, specify a location for the temporary setup files, then click **Next**.  
The installation program extracts the required files and opens the Installation Launcher window.  
If the installation program detects an existing local installation of SQL Server, it disables the corresponding **Install SQL Server Express** option.  
If you intend to use the Microsoft SQL Server Express Edition distributed with PlateSpin Protect, install it first. For more information, see [“Installing Microsoft SQL Server Express Edition” on page 16](#).  
If you intend to use an existing Microsoft SQL Server database server, skip the database software installation. Configure SQL Server settings and your environment as described in [“Configuring Your Remote Microsoft SQL Server Database Server” on page 17](#) before you install the product.

### 1.3.2 Installing the Database Server

Use one of the following methods to set up the database server before you install PlateSpin Protect:

- ♦ [“Installing Microsoft SQL Server Express Edition” on page 16](#)
- ♦ [“Configuring Your Remote Microsoft SQL Server Database Server” on page 17](#)

#### Installing Microsoft SQL Server Express Edition

If you do not have an existing Microsoft SQL Server database server, you can install the Microsoft SQL Server Express Edition included in your PlateSpin Protect software distribution.

---

**NOTE:** The Microsoft SQL Server Express Edition included with PlateSpin Protect Server cannot be installed on a domain controller in accordance with [Microsoft Developer Network recommendations](#).

---

#### To install Microsoft SQL Server Express:

- 1 On your intended database server host, start the Installation Launcher.



See [“Starting the PlateSpin Protect Installation Launcher” on page 16.](#)

- 2 Click **Install SQL Server Express** and follow the on-screen instructions.

The program installs a database server and the database instance required for the operation of PlateSpin Protect.

- 3 (Conditional) If your SQL Server database server is on a separate server than the one you plan to use for the PlateSpin Server, configure the settings in your environment to allow the remote connection. See [“Configuring Your Remote Microsoft SQL Server Database Server” on page 17.](#)

## Configuring Your Remote Microsoft SQL Server Database Server

In order for your existing Microsoft SQL Server installation to function properly, PlateSpin Protect requires that you configure specific settings in your environment before you install the product. These settings allow the remote connection between your SQL Server and PlateSpin Server.

### To prepare your existing SQL server:

- 1 Ensure that your database server is running a supported version of Microsoft SQL Server. See [“Database Server” on page 10.](#)
- 2 Ensure that you have a dedicated, named database instance to use with PlateSpin Protect. You need the database server name and database instance name during the product installation.

---

**NOTE:** You can use the same Microsoft SQL Server database server to host database instances for multiple PlateSpin Protect and PlateSpin Migrate servers. Each database instance must be uniquely named and configured separately for its PlateSpin Server.

---

3. Ensure that you configure Microsoft SQL Server to allow both TCP/IP and Named Pipe connections.
- 4 (Conditional) If you plan to use Windows Authentication to access the Microsoft SQL Server database, you must configure the following in Active Directory:
  - ♦ You must add the Microsoft SQL Server database server to the domain.
  - ♦ You need two domain user accounts for the PlateSpin Protect installation.
    - ♦ **A Domain user with the `sysadmin` role set:** This user is required to create databases, tables, and other schema objects.
    - ♦ **PlateSpin Service user:** The service user can be a low-privileged domain user in the domain. However, the service user must be a local administrator on the PlateSpin Protect Server and should be granted that permission prior to the installation.

If the Windows user's password changes, you must update the password for the PlateSpin Service user and for the IIS App Pool. Consider using a Windows user whose password never expires to avoid the situation.

---

**NOTE:** Using Windows Authentication to log in to the SQL Server database is not supported for upgrade scenarios. This capability is available for new installs of the product.

---

- 5 Open the following ports on the firewall to support authentication to the SQL Server:
  - ♦ **Ports 49152-65535/TCP:** Allow traffic for RPC for LSA, SAM, Netlogon.
  - ♦ **Port 1433/TCP:** Allow traffic for Microsoft SQL Server.
  - ♦ **Custom ports:** If you configure SQL Server to use a custom TCP port, you must open that port on the firewall.

---

**NOTE:** If you do not use dynamic ports, you must specify the dedicated port in the **Database Server** field.

---

- 6 (Conditional) If you want to use dedicated ports with PlateSpin Protect, you must open the ports on the firewall:

- 6a On the database server, determine which ports need to be opened:

- 6a1 In the SQL Server Configuration Manager, select **Protocols for SQLEXPRESS > TCP/IP**, then right-click and select **Properties**.

- 6a2 In the dialog, select the **IP Addresses** tab.

- 6a3 Under **IPAll** (or under the desired protocol), if **TCP Port** or **TCP Dynamic Ports** is set to any value other than 0, open the specified ports on the firewall. These are the ports you use to connect to the SQL Server.

For example, if the **TCP Dynamic Ports** field is set to 60664, and the **TCP Port** field is set to 1555, then you must enable Port 60664 and 1555 in the firewall rules on the SQL server.

- 6b Open the ports on the firewall.

---

**NOTE:** If you have a value set for dynamic ports, you may not see your server in the list of SQL servers when you click **Browse**. In this case, you must specify the server manually in the **Database Server** input field of the PlateSpin Protect installation.

For example, if your server name is `MYSQLSERVER`, the database instance name `SQLEXPRESS`, and the dedicated port set for the dynamic port is `60664`, you type the following text, and then select the desired authentication type:

`MYSQLSERVER\SQLEXPRESS,60664`

You must open the ports on the firewall.

---

### 1.3.3 Installing the PlateSpin Server

- 1 Ensure that your intended PlateSpin Server host meets the minimum system requirements.  
See [“System Requirements” on page 9](#).
- 2 Ensure that your intended PlateSpin Server host meets the recommended guidelines.  
See [“General Guidelines” on page 11](#).
- 3 Ensure that your intended PlateSpin Server host has the necessary prerequisite software installed.  
See [“Installing Prerequisite Software” on page 12](#).
- 4 Ensure that your intended PlateSpin Server host has the necessary database server installed and configured.  
See [“Installing the Database Server” on page 16](#).
- 5 On your intended PlateSpin Server host, start the Installation Launcher.  
See [“Starting the PlateSpin Protect Installation Launcher” on page 16](#).
- 6 In the PlateSpin Protect Installation Launcher, click **Install PlateSpin Server** and follow the on-screen instructions.

The program starts the installation process and prompts you to accept the PlateSpin Protect software license agreement.

You must accept the software license agreement before installing the product.

- 7 Select the **I accept the terms in the license agreement** option, then click **Next**.
- 8 Specify a database server and database instance. Do one of the following:
  - ♦ If you are using the database server included in your PlateSpin Protect software distribution installed locally (the default option), leave the default selection `(local)\PLATESPINDB` in the drop-down list and leave the default `sa` credentials.  
  
If you subsequently move your PlateSpin Protect database instance or change your SQL Server password, you must reset the PlateSpin Protect database connection settings. For more information, see [Knowledgebase Article 7970523](#).
  - ♦ If you are using a remote database server, click **Browse** to select from a list of available database servers in the network. Specify the database in the following format:
    - ♦ **Single-instance SQL Server installations:** `database_server`
    - ♦ **Multiple-instance SQL Server installations:** `database_server\database_instance` (specify the instance name)
- 9 Specify your database credentials for the specified database server, then click **Validate Server** to validate them.  
  
(The default settings are **SQL Server:** `(local) PLATESPINDB` and **SQL Logon:** `sa.`)
- 10 Click **Next** and verify your **SQL Instance** and **SQL Logon** selections.
- 11 Click **Next**.  
  
The installation program prompts you specify whether you want to allow HTTP or HTTPS:  
  
If you require unsecured connections (HTTP), select the **Allow unsecured connections (HTTP)** option; if you require secured connections (HTTPS), leave the option deselected (default).  
  
If your IIS server has a signed SSL certificate, the default communication protocol will be HTTPS; if not, your browser will display a warning about an “untrusted connection.” This is normal. For information on how to proceed, see your browser documentation.
- 12 Click **Next**, verify the installation settings, click **Install**, and follow the on-screen instructions.  
  
The installation program installs the PlateSpin Server software and prepares it to run.

---

**NOTE:** This process might take several minutes to complete.

---

## 1.3.4 Post-Installation Tasks

After completing the installation of the PlateSpin Server:

- ♦ License your product and configure your environment in preparation for workload protection.  
  
See “[PlateSpin Protect Application Configuration](#)” in your *User Guide*.
- ♦ Start the PlateSpin Protect Web Interface and familiarize yourself with its interface and the workload protection features.  
  
See “[Launching the PlateSpin Protect Web Interface](#)” in your *User Guide*.



---

# 2 Upgrading PlateSpin Protect

To upgrade your PlateSpin Server to PlateSpin Protect 11.1, you must have an existing installation of any of the following versions of the product:

- ♦ PlateSpin Protect 11.0
- ♦ PlateSpin Protect 11.0.1
- ♦ PlateSpin Protect 11.0.1 Hotfix 1

Ensure that you prepare your PlateSpin Servers and workload environments prior to applying the upgrade.

- ♦ [Section 2.1, “Before Upgrading PlateSpin Protect,” on page 21](#)
- ♦ [Section 2.2, “Upgrade Procedure,” on page 22](#)

## 2.1 Before Upgrading PlateSpin Protect

Before you upgrade your PlateSpin Protect software to version 11.1:

- ♦ (Conditional) If any of your containers are VMware ESX/ESXi 3.5 or 4.0, upgrade them to version 4.1, 5.1, or 5.5. For more information, see [“Supported VM Containers”](#) in the *PlateSpin Protect User Guide*.
- ♦ Pause your replication schedules.
- ♦ Make a record of any customized `.config` parameters controlling the server’s default behavior.
- ♦ Back up your database files. See [Section 2.1.1, “Backing Up Your Database Files,” on page 21](#).

### 2.1.1 Backing Up Your Database Files

Use the following procedure to manually back up the Microsoft SQL Server database file that resides on the same server as PlateSpin Protect. You can use the backup file if you need to roll back.

- 1 On your server host, stop Microsoft SQL services:
  - 1a On the **Start** menu, click **Run**, type `services.msc`, then click **OK**.
  - 1b In the Services window, right-click the SQL Server items, then select **Stop**.
- 2 Copy all `*.mdf` and `*.ldf` files to a location outside the product installation directory. The default location of these files is:  
`\Program Files\PlateSpin Protect Server\Database`
- 3 Restart MS SQL services that you stopped in [Step 1](#).

---

**NOTE:** This procedure assumes a database installed on the same server with your PlateSpin Protect Server. Steps for backing up an external SQL server would be similar, though the paths to the `*.mdf` and `*.ldf` files would be specific to your SQL server.

---

## 2.2 Upgrade Procedure

During the upgrade process, the installation program automatically imports data from your previous installation.

- ♦ [Section 2.2.1, “Upgrade Procedure,” on page 22](#)
- ♦ [Section 2.2.2, “Post-Upgrade Tasks,” on page 22](#)

### 2.2.1 Upgrade Procedure

Use this procedure to upgrade your PlateSpin Protect product.

- 1 Back up your data.  
See [“Before Upgrading PlateSpin Protect” on page 21](#).
- 2 Run the PlateSpin Protect setup executable and follow the on-screen instructions.  
Ensure that you select the **Save data** option when prompted during the server installation.

---

**NOTE:** In some situations the installation program might fail to automatically re-import data that it exports during the upgrade process. If this happens, use the `ImportExportAll.bat` utility to recover this data from the following directory on your server host:

- ♦ **Windows Server 2012 R2 Systems:** `\ProgramData\PlateSpin`  
This folder is hidden by default.
- ♦ **Windows Server 2008 Systems:** `\ProgramData\PlateSpin`  
This folder is hidden by default.
- ♦ **Windows Server 2003 Systems:** `\Documents and Settings\All Users\Application Data\PlateSpin`

In order to import/export when you use Windows Authentication for database access, the following conditions must be met:

1. The user must be logged in as the domain user used by the PlateSpin service to access the database. This user is specified during the installation.
  2. As is required by the installation, the domain user used by the PlateSpin service to access the database must be a member of the local Administrators group.
  3. The process that runs the import/export command must have elevated privileges. This is most easily accomplished by starting a command window using the **Run as administrator** context menu option.
- 

### 2.2.2 Post-Upgrade Tasks

- 1 (Optional, for International versions) Set up PlateSpin Protect and your browser for use in a specific supported language.  
See [“Configuring Language Settings for International Versions of PlateSpin Protect”](#) in your *User Guide*.
- 2 Check the Workloads page for any paused replication schedules. In particular, look for *Tasks* (special workload protection events with optional commands) generated for automatically upgrading protection contracts that were using a legacy block-based component from earlier versions of the product. This requires a reboot of the protected workload.

- 3 Reapply the required `.config` parameters in the new `.config` files.

See “[Configuring PlateSpin Server Behavior through XML Configuration Parameters](#)” in your *User Guide*.





---

# A Documentation Updates

This section contains information on documentation content changes that were made in this *Installation and Upgrade Guide* after the initial release of NetIQ PlateSpin Protect 11.1.

---

**NOTE:** This updated information does not appear in the help content accessible from the product's user interface, nor in localized versions of the *Installation and Upgrade Guide*.

---

- ♦ [Section A.1, "July 2015," on page 25](#)
- ♦ [Section A.2, "June 2015," on page 25](#)
- ♦ [Section A.3, "May 2015," on page 25](#)
- ♦ [Section A.4, "April 2015," on page 26](#)

## A.1 July 2015

Location	Update
<a href="#">Section 1.2.1, "Installing Prerequisite Software on Windows Server 2012 R2 Systems," on page 12</a>	Correction for IIS 6 Management Compatibility on Windows Server 2012 R2.

## A.2 June 2015

Location	Update
Various	Updated links.

## A.3 May 2015

Location	Update
Various	Updated links.
<a href="#">Section 1.2.2, "Installing Prerequisite Software on Windows Server 2008 R2 Systems," on page 14</a>	Added details about which role services and features are required for Web Server (IIS) on Windows Server 2008 R2.

## A.4 April 2015

Location	Update
Various	Applied editorial changes.