

# **Driver for Blackboard\* Implementation Guide Identity Manager 4.0.2**

June 22, 2012

## Legal Notices

Novell, Inc. and Omnibond Systems, LLC. make no representations or warranties with respect to the contents or use of this documentation, and specifically disclaim any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. and Omnibond Systems, LLC. reserve the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. and Omnibond Systems, LLC. make no representations or warranties with respect to any software, and specifically disclaim any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. and Omnibond Systems, LLC. reserve the right to make changes to any and all parts of the software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export, or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [the Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2012 Omnibond Systems, LLC. All rights reserved. Licensed to Novell, Inc. Portions copyright © 2012 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the [Novell Legal Patents Web page \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.  
1800 South Novell Place  
Provo, UT 84606  
U.S.A.  
[www.novell.com](http://www.novell.com)

*Online Documentation:* To access the online documentation for this and other Novell products, and to get updates, see [the Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation/).

## Novell Trademarks

For Novell trademarks, see the [Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

## Third-Party Materials

All third-party trademarks are the property of their respective owners.

---

# Contents

<b>About This Guide</b>	<b>5</b>
<b>1 Understanding the BlackBoard Driver</b>	<b>7</b>
1.1 What's New	7
1.2 Known Issues	8
1.3 Version Support	8
1.4 Blackboard Driver Concepts	8
1.4.1 Default Data Flow	8
1.4.2 Policies	9
1.4.3 Driver Components	9
1.5 Support for Standard Driver Features	9
1.5.1 Entitlements	10
1.5.2 Schema	10
1.5.3 Object Classes	10
1.5.4 Configuration	10
1.6 Differences Between eDirectory and Blackboard	10
1.6.1 Organization	10
1.6.2 Passwords	11
<b>2 Installing the Driver On Your Blackboard System</b>	<b>13</b>
2.1 Before You Begin	13
2.2 Required Knowledge and Skills	13
2.3 Getting the Installation Files	14
2.4 Installation Tasks	14
2.4.1 Installing the Driver Files	14
2.4.2 Installing the Java Class File on the Blackboard Server	14
2.4.3 Copying Blackboard Files to Remote Loader classpath	15
2.4.4 Extending the Schema for Identity Manager	15
2.4.5 Configuring the Remote Loader	16
2.4.6 Testing Connectivity to Blackboard	18
2.4.7 Starting the Remote Loader Service	18
2.5 Post-Installation Tasks	18
2.6 Uninstalling the Driver	18
<b>3 Creating a New Driver</b>	<b>19</b>
3.1 Creating the Driver in Designer	19
3.1.1 Importing the Current Driver Packages	19
3.1.2 Installing the Driver Packages	20
3.1.3 Configuring the Driver	22
3.1.4 Deploying the Driver	23
3.1.5 Starting the Driver	24
3.2 Creating the Driver in iManager (old method)	24
3.2.1 Importing the Driver Configuration File	24
3.2.2 Configuring the Driver	27
3.2.3 Starting the Driver	28
3.3 Activating the Driver	28

<b>4</b>	<b>Customizing the Driver</b>	<b>29</b>
4.1	Attributes Required for Blackboard Object Creation . . . . .	29
4.2	Attributes and Values for Blackboard Enumeration Types. . . . .	30
<b>5</b>	<b>Managing the Driver</b>	<b>33</b>
<b>6</b>	<b>Troubleshooting the Driver</b>	<b>35</b>
6.1	Viewing Driver Processes . . . . .	35
6.2	Troubleshooting Blackboard-Specific Items. . . . .	35
<b>A</b>	<b>Policies</b>	<b>37</b>
A.1	Event Transforms . . . . .	37
A.2	Matching. . . . .	37
A.3	Creation Policies . . . . .	38
A.4	Command Transforms . . . . .	39
A.5	Schema Mapping . . . . .	39
A.6	Output Transforms . . . . .	40
A.7	Input Transforms . . . . .	41
<b>B</b>	<b>Global Configuration Values</b>	<b>43</b>
B.1	General Settings . . . . .	43
B.2	Default Required Attribute Settings . . . . .	44
<b>C</b>	<b>Test Scripts</b>	<b>47</b>
C.1	Test Scripts . . . . .	47
C.1.1	Linux Test Script . . . . .	47
C.1.2	UNIX Test Script . . . . .	48
C.1.3	Windows Test Script . . . . .	48
C.2	Expected Results . . . . .	49

---

# About This Guide

This *Implementation Guide* explains implementation of the Novell® Identity Manager 4.0.2 driver for Blackboard\*.

The driver enables you to synchronize data in the Identity Vault to data stored in a Blackboard system. This configurable solution allows you to increase productivity and streamline business processes by integrating Blackboard with your other IT systems.

This *Guide* includes the following sections:

- ♦ Chapter 1, “Understanding the BlackBoard Driver,” on page 7
- ♦ Chapter 2, “Installing the Driver On Your Blackboard System,” on page 13
- ♦ Chapter 3, “Creating a New Driver,” on page 19
- ♦ Chapter 4, “Customizing the Driver,” on page 29
- ♦ Chapter 5, “Managing the Driver,” on page 33
- ♦ Chapter 6, “Troubleshooting the Driver,” on page 35
- ♦ Appendix A, “Policies,” on page 37
- ♦ Appendix B, “Global Configuration Values,” on page 43
- ♦ Appendix C, “Test Scripts,” on page 47

## Audience

This *Guide* is for system administrators and others who plan, install, configure, and use the Identity Manager driver for BlackBoard. It assumes that you are familiar with Identity Manager, Novell eDirectory™, and the administration of systems and platforms you connect to Identity Manager.

## Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to the [Novell Documentation Feedback site \(http://www.novell.com/documentation/feedback.html\)](http://www.novell.com/documentation/feedback.html) and enter your comments there.

## Documentation Updates

For the most recent version of this guide, visit the [Identity Manager 4.0.2 Drivers Documentation Web site \(http://www.novell.com/documentation/idm402drivers\)](http://www.novell.com/documentation/idm402drivers).

## Additional Documentation

For additional documentation about Identity Manager drivers, see the [Identity Manager 4.0.2 Drivers Documentation Web site \(http://www.novell.com/documentation/idm402drivers\)](http://www.novell.com/documentation/idm402drivers).

For additional documentation about Identity Manager, see the [Identity Manager 4.0.2 Documentation Web site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

For documentation about other related Novell products, such as eDirectory and iManager, see [the Novell Documentation Web site's product index \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

## Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (®, ™, etc.) denotes a Novell trademark. An asterisk (\*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux\* or UNIX\*, should use forward slashes as required by your software.

---

# 1 Understanding the BlackBoard Driver

The Novell® Identity Manager 4.0.2 driver for Blackboard lets you synchronize data in the Identity Vault to data stored in a Blackboard Learn implementation.

The Subscriber channel receives XDS command documents for users and groups from the Identity Manager Metadirectory engine, converts them to Blackboard API calls, and executes them. The Publisher channel is not implemented at this time.

The Subscriber channel does not perform validation of attribute values in the XDS command document. If the requirements of Blackboard are not met, the results of the Blackboard API calls are unpredictable. Exceptions detected by the Blackboard API bubble up to the driver trace to assist in troubleshooting data validity problems.

The following sections provide a basic overview of the driver:

- ♦ [Section 1.1, “What’s New,” on page 7](#)
- ♦ [Section 1.2, “Known Issues,” on page 8](#)
- ♦ [Section 1.3, “Version Support,” on page 8](#)
- ♦ [Section 1.4, “Blackboard Driver Concepts,” on page 8](#)
- ♦ [Section 1.5, “Support for Standard Driver Features,” on page 9](#)
- ♦ [Section 1.6, “Differences Between eDirectory and Blackboard,” on page 10](#)

## 1.1 What’s New

Version 4.0.2 of the Blackboard driver includes:

- ♦ Added shim support for course cloning
- ♦ Updated deprecated blackboard attributes
- ♦ Fixed windows install issues

## 1.2 Known Issues

At the time this *Implementation Guide* was published, one known issue existed for the Identity Manager 4.0.2 driver for Blackboard relating to structured Global Configuration Values (GCVs) and package management.

Until the issue is resolved, additional steps must be taken when upgrading or downgrading packages containing structured GCVs. The Blackboard Group Based Enrollments package (OBNDBKBDGBE) contains a structured GCV that represents group attributes to Blackboard role mappings. When upgrading or downgrading this package, please include the following procedure:

- 1 Copy the XML representation of the OBNDBKBDGBE-gcv GCV into a backup file.
- 2 After upgrading or downgrading, replace the XML in the OBNDBKBDGBE-gcv with the XML from the backup file.

## 1.3 Version Support

The Blackboard driver requires Identity Manager 3.6 or greater and Blackboard 9 or greater.

## 1.4 Blackboard Driver Concepts

The following sections explain concepts you should understand before implementing the BlackBoard driver:

- ♦ [Section 1.4.1, “Default Data Flow,” on page 8](#)
- ♦ [Section 1.4.2, “Policies,” on page 9](#)
- ♦ [Section 1.4.3, “Driver Components,” on page 9](#)

### 1.4.1 Default Data Flow

A channel is a combination of rules, policies, and filters that is used to synchronize data between two systems. The Subscriber and Publisher channels describe the direction in which the data flows. The Subscriber and Publisher channels act independently; actions in one channel are not affected by what happens in the other.

- ♦ [“Subscriber Channel” on page 8](#)
- ♦ [“Publisher Channel” on page 9](#)


#### Subscriber Channel

The Subscriber channel is the channel of communication from the Identity Vault to Blackboard. The channel takes events generated in the Identity Vault and sends them to the Blackboard system. The Subscriber channel also supports queries into BlackBoard.

[Figure 1-1](#) illustrates this data flow.



**Figure 1-1** Data Flow Through The Subscriber Channel



The driver can be configured to work with Blackboard, versions 9 and later.

## Publisher Channel

The Publisher channel is not implemented.

### 1.4.2 Policies

Policies are used to control the synchronization of data between the Identity Vault and Blackboard. The Blackboard driver is designed to be used with Identity Manager 4.0 Packages, but for backward compatibility the policies have been provided in an XML preconfiguration document. For information about the policies installed in the preconfiguration, see [Appendix A, "Policies,"](#) on [page 37](#). All policies contained in the Packages are included in the preconfiguration file for Identity Manager 3.6.

### 1.4.3 Driver Components

The driver contains the following components:

- ♦ **Default Driver Configuration File for Identity Manager 3.6:** A file you can import to set up default rules, style sheets, and driver parameters. The driver configuration file included with this driver is `BlackboardDriver.xml`.
- ♦ **Driver Files:** `Blackboard.jar` is the Java file that directs synchronization between Blackboard and the Identity Vault.
- ♦ **Schema File:** `blackboard.sch` contains optional schema extensions to be used with the Blackboard driver.

## 1.5 Support for Standard Driver Features

The Blackboard driver is designed to be run as a Remote Loader Service only.

The following sections provide information about how the driver supports standard driver features:

- ♦ [Section 1.5.1, "Entitlements,"](#) on [page 10](#)
- ♦ [Section 1.5.2, "Schema,"](#) on [page 10](#)
- ♦ [Section 1.5.3, "Object Classes,"](#) on [page 10](#)
- ♦ [Section 1.5.4, "Configuration,"](#) on [page 10](#)

## 1.5.1 Entitlements

The Blackboard driver can be configured to use entitlements to manage user accounts in Blackboard. When using entitlements, this driver works in conjunction with external services, such as the User Application with workflow or role-based provisioning or the Entitlements Service driver, to manage entitlement functionality.

## 1.5.2 Schema

The Blackboard driver uses the Blackboard schema to describe the attributes of Person, Course, Organization, and Enrollment objects in Blackboard. Optional schema definitions for the Blackboard driver are included in the `blackboard.sch` file.

## 1.5.3 Object Classes

The Blackboard driver provides auxiliary classes that can be used to add Blackboard-specific schema attributes to User and Group objects in eDirectory. Optional schema definitions for the Blackboard driver are included in the `blackboard.sch` file.

## 1.5.4 Configuration

The behavior of an Identity Manager driver is governed by its configuration of options, policies, and filters. The configuration of the Blackboard driver is managed by several packages that can be installed and configured using Designer for Identity Manager.

# 1.6 Differences Between eDirectory and Blackboard

## 1.6.1 Organization

Blackboard is similar to eDirectory in the way information is organized with the exception of Blackboard Enrollments.

User objects in eDirectory map directly to Person objects in Blackboard. Group objects in eDirectory map directly to Course and Organization objects in Blackboard. Course and Organization objects are differentiated by the `OBNDBKBDDC-sub-evt-DetermineBBObjectType` Event Transform Policy. Blackboard Enrollments have additional attributes that eDirectory Group memberships do not support. Two options exist to represent Enrollments in eDirectory:

- ♦ The suggested best practice is to create a Blackboard Enrollment Object using the `DirXML-BB-Enrollment` object class in eDirectory for each enrollment in Blackboard.
- ♦ The other option is to use the Group Member and Owner attributes to represent enrollments in Blackboard. The disadvantage of using the Member and Owner attributes is that enrollments can only be removed rather than being disabled.

While eDirectory is hierarchical, Blackboard is flat—there is no concept of a move function. The Subscriber channel rejects move commands. The sample Subscriber Event policy vetoes move events. You can change this policy to perform installation-specific processing of move events if required.

User object deletions in eDirectory result in the associated Person object in Blackboard being deleted. Group object deletions in eDirectory result in the associated Course or Organization object in Blackboard being deleted. There is no concept of rename in Blackboard. Blackboard is not hierarchical. There is no move function.

## 1.6.2 Passwords

Identity Manager uses the nspmDistributionPassword attribute to provide passwords from eDirectory. The mapping policy in the preconfigured sample policies maps nspmDistributionPassword to DirXML-BB-p-password. The password is md5-hashed by the Driver Shim before being stored into Blackboard. The driver will also accept a md5-hashed password if mapped to the DirXML-BB-p-hashed-password attribute.



---

# 2 Installing the Driver On Your Blackboard System

The Novell® Identity Manager 4.0.2 driver for Blackboard consists of the Blackboard Driver Shim installed with the Java\* Remote Loader. The Driver Shim provides the conduit for information transfer between eDirectory (through Identity Manager) and the Blackboard system.

The Driver Shim must be installed on the application server running the Blackboard system to connect to the Blackboard application using the Blackboard Administrative API. In a load balanced configuration the driver should only be run on one of the application servers.

This section provides the information you need for first-time installation of the Novell® Identity Manager 4.0.2 driver for Blackboard. Topics include:

- ♦ [Section 2.1, “Before You Begin,” on page 13](#)
- ♦ [Section 2.2, “Required Knowledge and Skills,” on page 13](#)
- ♦ [Section 2.3, “Getting the Installation Files,” on page 14](#)
- ♦ [Section 2.4, “Installation Tasks,” on page 14](#)
- ♦ [Section 2.5, “Post-Installation Tasks,” on page 18](#)
- ♦ [Section 2.6, “Uninstalling the Driver,” on page 18](#)

## 2.1 Before You Begin

Before you install the Novell Identity Manager Driver for Blackboard in a production environment:

- ♦ You should install the driver in a test environment for use in developing your full deployment plan.
- ♦ Ensure that you have the most recent distribution, support pack, and patches for the driver.
- ♦ Review the most recent support information for the driver on the [Novell Support Web site \(http://support.novell.com\)](http://support.novell.com).

## 2.2 Required Knowledge and Skills

Although different tasks can be performed by different people, your installation and deployment team must collectively have expertise with eDirectory, iManager, Identity Manager, Blackboard, and XSLT.

Full administrative rights are required, both in eDirectory and on Blackboard.

To find other documentation related to this product and its installation, see [“Additional Documentation” on page 5](#).

For an overview of driver facilities, see [Chapter 1, “Understanding the BlackBoard Driver,”](#) on page 7.

## 2.3 Getting the Installation Files

Obtain the most recent distribution of the Identity Manager 4.0.2 Driver for Blackboard from the [Novell Downloads Web site \(http://download.novell.com/\)](http://download.novell.com/).

At the time of this *Implementation Guide*'s release, the driver was included in the following ISO packages:

- ♦ Identity\_Manager\_4.0.2\_Linux\_Standard.iso
- ♦ Identity\_Manager\_4.0.2\_Windows\_Standard.iso
- ♦ Identity\_Manager\_4.0.2\_Linux\_Advanced.iso
- ♦ Identity\_Manager\_4.0.2\_Windows\_Advanced.iso

## 2.4 Installation Tasks

### 2.4.1 Installing the Driver Files

- 1 If you have not already done so, install a Metadirectory server. For instructions, see the *Identity Manager Installation Guide* at [Identity Manager 4.0.2 Documentation Page \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).
- 2 Install the Remote Loader on the Blackboard Application server. For instructions, the *Identity Manager Installation Guide* at [Identity Manager 4.0.2 Documentation Page \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).  
The Remote Loader installation includes jar files for the Blackboard driver.
- 3 Continue to the next section to complete installation of the files.

### 2.4.2 Installing the Java Class File on the Blackboard Server

The file `Blackboard.jar` contains Java classes used by the Publisher and Subscriber channels to convert XDS command documents into Blackboard API calls. RPM and PKG archives are provided for the appropriate operating systems to install `Blackboard.jar` into the correct location.

If you are running Linux, you can find the RPM and PKG archives in the `Additional_Drivers/Blackboard` directory in the ISO image for Linux. If you are running Windows, you can find the `Blackboard.jar` file in the `Additional_Drivers/Blackboard` directory in the ISO image for Windows.

Install the driver's Java class file on the Blackboard server as follows, depending on your operating system:

- ♦ If you are running Linux, enter: `rpm -ivh novell-DXMLbb.rpm`
- ♦ If you are running Solaris, enter: `pkgadd -n -d DXMLbb.pkg`
- ♦ If you are running Windows, copy `Blackboard.jar` to `\novell\RemoteLoader\lib`

## 2.4.3 Copying Blackboard Files to Remote Loader classpath

These files are needed to connect to the Blackboard Event API.

---

**IMPORTANT:** Before copying files into the `RemoteLoader\lib` directory, copy the contents of the `RemoteLoader\lib` directory to a backup location to be used when updating the Blackboard Driver. Future releases of Blackboard may include newer versions of jar files that will conflict with existing versions in this `lib` directory. After upgrading to a new version of Blackboard, replace the existing `RemoteLoader\lib` directory with the backup copy you created before installing the driver the first time. This should result in the directory only containing files that were added when the remote loader was originally installed. Follow the file copy instructions below to complete the installation or upgrade process.

---

### Linux

Copy: `/usr/local/blackboard/apps/tomcat/lib/*`

to: `/opt/novell/eDirectory/lib/dirxml/classes`

### Solaris

1 Copy: `/usr/local/blackboard/apps/tomcat/lib/*`

to: `/opt/novell/eDirectory/lib/dirxml/classes`

2 Copy: `/usr/local/blackboard/apps/tomcat/common/lib/xercesImpl.jar`

to: `/opt/novell/eDirectory/lib/sparcv9/nds-modules/jre/lib`

(replace `sparcv9` with correct version of `sparc`)

### Windows

1 Copy: `\blackboard\apps\tomcat\lib\*.*`

to: `\Novell\RemoteLoader\lib\`

2 Copy: `\blackboard\apps\tomcat\lib\xercesImpl.jar`

to: `\Novell\RemoteLoader\jre\lib\`

3 Create a `classes` directory in the `RemoteLoader` directory.

4 Copy: `\blackboard\apps\tomcat\lib\xythos.properties`

to: `\Novell\RemoteLoader\classes`

## 2.4.4 Extending the Schema for Identity Manager

If you plan on using the Identity Vault to manage connected system attributes that are not already mapped to standard eDirectory™ attributes, you will need to extend the schema. Otherwise, it is not necessary.

Extending the schema adds auxiliary classes to eDirectory User and Group objects for Blackboard user and group attributes. It also extends the schema for an effective class called DirXML-BB-Enrollment that can be used to represent an enrollment in a Blackboard Course or Organization.

To extend the schema:

- 1 Obtain the `blackboard.sch` file for browser access, depending on the operating system you are running:
  - ♦ **Linux or Solaris:** Copy the `blackboard.sch` file from `/opt/novell/eDirectory/lib/lib/nds-schema/` on the Blackboard application server where you installed the RPM or PKG archive (see ) to a location accessible to your web browser.
    - Windows:** Copy the `blackboard.sch` file from from the `Additional_Drivers/Blackboard` directory in the ISO image for Windows to a location accessible to your web browser.
- 2 In iManager, select the *Extend Schema* task under *Schema*.
- 3 Select *Import data from file on disk*, then click *Next*.
- 4 Select a file type of *Schema File*.
- 5 Type or browse for `blackboard.sch` as the file to import, then click *Next*.
- 6 Specify the host name or IP address and the LDAP port number of your Metadirectory server.
- 7 To connect to the non-secure LDAP port (389), you must have the *Require TLS for Simple Binds with Password* option disabled on your LDAP Group. If necessary, you can edit this option using the *LDAP Options* task under *LDAP* in iManager. For details, see the *Novell eDirectory Administration Guide*.
- 8 Select *Authenticated login* and log in as Admin or another user with rights to extend the schema.
- 9 Click *Next* to go to the summary.
- 10 Click *Finish* to extend the schema.

## 2.4.5 Configuring the Remote Loader

### Linux and UNIX

For detailed instructions on configuring the Remote Loader for Linux and UNIX, see the relevant instructions in the *Identity Manager 4.0.2 Remote Loader Guide* at the [Identity Manager 4.0.2 Documentation site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

Be sure to place the configuration file in `/etc/opt/novell/dirxml/rdxml` so the driver will start when the system is started. The following is an example configuration file that does not include settings for a secure connection:

```
-commandport 8000
-connection "port=8090 fromaddress=xxx.xxx.xxx.xxx"
-class com.Omnibond.nds.dirxml.driver.Blackboard.BlackboardDriverShim
-trace 0
-tracefile /tmp/bbtrace.log
```

If you are using SSL for a secure connection, see the relevant instructions in the *Identity Manager 4.0.2 Remote Loader Guide* at the [Identity Manager 4.0.2 Documentation site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

The configuration file will need to include the keystore and storepass settings for SSL. Following is an example configuration that includes settings for a secure connection:



```
-commandport 8000
-connection "port=8090 fromaddress=xxx.xxx.xxx.xxx keystore='mystore'
storepass='dirxml' "
-class com.Omnibond.nds.dirxml.driver.Blackboard.BlackboardDriverShim
-trace 0
-tracefile /tmp/bbtrace.log
```

## Windows

For detailed instructions on configuring the Remote Loader for Windows, see the relevant instructions in the *Identity Manager 4.0.2 Remote Loader Guide* at the [Identity Manager 4.0.2 Documentation site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402)

For the *Driver* field, enter:

```
com.Omnibond.nds.dirxml.driver.Blackboard.BlackboardDriverShim
```

**Figure 2-1** provides an example of the Remote Loader configuration dialog with this entry.

**Figure 2-1** Remote Driver Configuration dialog for Windows.

**Edit**

Remote Driver Configuration

Description: Blackboard Drive

Driver: com.Omnibond.nds.dirxml.driver.Blackboard.BlackboardDriverShim

Config File: C:\Novell\RemoteLoader\BlackboardDriver-Config.txt

Communication

IP Address: All

Connection Port - Metadirectory Server: 8090

Command Port - Local host communication only: 8000

Remote Loader Password

Password: \*\*\*\*\*

Confirm: \*\*\*\*\*

Driver Object Password

Password: \*\*\*\*\*

Confirm: \*\*\*\*\*

Secure Socket Layer(SSL)

Use an SSL Connection

Trusted Root File:

Trace File

Trace Level: 10 User defined trace level

Trace File: C:\Novell\RemoteLoader\Blackboard Driver-Trace.log

Maximum Disk Space Allowed for all Trace Logs (Mb):

Unlimited 0

Establish a Remote Loader service for this driver instance.

OK

Cancel

Advanced...

## 2.4.6 Testing Connectivity to Blackboard

To test connectivity to Blackboard, run the appropriate test script for your platform located in [Appendix C, “Test Scripts,” on page 47](#).

## 2.4.7 Starting the Remote Loader Service

Start the Remote Loader Service as follows, depending on your operating system.

### Linux and Solaris

- 1 Ensure the configuration file was copied to `/etc/opt/novell/dirxml/rdxml/`
- 2 Run the following command:

```
/etc/init.d/rdxml start
```

### Windows

Use the Remote Loader Console application to start the driver.

## 2.5 Post-Installation Tasks

Once you have installed and configured the driver software on your Blackboard system, do the following:

- 1 Start the remote loader based on the operating system you are running.
- 2 Follow the directions in [Chapter 3, “Creating a New Driver,” on page 19](#) to set up the corresponding representation of your driver in the Identity Vault.

## 2.6 Uninstalling the Driver

To uninstall the driver:

- 1 Remove the remote loader configuration information associated with the driver. For more information, see the *Identity Manager Installation Guide* at [Identity Manager 4.0.2 Documentation Page \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).
- 2 Remove the jar file associated with the driver.

---

# 3 Creating a New Driver

After the driver files are installed on the Blackboard system where you want to run the driver (see [Chapter 2, “Installing the Driver On Your Blackboard System,” on page 13](#)), you can create the driver’s representation in the Identity Vault. You do so by importing the basic driver configuration file and then modifying the driver configuration to suit your environment. The following sections provide instructions:

- ♦ [Section 3.1, “Creating the Driver in Designer,” on page 19](#)
- ♦ [Section 3.2, “Creating the Driver in iManager \(old method\),” on page 24](#)
- ♦ [Section 3.3, “Activating the Driver,” on page 28](#)

## 3.1 Creating the Driver in Designer

You create the Blackboard driver in Designer by importing its basic configuration file and then modifying the configuration to suit your environment. After creating and configuring the driver, you need to deploy it to the Identity Vault and start it.


- ♦ [Section 3.1.1, “Importing the Current Driver Packages,” on page 19](#)
- ♦ [Section 3.1.2, “Installing the Driver Packages,” on page 20](#)
- ♦ [Section 3.1.3, “Configuring the Driver,” on page 22](#)
- ♦ [Section 3.1.4, “Deploying the Driver,” on page 23](#)
- ♦ [Section 3.1.5, “Starting the Driver,” on page 24](#)

### 3.1.1 Importing the Current Driver Packages

The driver packages contain the items required to create a driver, such as policies, entitlements, filters, and Schema Mapping policies. These packages are only available in Designer and can be updated after they are initially installed. You must have the most current version of the packages in the Package Catalog before you can create a new driver object.

To verify you have the most recent version of the driver packages in the Package Catalog:

- 1 Open Designer.
- 2 In the toolbar, click *Help > Check for Package Updates*.
- 3 Click *OK* to update the packages  
or  
click *OK* if the packages are up-to-date.
- 4 In the Outline view, right-click the Package Catalog.  
Click *Import Package*.



- 5 Select any Blackboard driver packages  
or  
Click *Select All* to import all of the packages displayed.

---

**NOTE:** By default, only the base packages are displayed. Deselect *Show Base Packages Only* to display all packages.

---

- 6 Click *OK* to import the selected packages, then click *OK* in the successfully imported packages message.
- 7 After the current packages are imported, continue with [Installing the Driver Packages](#)

### 3.1.2 Installing the Driver Packages

- 1 In Designer, open your project.
- 2 In the Modeler, right-click the driver set where you want to create the driver, then select *New > Driver*.
- 3 Select *Blackboard Base*, then click *Next*.
- 4 Select the optional features to install the Blackboard driver. All options are selected by default. The options are:

**Blackboard Default Configuration:** This package contains the default configuration information for the Blackboard driver. Always leave this option selected.

**Blackboard Group Based Enrollments:** This package contains the policies required if you want to use Group attributes for Blackboard Enrollments .

**Blackboard User Entitlements:** This package contains the policies and entitlements required to enable the driver to account creation and management with entitlements. For more information, see the *Identity Manager 4.0.2 Entitlements Guide* on the [Identity Manager 4.0.2 Documentation Site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

- 5 Click *Next*.
- 6 On the *Driver Information* page, fill in the following field:  
**Driver Name:** The name that identifies the driver in Designer and eDirectory®.
- 7 Click *Next*.
- 8 On the *Remote Loader* page, fill in the following fields:  
**Host Name:** Enter the Host Name or IP Address where the Remote Loader Service has been installed and is running for this driver.  
**Port:** Enter the Port Number where the Remote Loader Service has been installed and is running for this driver. The Default Port is 8090.

**Remote Password:** The Remote Loader password is used to control access to the Remote Loader instance. It must be the same password that is specified as the Remote Loader password on the Identity Manager Remote Loader.

**Driver Password:** The Driver Object Password is used by the Remote Loader to authenticate itself to the Identity Manager server. It must be the same password that is specified as the Driver Object Password on the Identity Manager Remote Loader.

**Use Secure Remote Loader:** Choose if the driver should use SSL to connect to the remote loader.

**(optional) Key Material Object (KMO):** If *Yes* was selected for *Use Secure Remote Loader* enter the Key Material Object to be used for the SSL connection to the remote loader..

9 Click *Next*.

10 On the next page fill in the following fields:

**Location of the bb-config.properties file:** Specify the path to the location of the bb-config.properties file. You MUST include a trailing slash.

---

**NOTE:** The path on most Windows systems is `c:\blackboard\config\`.

---

**Name of Virtual Installation:** Name of the Virtual Installation for Blackboard. Leave blank if using the default installation.

11 (Conditional) This page displays only if you selected to install the Blackboard Group Based Enrolments package. Fill in the following field:

**Choose the roles that should be used for users who are added to the following group attributes:** This setting holds mappings from Group attributes to Blackboard Enrollment Roles. The default map contains mappings that map members of the Member attribute to Student enrollment object and members of the Owner attribute to Instructor enrollment objects. Additional roles can be supported by extending the schema and mapping the desired group attribute to a Blackboard role.

---

**NOTE:** You must remember to add the additional attributes to the filter.

---

12 Click *Next*.

13 (Conditional) This page displays only if you selected to install the Blackboard User Entitlements package. Fill in the following field:

**If a user loses the bbAccount Entitlement take the following action:** Choose the desired action if a user loses the bbAccount Entitlement.

14 Click *Next*.

15 (Conditional) This page displays only if you selected to install the Blackboard Default Configuration package. (This package should always be selected.) Fill in the following fields:

**Limit the driver to a base container in the Identity Vault for synchronization:** Limit events the driver processes to a base container in eDirectory.

**Specify the base container in the Identity Vault for User synchronization:** This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: users.myorg.

**Specify the base container in the Identity Vault for Group synchronization:** This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: groups.myorg

**What action should be taken on an enrollment when a Person is removed from a Group:** If set to *Delete* enrollments dropped from a Group will result in the Person being removed from the Course or Organization. If set to *Disable* the Person's enrollment will be disabled in the Course or Organization.

**Automatically set the required ID attribute for new Person, Course, and Organization objects to the source name of the object :** If true then the required id attribute for Person, Course, and Organization types in Blackboard will be automatically set to Source Name if the id attribute is not already set. The attributes are DirXML-BB-p-id for Person, DirXML-BB-c-id for Course, and DirXML-BB-o-id for Organization.

**Automatically set the required title attribute for new Course, and Organization objects to the source name of the Group:** Automatically set required attribute DirXML-bb-c-course-title to the source name for Course objects if it is not already set. Automatically set required attribute DirXML-bb-o-title to source name for Organization objects.

**Automatically set the required user roles attributes for Person objects :** If true the default roles chosen below will be set for a user if they are not present on the user object.

**Default System Role for new users:** The default system role to use for new users. See Blackboard Documentation for more information about System Roles.

**Default Institutional Role for new users. [ex. STUDENT, STAFF, ALUMNI, GUEST, FACULTY, OBSERVER, or any custom defined roles]:** Default Institutional Role. See Blackboard documentation for more information about Institutional Roles.

**Group objects in this subtree will be synchronized as Courses in Blackboard:** All group objects in this subtree will be synchronized as Courses in Blackboard. Group objects in eDirectory can represent a Course or Organization object in Blackboard.

**Group objects in this subtree will be synchronized as Organizations in Blackboard:** All group objects in this subtree will be synchronized as Organizations in Blackboard. Group objects in eDirectory can represent a Course or Organization object in Blackboard.

**Automatically set required Person attribute DirXML-BB-p-email if it is not set:** Email address is a required attribute for User creation in Blackboard. If true then the following setting will be used to create the user's email address in Blackboard.

**Domain name to use for default email address:** Email address is a required attribute for a Person in Blackboard. This value will be used to set the email address attribute in Blackboard for users who do not have an email address specified in their eDirectory User object. The CN of the user will be used with the value provided to create the email address.

16 Click *Next*.

17 Review the summary of tasks that will be completed to create the driver, then click *Finish*.

18 After you have installed the driver, you must change the configuration for your environment. Proceed to [Configuring the Driver](#).

### 3.1.3 Configuring the Driver

After importing the driver configuration file, you need to configure the driver before it can run. Complete the following tasks to configure the driver:

- ♦ **Configure the driver parameters:** There are many settings that can help you customize and optimize the driver. The settings are divided into categories such as Driver Configuration, Engine Control Values, and Global Configuration Values (GCVs). Although it is important for you to understand all of the settings, your first priority should be to configure the driver parameters located on the Global Configuration Values page.

- ♦ **Configure the driver filter:** Modify the driver filter to include the object classes and attributes you want synchronized between the Identity Vault and Blackboard.
- ♦ **Configure Policies:** Modify the policies as needed.

---

**IMPORTANT:** Policies should only be modified using Designer or changes could be lost when a package is upgraded or the driver is run in “factory mode.”

---

For information about the default configuration policies, see [Appendix A, “Policies,”](#) on page 37.

- ♦ **Configure password synchronization:** The basic driver configuration is set up to support password synchronization through Universal Password. If you don’t want this setup, see “Configuring Password Flow ” in the *Identity Manager 4.0.2 Password Management Guide*.

After completing the configuration tasks, continue with the next section, [Deploying the Driver](#).

### 3.1.4 Deploying the Driver

After a driver is created in Designer, it must be deployed into the Identity Vault.

- 1 In Designer, open your project.
- 2 In the Modeler, right-click the driver icon or the driver line, then select *Live > Deploy*.
- 3 If you are authenticated to the Identity Vault, skip to Step 5; otherwise, specify the following information:
  - ♦ **Host:** Specify the IP address or DNS name of the server hosting the Identity Vault.
  - ♦ **Username:** Specify the DN of the user object used to authenticate to the Identity Vault.
  - ♦ **Password:** Specify the user’s password.
- 4 Click *OK*.
- 5 Read the deployment summary, then click *Deploy*.
- 6 Read the message, then click *OK*.
- 7 Click *Define Security Equivalence* to assign rights to the driver.

The driver requires rights to objects within the Identity Vault. The Admin user object is most often used to supply these rights. However, you might want to create a DriversUser (for example) and assign security equivalence to that user. Whatever rights that the driver needs to have on the server, the DriversUser object must have the same security rights.

**7a** Click *Add*, then browse to and select the object with the correct rights.

**7b** Click *OK* twice.

- 8 Click *Exclude Administrative Roles* to exclude users that should not be synchronized.

You should exclude any administrative User objects (for example, Admin and DriversUser) from synchronization.

**8a** Click *Add*, then browse to and select the user object you want to exclude.

**8b** Click *OK*.

**8c** Repeat Step 8a and 8b for each object you want to exclude.

**8d** Click *OK*.

### 3.1.5 Starting the Driver

When a driver is created, it is stopped by default. To make the driver work, you must start the driver and cause events to occur. Identity Manager is an event-driven system, so after the driver is started, it won't do anything until an event occurs.

To start the driver:

- 1 Make sure the Remote Loader driver instance is running:
  - ♦ **Windows:** Open the Remote Loader console on the driver's server, select the driver in the list, then click *Start*.
  - ♦ **Linux, AIX or Solaris:** At the server command line, enter:

```
/etc/init.d/rdxml start
```


- 2 In Designer, open your project.
- 3 In the Modeler, right-click the driver icon or the driver line, then select *Live > Start Driver*.

## 3.2 Creating the Driver in iManager (old method)

Since the Blackboard driver supports Identity Manager versions earlier than 4.0, you may need to create your driver using the XML import file rather than the driver packages. You accomplish this by importing the driver's basic configuration file and then modifying the configuration to suit your environment. After you've created and configured the driver, you need to start it.

- ♦ [Section 3.2.1, "Importing the Driver Configuration File," on page 24](#)
- ♦ [Section 3.2.2, "Configuring the Driver," on page 27](#)
- ♦ [Section 3.2.3, "Starting the Driver," on page 28](#)

### 3.2.1 Importing the Driver Configuration File

- 1 In iManager, click  to display the Identity Manager Administration page.
- 2 In the Administration list, click *Import Configuration* to launch the Import Configuration wizard.
- 3 Follow the wizard prompts, filling in the requested information (described below) until you reach the Summary page.

Prompt	Description
Where do you want to place the new driver?	You can add the driver to an existing driver set, or you can create a new driver set and add the driver to the new set. If you choose to create a new driver set, you are prompted to specify the name, context, and server for the driver set.
Import a configuration into this driver set	Use the default option, <i>Import a configuration from the server (.XML file)</i> .  In the <i>Show</i> field, select <i>Identity Manager 4.0.2 configurations</i> .  In the <i>Configurations</i> field, select the Blackboard file.
Driver name	Specify a name that is unique within the driver set.



Prompt	Description
Path to config file	Specify the path to the <code>bb-config.properties</code> file on the Blackboard server where you installed the remote loader. You MUST include a trailing slash.
Virtual Installation Host Name	Enter the host name of the virtual installation you want the driver to update. If you are using the default installation then leave this field blank.
Remote Host Name and Port	Specify the host name or IP address of the server where the driver's Remote Loader service is running.
Driver Object Password	Specify the driver object password that is defined in the Remote Loader service. The Remote Loader requires this password to authenticate to the Metadirectory server.
Remote Object Password	Specify the Remote Loader's password (as defined on the Remote Loader service). The Metadirectory engine (or Remote Loader shim) requires this password to authenticate to the Remote Loader.
Enable Entitlements	Do you want the driver to use Approval Flow or Role-Based Entitlements with the Entitlements Service driver?
Use scope filtering	Do you want to choose a base container in the Identity Vault for synchronization? If you choose Yes you will be prompted on the next screen for the base container.
<ul style="list-style-type: none"> <li>• Base Container in eDirectory</li> </ul>	Specify the base container in the Identity Vault for User synchronization. This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: <code>users.myorg</code>
<ul style="list-style-type: none"> <li>• Base Container in eDirectory</li> </ul>	Specify the base container in the Identity Vault for Group synchronization. This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: <code>groups.myorg</code>
Automatically set ID attribute	Do you want the driver to automatically set the required ID attribute for new Person, Course, and Organization objects to the source name of the object if the ID attribute is not already set? The attributes are <code>DirXML-BB-p-id</code> for Person, <code>DirXML-BB-c-id</code> for Course, and <code>DirXML-BB-o-id</code> for Organization.
Automatically set title attribute	Do you want the driver to automatically set the required title attribute for new Course and Organization objects to the source name of the object if the title attribute is not already set? The attributes are <code>DirXML-BB-c-course-title</code> for Course and <code>DirXML-BB-o-title</code> for Organization.
Automatically set role attribute	Do you want the driver to automatically set the required user roles attributes for Person objects if it is not already set? If you choose Yes you will be prompted on the next screen for the default roles.
Automatically set email address	Do you want the driver to automatically set required attribute <code>DirXML-BB-p-email</code> if it is not set? If you choose Yes you will be prompted for the default email address on the next screen.
Base Container in eDirectory	Enter the subtree where group objects will be treated as Courses in Blackboard.
Base Container in eDirectory	Enter the subtree where group objects will be treated as Organizations in Blackboard.

Prompt	Description
If you selected <i>Yes</i> for the <i>Enable Entitlements</i> option, this field option displays:	
The enrollment should be	Choose the action the driver should take on the user's enrollment (Disabled or Deleted) if a user loses the bbAccount Entitlement.
If you selected <i>Yes</i> for the <i>Use Scope Filtering</i> option, these field options display:	
Base Container in eDirectory	Specify the base container in the Identity Vault for User synchronization. This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: users.myorg
Base Container in eDirectory	Specify the base container in the Identity Vault for Group synchronization. This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. Example: groups.myorg
If you selected <i>Yes</i> for the <i>Automatically set roles attributes</i> option, these field options display:	
Default System Role for users	What should be the default System Role for new users?
Default Institution Role	What should be the default Institutional Role for new users? Examples: STUDENT, STAFF, ALUMNI, GUEST, FACULTY, OBSERVER, or any custom defined roles

When you finish providing the information required by the wizard, a Summary page similar to the following is displayed.

**Import Configuration**

Summary - Current Configuration

**Warning: Drivers May Require Configuration**

Drivers imported from a configuration file may require additional configuration settings to be fully functional. Select the driver's link to edit its configuration settings.

The following summarizes the state of the driver as it currently exists.

- [SLES10SP264-edir883](#) (NCP Server)
- [driverset](#) (Driver Set)
- [Blackboard](#) (Drivers May Require Configuration) (Driver)**
  - [OBNDBKBDDC-smp-SchemaMapping](#) (Schema Mapping Policy)
  - [OBNDBKBDDC-ipt-VetoPseudoEntitlementAssociation](#) (Input Transformation Policy)
  - [OBNDBKBDDC-otp-CheckRequiredAttrs](#) (Output Transformation Policy)
- [Publisher](#) (Publisher)
  - [none](#) (Command Transformation Policy)
  - [none](#) (Event Transformation Policy)
  - [none](#) (Matching Policy)
  - [none](#) (Creation Policy)
  - [none](#) (Placement Policy)
- [Subscriber](#) (Subscriber)
  - [OBNDBKBDDC-sub-ctp-EntitlementProcessing](#) (Command Transformation Policy)
  - [OBNDBKBDDC-sub-evt-VetoRenameEvents](#) (Event Transformation Policy)
  - [OBNDBKBDDC-sub-mp-SubscriberMatching](#) (Matching Policy)
  - [OBNDBKBDDC-sub-cp-SubscriberCreation](#) (Creation Policy)
  - [none](#) (Placement Policy)

javascript:handleNavigationPB( 'DWizPB\_Next' )

At this point, the driver is created from the basic configuration file. To ensure that the driver works the way you want it to for your environment, you must review and modify the driver's default configuration settings

- 4 To modify the default configuration settings, click the linked driver name, then continue with the next section, [Configuring the Driver](#).

or

To skip the configuration settings at this time, click Finish. When you are ready to configure the settings, continue with [Configuring the Driver](#).

## 3.2.2 Configuring the Driver

After importing the driver configuration file, you need to configure the driver before it can run. You should complete the following tasks to configure the driver:

- ♦ **Configure the driver parameters:** There are many settings that can help you customize and optimize the driver. The settings are divided into categories such as Driver Configuration, Engine Control Values, and Global Configuration Values (GCVs). Although it is important for you to understand all of the settings, your first priority should be to configure the driver parameters located on the Global Configuration Values page.
- ♦ **Configure the driver filter:** Modify the driver filter to include the object classes and attributes you want synchronized between the Identity Vault and Blackboard.

- ♦ **Configure Policies:** Modify the policies as needed. For information about the default configuration policies, see [Appendix A, “Policies,” on page 37](#).
- ♦ **Configure password synchronization:** The basic driver configuration is set up to support password synchronization through Universal Password. If you don't want this setup, see “Configuring Password Flow ” in the *Identity Manager 4.0.2 Password Management Guide*.

After completing the configuration tasks, continue with the next section, [Starting the Driver](#).


### 3.2.3 Starting the Driver

When a driver is created, it is stopped by default. To make the driver work, you must start the driver and cause events to occur. Identity Manager is an event-driven system, so after the driver is started, it won't do anything until an event occurs.

To start the driver:

- 1 If you are using the Remote Loader with the driver, make sure the Remote Loader driver instance is running:
  - ♦ **Windows:** Open the Remote Loader console on the driver's server, select the driver in the list, then click *Start*.
  - ♦ **Linux, AIX or Solaris:** Ensure the configuration file was copied to `/etc/opt/novell/dirxml/rdxml`, then enter the following at the server command line:

```
/etc/init.d/rdxml start
```

- 2 In iManager, click  to display the Identity Manager Administration page.
- 3 Click *Identity Manager Overview*.
- 4 Browse to and select the driver set object that contains the driver you want to start.
- 5 Click the driver set name to access the *Driver Set Overview* page.
- 6 Click the upper-right corner of the driver, then click *Start driver*.

## 3.3 Activating the Driver

If you created the driver in a driver set where you've already activated the Metadirectory engine and service drivers, the driver inherits the activation. If you created the driver in a driver set that has not been activated, you must activate the driver within 90 days. Otherwise, the driver stops working.

For information on activation, refer the *Identity Manager 4.0.2 Installation Guide* on the [Identity Manager 4.0.2 Documentation Site \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

---

# 4 Customizing the Driver

This section provides guidelines for customizing your driver to your specific business rules.

## 4.1 Attributes Required for Blackboard Object Creation

The Subscriber channel issues Blackboard API calls to process XDS commands received for objects and attributes represented in the Blackboard schema. It is up to the policy writer to ensure all required attributes are sent for Blackboard object creation. The sample policies can be configured on driver import or through global configuration values to ensure all required attributes are set on creation. The Blackboard API places restrictions on attribute values. It is up to the policy writer to ensure attributes mapped to Blackboard attributes contain values that conform to Blackboard attribute restrictions. The following tables list attributes required for Person, Course, Enrollment, and Organization creation in Blackboard. For information about restrictions on values for these attributes consult Blackboard documentation.

**Table 4-1** *Person Attributes Required For Creation*

<b>Blackboard Schema</b>	<b>Blackboard Attribute</b>
DirXML-BB-p-ext-key	EXTERNAL_PERSON_KEY
DirXML-BB-p-id	USER_ID
DirXML-BB-p-sys-role	SYSTEM_ROLE
DirXML-BB-p-firstname	FIRSTNAME
DirXML-BB-p-lastname	LASTNAME
DirXML-BB-p-email	EMAIL

**Table 4-2** *Course Attributes Required For Creation*

<b>Blackboard Schema</b>	<b>Blackboard Attribute</b>
DirXML-BB-c-id	COURSE_ID
DirXML-BB-c-ext-key	EXTERNAL_COURSE_KEY
DirXML-BB-c-course-title	COURSE_NAME

**Table 4-3** Organization Attributes Required For Creation

Blackboard Schema	Blackboard Attribute
DirXML-BB-o-id	ORGANIZATION_ID
DirXML-BB-o-ext-key	EXTERNAL_ORGANIZATION_KEY
DirXML-BB-o-title	ORGANIZATION_NAME

**Table 4-4** Course Enrollment Attributes Required For Creation

Blackboard Schema	Blackboard Attribute
DirXML-BB-enr-c-ext-key	EXTERNAL_COURSE_KEY
DirXML-BB-enr-p-ext-key	EXTERNAL_PERSON_KEY

**Table 4-5** Organization Enrollment Attributes Required For Creation

Blackboard Schema	Blackboard Attribute
DirXML-BB-enr-o-ext-key	EXTERNAL_ORGANIZATION_ID
DirXML-BB-enr-p-ext-key	EXTERNAL_PERSON_KEY

## 4.2 Attributes and Values for Blackboard Enumeration Types

The following tables list valid values for enumeration type attributes supported by the driver.

**Table 4-6** DirXML-BB-Course Enumeration Types And Valid Values

Enumeration Type Attribute	Valid Values	Description
DirXML-BB-c-duration-type	CONTINUOUS	Course is active on an ongoing basis.
	DATE_RANGE	Course is only intended to be available between specific date ranges.
	FIXED_NUM_DAYS	Course is only available for a set number of days.
DirXML-BB-c-enrollment-type	EMAIL_ENROLLMENT	Instructors have the ability to enroll users, and students can email requests to the instructor for enrollment.
	INSTRUCTOR_LED	Enrollment tasks for the course can only be performed by the instructor.
	SELF_ENROLLMENT	Instructors have the ability to enroll users, and students can also enroll themselves in the course.
DirXML-BB-c-pace	INSTRUCTOR_LED	Course is intended to be led by an instructor.
	SELF_PACED	Students use the course at their own speed.

**Table 4-7** DirXML-BB-Person Enumeration Types And Valid Values

Enumeration Type Attribute	Valid Values	Description
DirXML-BB-p-educ-level	FRESHMAN	College or university freshman.
	GRADUATE_SCHOOL	Graduate school student.
	HIGH_SCHOOL	Grades 9 through 12.
	JUNIOR	College or university junior.
	K_8	Kindergarten through 8th grade.
	POST_GRADUATE_SCHOOL	Post-graduate school student.
	SENIOR	College or university senior.
	SOPHOMORE	College or university sophomore.
	UNKNOWN	Education level is not known, or not specified.
DirXML-BB-p-gender	FEMALE	Female.
	MALE	Male.
	UNKNOWN	Gender is not known, or not specified.
DirXML-BB-p-sys-role	ACCOUNT_ADMIN	Account Administrator role.
	CARD_OFFICE_ADMIN	Manages the front-end settings (tabs, modules, etc.) for portal-ecommerce functionality.
	COURSE_CREATOR	Course Creator role.
	COURSE_SUPPORT	Course Support role.
	ECOMMERCE_ADMIN	Manages the back-end settings for portal-ecommerce functionality.
	GUEST	Guest role.
	INTEGRATION	This role is private, used only for special processes that interact for data integration authentication.
	NONE	No explicit role.
	OBSERVER	Observer role.
	PORTAL	Portal Administrator role.
	STORE_ADMIN	Manages the front-end portal-ecommerce functionality related to purchases.
	SYSTEM_ADMIN	System Administrator role.
	SYSTEM_SUPPORT	System Support role.
	USER	Normal user role.
	(User-defined system roles)	To set a user-defined system role, click the Blackboard <i>Administrator Panel</i> > <i>System Role</i> and select a Role ID.

**Table 4-8** DirXML-BB-Enrollment Enumeration Types And Valid Values

<b>Enumeration Type Attribute</b>	<b>Valid Values</b>	<b>Description</b>
DirXML-BB-enr-role	COURSE_BUILDER	The Course Builder role has access to most areas of the Control Panel. This role is appropriate for a user to manage the Course without having access to Student grades. A Course Builder can still access the Course if the Course is unavailable to Students. A Course Builder cannot delete an Instructor from a Course.
	GRADER	A Grader assists the Instructor in the creation, management, delivery, and grading of items, such as Tests and Discussion Board posts. A Grader also assists the Instructor with managing the Grade Center. A Grader cannot access a Course if it is unavailable to Students.
	GUEST	Guests have no access to the Control Panel. Areas within the Course are made available to Guests. Visitors, such as prospective Students, alumni, or parents may be given the role of Guest.
	INSTRUCTOR	Instructors have access to all areas in the Control Panel. This role is generally given to those developing, teaching, or facilitating the class. Instructors may access a Course that is unavailable to Students.
	NONE	No explicit Course role.
	STUDENT	Student is the default Course Role. Students have no access to the Control Panel.
	TEACHING_ASSISTANT	The Teaching Assistant role is that of a co-teacher. Teaching Assistants are able to administer all areas of a course. Their only limitations are those imposed by the Instructor or Blackboard administrator at your school. A Teaching Assistant cannot delete an Instructor from a Course.



---

# 5 Managing the Driver

As you work with the Blackboard driver, there are a variety of management tasks you might need to perform, including the following:

- ♦ Starting, stopping, and restarting the driver

---

**NOTE:** If the connectivity to the database server for Blackboard is lost, the driver shim must be restarted to re-establish communication with the Blackboard Application.

---

- ♦ Viewing driver version information
- ♦ Using Named Passwords to securely store passwords associated with the driver
- ♦ Monitoring the driver's health status
- ♦ Backing up the driver
- ♦ Inspecting the driver's cache files
- ♦ Viewing the driver's statistics
- ♦ Using the DirXML Command Line utility to perform management tasks through scripts
- ♦ Securing the driver and its information
- ♦ Synchronizing objects
- ♦ Migrating and resynchronizing data
- ♦ Activating the driver

Because these tasks, as well as several others, are common to all Identity Manager drivers, they are included in one reference, the *Identity Manager 4.0.2 Common Driver Administration Guide*, available at the [Identity Manager 4.0.2 Documentation page \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).



---

# 6 Troubleshooting the Driver

This section provides information about troubleshooting the Blackboard driver.

- ♦ [Section 6.1, “Viewing Driver Processes,” on page 35](#)
- ♦ [Section 6.2, “Troubleshooting Blackboard-Specific Items,” on page 35](#)

## 6.1 Viewing Driver Processes

Viewing driver processes is necessary to analyze unexpected behavior. To view the driver processing events, use DSTrace. You should only use it during testing and troubleshooting the driver. Running DSTrace while the drivers are in production increases the utilization on the Identity Manager server and can cause events to process very slowly.

For more information, see the *Identity Manager 4.0.2 Common Driver Administration Guide*, available at the [Identity Manager 4.0.2 Documentation page \(http://www.novell.com/documentation/idm402\)](http://www.novell.com/documentation/idm402).

## 6.2 Troubleshooting Blackboard-Specific Items

Following is a list of things to check when troubleshooting problems specific to Blackboard:

- ♦ Ensure the remote loader can make a connection to the Blackboard Application. Run the test script mentioned in [Section 2.4.6, “Testing Connectivity to Blackboard,” on page 18](#). If the test program fails ensure the following paths are set correctly in the test script and retry the tests:

```
# path to jre installed with the remote loader
RDXML_JRE=/opt/novell/eDirectory/lib/sparcv9/nds-modules/jre

# path to remote loader classes directory
DIRXML_LIB=/opt/novell/eDirectory/lib/dirxml/classes
```

- ♦ Ensure you have a valid license installed for the Blackboard application. Turn the trace level up to 10 in the driver remote loader configuration file and specify an output file for debug information:

```
-trace 10
-tracefile /tmp/bbtrace.log
```

- ♦ If you recently upgraded Blackboard, remember to copy all of the updated jar files to the correct location. See [Section 2.4.3, “Copying Blackboard Files to Remote Loader classpath,” on page 15](#).
- ♦ If the connectivity to the database server for Blackboard is lost, the driver must be restarted to re-establish communication with the Blackboard application.



---

# A Policies

This section provides information about Policies for the Blackboard driver.

- ♦ [Section A.1, “Event Transforms,” on page 37](#)
- ♦ [Section A.2, “Matching,” on page 37](#)
- ♦ [Section A.3, “Creation Policies,” on page 38](#)
- ♦ [Section A.4, “Command Transforms,” on page 39](#)
- ♦ [Section A.5, “Schema Mapping,” on page 39](#)
- ♦ [Section A.6, “Output Transforms,” on page 40](#)
- ♦ [Section A.7, “Input Transforms,” on page 41](#)

## A.1 Event Transforms

### **OBNDBKBDDC-sub-evt-VetoRenameEvents**

**Description:** Veto rename events.

### **OBNDBKBDDC-sub-evt-DetermineBBObjectType**

**Description:** Set an operation property name "BBObjectType" that helps map the operation to the type of Blackboard object. Group objects can represent Blackboard Courses or Organizations so it is necessary to specify which one should be used.

## A.2 Matching

### **OBNDBKBDDC-sub-mp-SubscriberMatching**

**Description:** Search for a matching Blackboard object based on the type of Blackboard object type set in the BBObjectType operation property. Refer to [Table A-1](#) for matching attributes.

**Table A-1** Matching Attributes

eDirectory Object Class	eDirectory Attribute	BObjectType	Blackboard Attribute
User	Source Name	DirXML-BB-Person	DirXML-BB-p-id
Group	Source Name	DirXML-BB-Course	DirXML-BB-c-id
Organization	Source Name	DirXML-BB-Organization	DirXML-BB-o-id
DirXML-BB-Enrollment*	DirXML-BB-c-ext-key, DirXML-BB-p-ext-key	DirXML-BB-Enrollment	DirXML-BB-c-ext-key, DirXML-BB-p-ext-key

\* The DirXML-BB-Enrollment class can represent objects using effective class DirXML-BB-Enrollment in eDirectory or can represent pseudo enrollment objects created in policy when using attributes on groups to represent enrollments. For more information see [Section 1.6.1, "Organization," on page 10](#).

## A.3 Creation Policies

### OBNDKBD-sub-cp-SubscriberCreation

**Description:** Check to see if required attributes are set for object creation in Blackboard. If not set and specified in the GCVs default values will be set for some of the required attributes. Refer to [Table A-2](#), [Table A-3](#) and [Table A-4](#) for required attributes.

**Table A-2** Required User Attributes (BObjectType operation property = DirXML-BB-Person)

Required User Attribute	Action
DirXML-BB-p-id	If not set and GCV auto_set_ids is true set to Source Name.
Internet Email Address	If not set and GCV auto_set_email is true set to CN + @ + GCV default_email_domain.
DirXML-BB-p-sys-role	If not set and GCV auto_set_roles is true set to value of GCV default_user_role.
DirXML-BB-p-portal-role	DirXML-BB-p-portal-roleIf not set and GCV auto_set_roles is true set to value of GCV default_portal_role.
DirXML-BB-p-ext-key	Set to Source Name with underscores replacing spaces.

**Table A-3** Required Group Attributes (BObjectType operation property = DirXML-BB-Course)

Required Group Attribute	Action
DirXML-BB-c-course-title	If not set and GCV auto_set_title is true then set value to Source Name.
DirXML-BB-c-id	If not set and GCV auto_set_ids is true then set value to Source Name.
DirXML-BB-c-ext-key	Set to Source Name with underscores replacing spaces.

**Table A-4** Required Organization Attributes (BBOBJECTType operation property = DirXML-BB-Organization)

Required Organization Attribute	Action
DirXML-BB-o-title	If not set and GCV auto_set_title is true then set value to Source Name.
DirXML-BB-o-id	If not set and GCV auto_set_ids is true then set value to Source Name.
DirXML-BB-o-ext-key	Set to Source Name with underscores replacing spaces.

## A.4 Command Transforms

### OBNDBKBDDC-ctp-TransformLoginDisabled

**Description:** Transform changes on user object attribute “Login Disabled” to Blackboard DirXML-BB-Person object attributes DirXML-BB-p-row-status and DirXML-BB-p-available-ind. Refer to [Table A-5](#) for attribute value settings.

**Table A-5** Attribute Values

Login Disabled	DirXML-BB-p-row-status	DirXML-BB-p-available-ind
True	ENABLED	True
False	ENABLED	False

### OBNDBKBDDC-ctp-SetClassnameForGroups

**Description:** Set the operation object class for groups to the Blackboard object class type based on the value in the BBOBJECTType operation property. BBOBJECTType is set in the OBNDBKBDDC-evt-DetermineBBOBJECTType policy. Group objects can represent a Blackboard Course or Organization so the object class determines which one the operation maps to.

### OBNDBKBDDC-sub-ctp-TransformGroupAttrsToEnrollmentObjects

**Description:** Transforms changes on Group attributes listed in the “attribute\_role\_map” GCV to DirXML-BB-Enrollment object events.

## A.5 Schema Mapping

### OBNDBKBDDC-smp-SchemaMapping

**Description:** Mapping contains some basic default mappings. Refer to [Table A-6](#) for attribute details.

**Table A-6** Object Mapping (eDirectory to BBOBJECTType operation property)

eDirectory Object Class	Blackboard Object Type
Group	DirXML-BB-Course
Description	DirXML-BB-c-description
Organization	DirXML-BB-Organization
Description	DirXML-BB-o-description
User	DirXML-BB-Person
Given Name	DirXML-BB-p-firstname
Internet Email Address	DirXML-BB-p-email
nspmDistributionPassword	DirXML-BB-p-password
Surname	DirXML-BB-p-lastname

## A.6 Output Transforms

### OBNDBKDDC-otp-CheckRequiredAttrs

**Description:** Ensure attributes required by Blackboard object types are set before sending document to the driver shim. Refer to [Table A-7](#) for required attributes.

**Table A-7** Attributes Required by Blackboard

Blackboard Object Type	Attribute Settings Required by Blackboard
DirXML-BB-Person	DirXML-BB-p-id DirXML-BB-p-firstname DirXML-BB-p-lastname DirXML-BB-p-sys-role DirXML-BB-p-portal-role DirXML-BB-p-email DirXML-BB-p-ext-key
DirXML-BB-Course	DirXML-BB-c-id DirXML-BB-c-ext-key DirXML-BB-c-course-title
DirXML-BB-Organization	DirXML-BB-o-id DirXML-BB-o-ext-key DirXML-BB-o-title
DirXML-BB-Enrollment	DirXML-BB-enr-p-ext-key DirXML-BB-enr-c-ext-key



## A.7 Input Transforms

### **OBNDKBDGBE-ipt-VetoPseudoEntitlementAssociation**

**Description:** When using group based enrollments no object exists in eDirectory that can hold an association for a corresponding Blackboard Enrollment Object. The driver shim returns a destination DN value of “pseudo-enrollment-object” if no source DN was present. This policy vetos add-association operations for pseudo-enrollment-objects.



---

# B Global Configuration Values

This section provides information about the Driver Configuration and Global Configuration Values properties for the Blackboard driver.

- ♦ [Section B.1, “General Settings,” on page 43](#)
- ♦ [Section B.2, “Default Required Attribute Settings,” on page 44](#)

## B.1 General Settings

**Table B-1** Global Configuration Values - General Settings

Name	Display Name	Description	Default Value
use_entitlements	Enable the driver to use Approval Flow or Role-Based Entitlements with the Entitlements Service driver.	na	na
use_scope_filtering	Limit the driver to a base container in the Identity Vault for synchronization?	Limit events the driver processes to a base container in eDirectory	True
container_scope_filter_user	Specify the base container in the Identity Vault for User synchronization.	This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. For example: [users.myorg]	na
container_scope_filter_group	Specify the base container in the Identity Vault for Group synchronization.	This container is used in the Subscriber channel Event Transformation policies to limit the Identity Vault objects being synchronized. For example: [groups.myorg]	System
disable_or_delete_enrollments	What action should be taken on an enrollment when a Person is removed from a Group?	If set to Delete enrollments dropped from a Group will result in the Person being removed from the Course or Organization. If set to Disable the Person's enrollment will be disabled in the Course or Organization.	Delete

## B.2 Default Required Attribute Settings

**Table B-2** Global Configuration Values - Default Required Settings on New Blackboard Objects

Name	Display Name	Description	Default Value
auto_set_ids	Automatically set the required Id attribute for new Person, Course, and Organization objects to the source name of the object.	If true then the required id attribute for Person, Course, and Organization types in Blackboard will be automatically set to Source Name if the id attribute is not already set. The attributes are DirXML-BB-p-id for Person, DirXML-BB-c-id for Course, and DirXML-BB-o-id for Organization.	True
auto_set_title	Automatically set the required title attribute for new Course, and Organization objects to the source name of the Group.	Automatically set required attribute DirXML-bb-c-course-title to the source name for Course objects if it is not already set. Automatically set required attribute DirXML-bb-o-title to source name for Organization objects.	True
auto_set_roles	Automatically set the required user roles attributes for Person objects.	If true the default roles chosen below will be set for a user if they are not present on the user object.	True
default_user_role	Default System Role for new users	na	USER
default_portal_role	Default Institutional Role for new users.  Example: STUDENT, STAFF, ALUMNI, GUEST, FACULTY, OBSERVER, or any custom defined roles	na	STUDENT
add_aux_classes	Automatically add a required Blackboard auxiliary class to Person and Course or Organization objects.	If true automatically add the DirXML-BB-Person auxiliary class to Person objects and the DirXML-BB-Course auxiliary class to Course or Organization objects.	True
bb-course-subtree	Apply DirXML-BB-Course to groups in the following subtree	na	na
bb-organization-subtree	Apply DirXML-BB-Organization to groups in the following subtree.	na	na

Name	Display Name	Description	Default Value
auto_set_email	Automatically set required Person attribute DirXML-BB-p-email if it is not set.	na	True
default_email_domain	Domain name to use for default email address.	Email address is a required attribute for a Person in Blackboard. This value will be used to set the email address attribute in Blackboard for users who do not have an email address specified in their eDirectory User object. The CN of the user will be used with the value provided to create the email address.	na



---

# C Test Scripts

This section provides test scripts for the Blackboard driver, as well as an example of the results to expect from running them.

- [Section C.1, “Test Scripts,” on page 47](#)
- [Section C.2, “Expected Results,” on page 49](#)

## C.1 Test Scripts

Following are test scripts for each supported operating system.

- [Section C.1.1, “Linux Test Script,” on page 47](#)
- [Section C.1.2, “UNIX Test Script,” on page 48](#)
- [Section C.1.3, “Windows Test Script,” on page 48](#)

### C.1.1 Linux Test Script

```
Linux
-----
#!/bin/sh
# Blackboard Driver Test Script
#
# Usage: bbdriver_tester [path to blackboard config dir] [hostname] [optional
#       cleanup Y/N]
#
# path to blackboard config dir = location of bb-config.properties file
# hostname = virtual installation name (set to localhost for default virtual
#       installation)
# optional cleanup = If Y then remove test objects after running test.  If N
#       then leave test objects in Blackboard.
#
# path to jre installed with the remote loader
RDXML_JRE=/opt/novell/eDirectory/lib64/nds-modules/jre
# path to remote loader classes directory
DIRXML_LIB=/opt/novell/eDirectory/lib/dirxml/classes

CLASSPATH=$DIRXML_LIB/xercesImpl.jar:$DIRXML_LIB/
          Blackboard.jar:$DIRXML_LIB:$DIRXML_LIB/*

echo "Blackboard Driver Installation Tester"
echo ""
echo "Using java: $RDXML_JRE/bin/java"
$RDXML_JRE/bin/java -version
echo ""
echo "Starting test.."

$RDXML_JRE/bin/java -classpath $CLASSPATH
                    com.Omnibond.nds.dirxml.driver.Blackboard.Tester $*
```

## C.1.2 UNIX Test Script

```
Solaris
-----
#!/bin/sh
# Blackboard Driver Test Script
#
# Usage: bbdriver_tester [path to blackboard config dir] [hostname]
#       [optional cleanup Y/N]
#
# path to blackboard config dir = location of bb-config.properties file
# hostname = virtual installation name (set to localhost for default virtual
# installation)
# optional cleanup = If Y then remove test objects after running test.  If N
# then leave test objects in Blackboard.
#
# path to jre installed with the remote loader
RDXML_JRE=/opt/novell/eDirectory/lib/sparcv9/nds-modules/jre
#
# path to remote loader classes directory
DIRXML_LIB=/opt/novell/eDirectory/lib/dirxml/classes
#
CLASSPATH=$DIRXML_LIB/xercesImpl.jar:$DIRXML_LIB/
          Blackboard.jar:$DIRXML_LIB:$DIRXML_LIB/*
#
echo "Blackboard Driver Installation Tester"
echo ""
echo "Using java: $RDXML_JRE/bin/java"
$RDXML_JRE/bin/java -version
echo ""
echo "Starting test.."
$RDXML_JRE/bin/java -classpath $CLASSPATH
                    com.Omnibond.nds.dirxml.driver.Blackboard.Tester $*
```

## C.1.3 Windows Test Script

```
Windows
-----
@echo off
rem Blackboard Driver Test Script
rem
rem Usage: bbdriver_tester [path to blackboard config dir] [hostname]
rem       [optional cleanup Y/N]
rem
rem path to blackboard config dir = location of bb-config.properties file
rem hostname = virtual installation name (set to localhost for default
rem virtual installation)
rem optional cleanup = If Y then remove test objects after running test.
rem If N then leave test objects in Blackboard.
#
rem path to jre installed with the remote loader
set RDXML_JRE=\novell\remoteloader\jre
#
rem path to remote loader classes directory
```



```

set RDXML_LIB=\novell\remoteloader\lib

set CP=%RDXML_LIB%\xercesimpl.jar;%RDXML_LIB%\Blackboard.jar;%
RDXML_LIB%;%RDXML_LIB%\*

echo "Blackboard Driver Installation Tester"
echo.
echo "Using java: %RDXML_JRE%\bin\java"
"%RDXML_JRE%\bin\java" -version
echo.
echo "Starting test.."

"%RDXML_JRE%\bin\java" -cp %CP%
com.Omnibond.nds.dirxml.driver.Blackboard.Tester %1 %2 %3

```

## C.2 Expected Results

A successful test run should resemble the following example:

```

[root@bb2 blackboard]# ./bbdriver_test_linux /usr/local/blackboard/
config localhost Y
Blackboard Driver Installation Tester

Using java: /opt/novell/eDirectory/lib64/nds-modules/jre/bin/java
java version "1.6.0_20"
Java(TM) SE Runtime Environment (build 1.6.0_20-b02)
Java HotSpot(TM) 64-Bit Server VM (build 16.3-b01, mixed mode)

Starting test..
Initializing Blackboard API..
Testing Person Attributes
Passed - DirXML-BB-p-datasource
Passed - DirXML-BB-p-ext-key
Passed - DirXML-BB-p-id
Passed - DirXML-BB-p-sys-role
Passed - DirXML-BB-p-portal-role
Passed - DirXML-BB-p-row-status
Passed - DirXML-BB-p-company
Passed - DirXML-BB-p-firstname
Passed - DirXML-BB-p-middlename
Passed - DirXML-BB-p-lastname
Passed - DirXML-BB-p-student-id
Passed - DirXML-BB-p-email
Passed - DirXML-BB-p-street1
Passed - DirXML-BB-p-street2
Passed - DirXML-BB-p-gender
Passed - DirXML-BB-p-birthdate
Passed - DirXML-BB-p-title
Passed - DirXML-BB-p-city
Passed - DirXML-BB-p-state
Passed - DirXML-BB-p-zip-code
Passed - DirXML-BB-p-department
Passed - DirXML-BB-p-country
Passed - DirXML-BB-p-bphone1
Passed - DirXML-BB-p-bphone2
Passed - DirXML-BB-p-bfax
Passed - DirXML-BB-p-hfax
Passed - DirXML-BB-p-hphone1
Passed - DirXML-BB-p-hphone2
Passed - DirXML-BB-p-mphone
Passed - DirXML-BB-p-job-title
Passed - DirXML-BB-p-educ-level
Passed - DirXML-BB-p-webpage
Passed - DirXML-BB-p-locale
Passed - DirXML-BB-p-cardnumber
Passed - DirXML-BB-p-public-ind
Passed - DirXML-BB-p-available-ind

```

Passed - DirXML-BB-p-address-ind  
Passed - DirXML-BB-p-phone-ind  
Passed - DirXML-BB-p-email-ind  
Passed - DirXML-BB-p-work-ind

#### Testing Course Attributes

Passed - DirXML-BB-c-datasource  
Passed - DirXML-BB-c-id  
Passed - DirXML-BB-c-ext-key  
Passed - DirXML-BB-c-course-title  
Passed - DirXML-BB-c-inst-name  
Passed - DirXML-BB-c-fee  
Passed - DirXML-BB-c-locale-enforced  
Passed - DirXML-BB-c-description  
Passed - DirXML-BB-c-start-date  
Passed - DirXML-BB-c-end-date  
Passed - DirXML-BB-c-enroll-start-date  
Passed - DirXML-BB-c-enroll-end-date  
Passed - DirXML-BB-c-row-status  
Passed - DirXML-BB-c-pace  
Passed - DirXML-BB-c-enrollment-type  
Passed - DirXML-BB-c-allow-guest-ind  
Passed - DirXML-BB-c-available-ind  
Passed - DirXML-BB-c-catalog-ind  
Passed - DirXML-BB-c-desc-page  
Passed - DirXML-BB-c-lockout-ind  
Passed - DirXML-BB-c-abs-limit  
Passed - DirXML-BB-c-soft-limit  
Passed - DirXML-BB-c-upload-limit  
Passed - DirXML-BB-c-days-of-use  
Passed - DirXML-BB-c-enr-access-code  
Passed - DirXML-BB-c-locale  
Passed - DirXML-BB-c-duration-type

#### Testing Organization Attributes

Passed - DirXML-BB-o-datasource  
Passed - DirXML-BB-o-id  
Passed - DirXML-BB-o-ext-key  
Passed - DirXML-BB-o-title  
Passed - DirXML-BB-o-inst-name  
Passed - DirXML-BB-o-description  
Passed - DirXML-BB-o-allow-guest-ind  
Passed - DirXML-BB-o-available-ind  
Passed - DirXML-BB-o-catalog-ind  
Passed - DirXML-BB-o-desc-page  
Passed - DirXML-BB-o-lockout-ind  
Passed - DirXML-BB-o-locale-enforced  
Passed - DirXML-BB-o-abs-limit  
Passed - DirXML-BB-o-soft-limit  
Passed - DirXML-BB-o-upload-limit  
Passed - DirXML-BB-o-days-of-use  
Passed - DirXML-BB-o-fee  
Passed - DirXML-BB-o-enr-access-code  
Passed - DirXML-BB-o-locale  
Passed - DirXML-BB-o-start-date  
Passed - DirXML-BB-o-end-date  
Passed - DirXML-BB-o-enroll-start-date

Passed - DirXML-BB-o-enroll-end-date  
Passed - DirXML-BB-o-row-status  
Passed - DirXML-BB-o-pace  
Passed - DirXML-BB-o-enrollment-type  
Passed - DirXML-BB-o-duration-type

Testing Enrollment Attributes

Passed - DirXML-BB-enr-c-ext-key  
Passed - DirXML-BB-enr-p-ext-key  
Passed - DirXML-BB-enr-role  
Passed - DirXML-BB-enr-datasource  
Passed - DirXML-BB-enr-row-status  
Disconnected from Blackboard  
Test Complete

