



# SQL Views Guide

Operations Center 5.6

June 2015

## Legal Notices

THIS DOCUMENT AND THE SOFTWARE DESCRIBED IN THIS DOCUMENT ARE FURNISHED UNDER AND ARE SUBJECT TO THE TERMS OF A LICENSE AGREEMENT OR A NON-DISCLOSURE AGREEMENT. EXCEPT AS EXPRESSLY SET FORTH IN SUCH LICENSE AGREEMENT OR NON-DISCLOSURE AGREEMENT, NETIQ CORPORATION PROVIDES THIS DOCUMENT AND THE SOFTWARE DESCRIBED IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. SOME STATES DO NOT ALLOW DISCLAIMERS OF EXPRESS OR IMPLIED WARRANTIES IN CERTAIN TRANSACTIONS; THEREFORE, THIS STATEMENT MAY NOT APPLY TO YOU.

For purposes of clarity, any module, adapter or other similar material ("Module") is licensed under the terms and conditions of the End User License Agreement for the applicable version of the NetIQ product or software to which it relates or interoperates with, and by accessing, copying or using a Module you agree to be bound by such terms. If you do not agree to the terms of the End User License Agreement you are not authorized to use, access or copy a Module and you must destroy all copies of the Module and contact NetIQ for further instructions.

This document and the software described in this document may not be lent, sold, or given away without the prior written permission of NetIQ Corporation, except as otherwise permitted by law. Except as expressly set forth in such license agreement or non-disclosure agreement, no part of this document or the software described in this document may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, or otherwise, without the prior written consent of NetIQ Corporation. Some companies, names, and data in this document are used for illustration purposes and may not represent real companies, individuals, or data.

This document could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein. These changes may be incorporated in new editions of this document. NetIQ Corporation may make improvements in or changes to the software described in this document at any time.

U.S. Government Restricted Rights: If the software and documentation are being acquired by or on behalf of the U.S. Government or by a U.S. Government prime contractor or subcontractor (at any tier), in accordance with 48 C.F.R. 227.7202-4 (for Department of Defense (DOD) acquisitions) and 48 C.F.R. 2.101 and 12.212 (for non-DOD acquisitions), the government's rights in the software and documentation, including its rights to use, modify, reproduce, release, perform, display or disclose the software or documentation, will be subject in all respects to the commercial license rights and restrictions provided in the license agreement.

**© 2015 NetIQ Corporation. All Rights Reserved.**

For information about NetIQ trademarks, see <https://www.netiq.com/company/legal/> (<https://www.netiq.com/company/legal/>).

All third-party trademarks are the property of their respective owners.

---

# Contents

<b>About This Guide</b>	<b>5</b>
<b>1 About SQL Views</b>	<b>7</b>
<b>2 Configuration</b>	<b>9</b>
2.1 Prerequisites	9
2.2 Configuring the ODBC Driver	9
2.2.1 Defining an ODBC Data Source for Windows	10
2.2.2 Setting Up an ODBC Data Source for UNIX	13
2.2.3 Reconfiguring the Command Line Driver	13
2.2.4 Defining Character Encoding for Windows Clients in International Environments	14
2.3 JDBC Driver Requirements	14
2.4 Verifying SQL Views Status	15
2.5 Auditing SQL Views	16
<b>3 Queries and Reports</b>	<b>17</b>
3.1 Using Excel for Queries and Reports	18
3.2 Using Crystal Reports for Queries and Reports	20
<b>4 Tables and Views</b>	<b>25</b>
4.1 Using Tables	25
4.1.1 Agreement Table	26
4.1.2 Alarms Table	26
4.1.3 AlarmsConstructed Table	27
4.1.4 AlarmsNamed Table	29
4.1.5 Availability Table	30
4.1.6 Breaches Table	32
4.1.7 Condition Table	33
4.1.8 Elements Table	34
4.1.9 Health Table	34
4.1.10 Outages Table	35
4.1.11 Performance Table	36
4.1.12 Properties Table	37
4.1.13 PropertiesConstructed Table	38
4.1.14 PropertiesNamed Table	38
4.1.15 Relationships Table	39
4.2 Using System Views	39
4.3 Creating Views in the Operations Center console	40
4.3.1 Editing a View	41
4.3.2 Creating a New View	41
4.3.3 Deleting Views	42
4.4 Creating Custom Views	43
4.4.1 Testing Mossqclcli	43
4.4.2 Creating a View using Mossqclcli	44
4.5 Writing Custom Queries	44

<b>5</b>	<b>Example Reports</b>	<b>47</b>
5.1	Alarms Reports . . . . .	48
5.2	Performance Reports . . . . .	49
5.3	SLA Catalog Reports . . . . .	50
5.4	SLA Availability Reports . . . . .	51
5.4.1	Understanding Availability and Downtime . . . . .	52
5.4.2	Creating an Availability Report . . . . .	53
5.5	Service Catalog Changes Report . . . . .	53

---

# About This Guide

The *SQL Views Guide* provides functionality in Operations Center that allows for third-party applications to have read access to Operations Center data.

- ♦ [Chapter 1, “About SQL Views,” on page 7](#)
- ♦ [Chapter 2, “Configuration,” on page 9](#)
- ♦ [Chapter 3, “Queries and Reports,” on page 17](#)
- ♦ [Chapter 4, “Tables and Views,” on page 25](#)
- ♦ [Chapter 5, “Example Reports,” on page 47](#)

## Audience

This guide is intended for Operations Center system administrators.

## Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the *User Comments* feature at the bottom of each page of the online documentation.

## Additional Documentation & Documentation Updates

This guide is part of the Operations Center documentation set. For the most recent version of the *SQL Views Guide* and a complete list of publications supporting Operations Center, visit our Online Documentation Web Site at [Operations Center 5.6 online documentation](#).

The Operations Center documentation set is also available as PDF files on the installation CD or ISO; and is delivered as part of the online help accessible from multiple locations in Operations Center depending on the product component.

## Additional Resources

We encourage you to use the following additional resources on the Web:

- ♦ [NetIQ User Community \(https://www.netiq.com/communities/\)](https://www.netiq.com/communities/): A Web-based community with a variety of discussion topics.
- ♦ [NetIQ Support Knowledgebase \(https://www.netiq.com/support/kb/?product%5B%5D=Operations\\_Center\)](https://www.netiq.com/support/kb/?product%5B%5D=Operations_Center): A collection of in-depth technical articles.
- ♦ [NetIQ Support Forums \(https://forums.netiq.com/forumdisplay.php?26-Operations-Center\)](https://forums.netiq.com/forumdisplay.php?26-Operations-Center): A Web location where product users can discuss NetIQ product functionality and advice with other product users.

## Technical Support

You can learn more about the policies and procedures of NetIQ Technical Support by accessing its [Technical Support Guide \(https://www.netiq.com/Support/process.asp#\\_Maintenance\\_Programs\\_and\)](https://www.netiq.com/Support/process.asp#_Maintenance_Programs_and).

Use these resources for support specific to Operations Center:

- ◆ Telephone in Canada and the United States: 1-800-858-4000
- ◆ Telephone outside the United States: 1-801-861-4000
- ◆ E-mail: [support@netiq.com](mailto:support@netiq.com) ([support@netiq.com](mailto:support@netiq.com))
- ◆ Submit a Service Request: <http://support.novell.com/contact/> (<http://support.novell.com/contact/>)

## Documentation Conventions

A greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path. The > symbol is also used to connect consecutive links in an element tree structure where you can either click a plus symbol (+) or double-click the elements to expand them.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a forward slash to preserve case considerations in the UNIX\* or Linux\* operating systems.

A trademark symbol (®, ™, etc.) denotes a NetIQ trademark. An asterisk (\*) denotes a third-party trademark.

---

# 1 About SQL Views

Operations Center SQL Views provides functionality in Operations Center that allows for third-party applications to have read access to Operations Center data. The purpose of SQL Views is to take data from the Operations Center server and the Service Warehouse and make it accessible for you to query it and write reports using it. External products, such as Business Objects Crystal Reports or Microsoft Excel can be used to create reports. In addition to reporting, Operations Center data can also be used by other applications for other business purposes.

The Operations Center server contains real-time data feeds from external management systems and the Service Warehouse contains historical data, such as alarms, Service Level Agreement data, and performance data.

The foundation of SQL Views is Apache Derby, which is a relational database implemented entirely in Java. This database is embedded in the Operations Center server. For more information on Apache Derby, see [www.db.apache.org](http://www.db.apache.org).

To use SQL Views, do the following:

1. Obtain a license that allows access to both Operations Center SQL Views and the Operations Center Web Services Application Interface.
2. Configure SQL Views.
3. Connect a third party reporting tool to SQL Views.
4. Write queries and create reports using the reporting tool.

The data in SQL Views is surfaced using views. Operations Center ships with some existing system views. You can create additional views to use to create your reports.

The other sections in this guide explain each step in detail and describe how to create new views. In addition, examples of reports that you can create are included in [Chapter 5, "Example Reports," on page 47](#).

In order to explain how to use SQL Views, this guide includes step-by-step instructions and illustrations from other products that are not associated with Operations Center, including Microsoft Excel and Business Objects Crystal Reports. These instructions and illustrations can vary, depending on the version of the product being used. Consult the documentation for the product for additional information.





---

# 2 Configuration

To use SQL Views, you must configure it so it can be connected to a reporting tool. After SQL Views is configured, you can verify its status and set audit options in the Operations Center console.

- ♦ [Section 2.1, “Prerequisites,” on page 9](#)
- ♦ [Section 2.2, “Configuring the ODBC Driver,” on page 9](#)
- ♦ [Section 2.3, “JDBC Driver Requirements,” on page 14](#)
- ♦ [Section 2.4, “Verifying SQL Views Status,” on page 15](#)
- ♦ [Section 2.5, “Auditing SQL Views,” on page 16](#)

## 2.1 Prerequisites

SQL Views is automatically installed during the installation of Operations Center. To use SQL Views, the following requirements must be met:

- ♦ The Operations Center server must be up and running.
- ♦ SQL Views is installed with the default port of 1560. However, this port might be changed in the Configuration Manager.

Configuration settings are generally set at the time Operations Center is installed. If another port is used, you must specify it in order to connect to SQL Views. For more information, see the [Operations Center 5.6 Server Installation Guide](#).

- ♦ For an external reporting tool to connect to Operations Center, one of the following requirements must be met, depending on the tool used:
  - ♦ An ODBC driver for reporting tools that do not have native support for JDBC  
This includes most Windows reporting tools. After an ODBC driver is installed, an ODBC data source must be defined.  
For information on ODBC drivers, see [Section 2.2, “Configuring the ODBC Driver,” on page 9](#).
  - ♦ A JDBC driver for access to Java applications that have native support for JDBC  
For information on JDBC drivers, see [Section 2.3, “JDBC Driver Requirements,” on page 14](#).

## 2.2 Configuring the ODBC Driver

An ODBC driver is required to connect SQL Views on the Operations Center server to any external reporting tool that does not have native support for JDBC. This includes most Windows reporting tools (such as Business Objects Crystal Reports, Microsoft Excel, and so on).

An Open Database Connectivity (ODBC) driver is a standard database access method. It is used to access any data from any application, regardless of the database management system (DBMS) that handles the data. It translates application data queries into commands understood by the DBMS.

At the time of the release of Operations Center 5.6, no free 64-bit Windows ODBC drivers were compatible with SQL Views. If your reporting solution requires an ODBC connection to SQL Views, you can evaluate the IBM JDBC/ODBC driver, but there are reliability issues with the driver for SQL Views on 32-bit Windows operating systems and it does not work with 64-bit Windows operating systems. Some third parties have drivers that seem to work available for a fee.

The ODBC client driver for DB2 (Version 9 or lower) from IBM works with SQL Views. The ODBC driver for DB2 from IBM can be downloaded from the [IBM Web site \(http://www-01.ibm.com/support/docview.wss?uid=swg21363866\)](http://www-01.ibm.com/support/docview.wss?uid=swg21363866).

The ODBC client driver from IBM does not work with Apache Derby. To use an ODBC driver with Apache Derby, you must purchase a proprietary driver from another vendor. You can use a JDBC driver with Apache Derby.


After the driver has been installed, you must define an ODBC data source in either Windows or UNIX.

- ♦ [Section 2.2.1, “Defining an ODBC Data Source for Windows,” on page 10](#)
- ♦ [Section 2.2.2, “Setting Up an ODBC Data Source for UNIX,” on page 13](#)
- ♦ [Section 2.2.3, “Reconfiguring the Command Line Driver,” on page 13](#)
- ♦ [Section 2.2.4, “Defining Character Encoding for Windows Clients in International Environments,” on page 14](#)

## 2.2.1 Defining an ODBC Data Source for Windows


To define an ODBC Data Source for Windows:

- 1 To open the ODBC Data Source Administrator, click *Start > Control Panel > Administrative Tools > ODBC Data Source Administrator*.




- 2 Click *Add* to open the Create New Data Source dialog box.
- 3 Select *IBM DB2 ODBC Driver* from the list, then click *Finish* to open the ODBC IBM DB2 Driver – Add dialog box.

- 4 In the *Data Source Name* field, enter `MOSQL`.



Leave the *Database Alias* field empty.


- 5 Click *Add* next to the *Database Alias* field to open the CLI/ODBC Settings dialog box.  
If *Add* does not display, then you could have a different version of the DB2 driver. These instructions are based on version 8.2.4. Earlier versions might require configuring SQL using the IBM DB2 Configuration Assistant or the command line interface.
- 6 Enter the user name for a user account with admin privileges in the *User ID* field and the corresponding password in the *Password* field.
- 7 Select the *Save Password* check box.



A warning dialog box opens, indicating that the password is stored in an unsecured location.


- 8 Click *OK* to close the warning dialog box.
- 9 Click the *TCP/IP* tab.
- 10 In the *Database Name* and *Database Alias* fields, enter `mosql`.
- 11 In the *Host name* field, specify the host name of the Operations Center server.  
If configuring remote client access, specify the client machine name instead of `localhost`.

- 12 Enter the port number for SQL Views.



The default value is 1560. This port number is set in the Configuration Manager. For more information, see the [Operations Center 5.6 Server Installation Guide](#).

- 13 Click the *Security Options* tab:



- 14 Select the *Specify the Security Options* check box.
- 15 Select the *Server Authentication (SERVER)* option.
- 16 Click *OK*.

The ODBC Data Source Administrator dialog box displays MOSQL, which represents the database alias.

## 2.2.2 Setting Up an ODBC Data Source for UNIX

To set up the database source on UNIX, use the DB2 command prompt.

The general set up process involves setting up a database and node in the DB2 database catalog. This involves running the DB2 command prompt and setting up the proper aliases in the DB2 driver database. To catalog the SQL database, run the DB2 command prompt.

The following commands use the database name `mosql` and the node name `fnode`:

```
db2 => catalog tcpip node fnode remote localhost server 1527
DB20000I The CATALOG TCP/IP NODE command completed successfully.
DB21056W Directory changes may not be effective until the directory cache is
refreshed.
```

```
db2 => catalog db mosql at node fnode authentication server
DB20000I The CATALOG DATABASE command completed successfully.
DB21056W Directory changes may not be effective until the directory cache is
refreshed.
```

```
db2 => connect to mosql user admin using formula
Database Connection Information
Database server      = Server_Name
SQL authorization ID = FNODE
Local database alias = MOSQL
```

If you are using other names for the database and node, change the commands accordingly.

## 2.2.3 Reconfiguring the Command Line Driver

After reinstalling Operations Center, it is sometimes necessary to reconfigure the command line driver. Use the following commands to uncatalog the database and node in DB2. The examples use a database name `mosql` and a node name `fnode`. If necessary, replace these with the names used in your system.

To reconfigure the driver:

- 1 Open the ODBC Data Source Administrator and delete the SQL Views ODBC configuration.
- 2 Go to the DB2 command prompt and enter the `Uncatalog db mosql` command:

```
db2 => uncatalog db mosql
DB20000I The UNCATALOG DATABASE command completed successfully.
DB21056W Directory changes may not be effective until the directory cache is
refreshed.
```

- 3 Enter the `Uncatalog fnode` command:

```
db2 => uncatalog node fnode
DB20000I The UNCATALOG NODE command completed successfully.
DB21056W Directory changes may not be effective until the directory cache is
refreshed.
```

- 4 Use the ODBC Data Source Administrator to reconfigure SQL Views.

## 2.2.4 Defining Character Encoding for Windows Clients in International Environments

Client programs, such as MS Excel, might error out because of character encoding issues while accessing SQL Views on computers that are configured for non-western regional languages.

To force the ODBC drivers to use UTF character encoding:

- 1 Set the environment variable `DB2CODEPAGE` to `1208` on the client side machine.  
This forces the IBM DB2 ODBC driver to use UTF character encoding.
- 2 Restart the client program interfacing with SQL Views (such as MS-Excel) after setting the environment variable.
- 3 If restarting the client program does not work, reboot the machine for the client programs to pick up the environment variable change.

## 2.3 JDBC Driver Requirements

A JDBC driver is necessary for Java applications that have native JDBC support to access SQL Views. Java Database Connectivity (JDBC) is an API for the Java programming language that defines how a client can access a database. It provides methods for querying and updating data in a database.

Defining the JDBC access mode for Java applications involves installing `derbyclient.jar` to the target program's classpath. Each database tool handles this differently. The class for the JDBC driver is: `org.apache.derby.jdbc.ClientDriver`.

The URL is:

```
jdbc:derby://host:port/database_name_and_credentials
```


A sample URL is:

```
jdbc:derby://localhost:1560/MOSQL;user=formula;password=formula;
```

For more information, consult your documentation for the JDBC drivers.

## 2.4 Verifying SQL Views Status

- 1 In the Operations Center console, expand *Enterprise > Administration > SQL Views*.
- 2 Right-click the *SQL Views* element, then select *Properties > Status* to display:



- 3 Verify that condition of *SQL Views* is the same as the condition of other elements in Operations Center.


For more information about condition, see [“Understanding Element Condition”](#) in the *Operations Center 5.6 User Guide*.

## 2.5 Auditing SQL Views

You can audit the events impacting SQL Views. You can audit when operations are started and stopped, and when views are created and dropped.

To access the audit options:

- 1 In the Operations Center console, expand *Enterprise > Administration > SQL Views*.
- 2 Right-click the *SQL Views* element, then select *Properties > Audit* to display:



- 3 For more information about auditing, particularly how to use the global options and how to view audited events, see the [Operations Center 5.6 Security Management Guide](#).



---

# 3 Queries and Reports

After you are connected to SQL Views, you can use any third-party reporting tools, such as Microsoft Excel and Business Objects Crystal Reports, to make reports and charts using data from Operations Center. SQL Views uses views to make data accessible to these tools.

Some basic instructions are included here to get you started using Excel or Crystal Reports to build reports. For more information, consult the documentation for these products.

To create reports, you might need to enter some SQL statements. It is your responsibility to ensure the SQL statement syntax is correct. For example, when using Excel, it is necessary to manually enter the statement. Otherwise, Excel enters column names without enclosing them in parentheses, which results in invalid statement because the dot (.) is a keyword. An example of the correct syntax for such a column name is:

```
.CI.HARDWARE.CPU.MODEL
```

With regard to SQL statements, SQL Views accepts the following two time stamp formats. These formats are required for specifying the start time and end time of a historical query.

```
yyyy-MM-dd-HH.mm.ss  
Example: 2006-05-01-00.00.00
```

```
yyyy-MM-dd HH:mm:ss  
Example: 2006-05-01 00:00:00
```


The following sections review how to integrate Operations Center data into reports via Excel or Crystal Reports:

- ◆ [Section 3.1, “Using Excel for Queries and Reports,” on page 18](#)
- ◆ [Section 3.2, “Using Crystal Reports for Queries and Reports,” on page 20](#)

## 3.1 Using Excel for Queries and Reports


Microsoft Excel is a commonly used application that can extract external data using its Import wizard. This section explains how to extract data from SQL Views using Excel. Sample reports are available in `/OperationsCenter_install_path/database/examples/mosql`.

**Figure 3-1** Data from SQL Views formatted in Microsoft Excel




To extract data from SQL Views into Excel:

- 1 Launch Microsoft Excel.
- 2 Click *Data > Import External Data*, then select *New Database Query* to open the Choose Data Source dialog box:



- 3 Select *MOSQL*, then click *OK* to open the Query Wizard – Choose Columns dialog box:




- 4 Select the tables and columns for your query, then click *Next*.

The remaining wizard pages are standard Excel dialogs. For information on these features, see your Microsoft Excel documentation.

## 3.2 Using Crystal Reports for Queries and Reports


Business Objects Crystal Reports is a popular application that allows you to use data from another source to create reports and charts. This section explains how to extract data from SQL Views using Crystal Reports. Sample reports are available in `/OperationsCenter_install_path/database/examples/mosql`.

**Figure 3-2** Data from SQL Views formatted in Crystal Reports




To extract data from SQL Views to Crystal Reports:


- 1 Launch Crystal Reports.
- 2 Click *Start* and select a blank report to display the Database Expert:



- 3 In the *Available Data Sources* list, expand *Create New Connection*:



- 4 Click *DB2 Unicode* to open the connection dialog box:



The screenshot shows a dialog box titled "DB2 Unicode" with a close button in the top right corner. Below the title bar, the text "Connection" is displayed, followed by the instruction "Please enter connection information ...". The dialog contains four input fields: "Database:" with a dropdown menu showing "MOSQL"; "User ID:" with a text box containing "admin"; "Password:" with a text box containing seven dots; and "OS Authentication:" with an unchecked checkbox. At the bottom of the dialog, there are five buttons: "< Back", "Next >", "Finish", "Cancel", and "Help".

- 5 Fill in the fields:

**Database:** Enter MOSQL.


**User ID:** Enter admin.

**Password:** Enter formula.


- 6 Click *Finish*.

The MOSQL database is connected and displays under *DB2 Unicode*.

7 Click *MOSQL* and all the views display in the *Available Data Sources* list:




8 In the *Available Data Sources* list, select the views to use, then click the > button:



9 Click OK.

The selected views are imported into Crystal Reports:



10 Use the Crystal Reports features to enhance the final report.

For more information, see your Crystal Reports documentation.



---

# 4 Tables and Views

SQL Views uses views to make data stored in tables accessible for creating reports using third-party reporting tools. There are two types of views:

- ♦ **Predefined:** Called system views that ship with Operations Center
- ♦ **Custom:** views that you create

You can create views from a single table in the Operations Center console or you can use a third-party tool, such as Apache Derby to create views from multiple tables.

System views extract data only one level deep in the *Operations Center* hierarchy.

You can also write custom queries that extract data directly from the tables.

- ♦ [Section 4.1, “Using Tables,” on page 25](#)
- ♦ [Section 4.2, “Using System Views,” on page 39](#)
- ♦ [Section 4.3, “Creating Views in the Operations Center console,” on page 40](#)
- ♦ [Section 4.4, “Creating Custom Views,” on page 43](#)
- ♦ [Section 4.5, “Writing Custom Queries,” on page 44](#)

## 4.1 Using Tables

The system views and any views you create are based on the following tables:

- ♦ [Section 4.1.1, “Agreement Table,” on page 26](#)
- ♦ [Section 4.1.2, “Alarms Table,” on page 26](#)
- ♦ [Section 4.1.3, “AlarmsConstructed Table,” on page 27](#)
- ♦ [Section 4.1.4, “AlarmsNamed Table,” on page 29](#)
- ♦ [Section 4.1.5, “Availability Table,” on page 30](#)
- ♦ [Section 4.1.6, “Breaches Table,” on page 32](#)
- ♦ [Section 4.1.7, “Condition Table,” on page 33](#)
- ♦ [Section 4.1.8, “Elements Table,” on page 34](#)
- ♦ [Section 4.1.9, “Health Table,” on page 34](#)
- ♦ [Section 4.1.10, “Outages Table,” on page 35](#)
- ♦ [Section 4.1.11, “Performance Table,” on page 36](#)
- ♦ [Section 4.1.12, “Properties Table,” on page 37](#)
- ♦ [Section 4.1.13, “PropertiesConstructed Table,” on page 38](#)
- ♦ [Section 4.1.14, “PropertiesNamed Table,” on page 38](#)
- ♦ [Section 4.1.15, “Relationships Table,” on page 39](#)

## 4.1.1 Agreement Table

The Agreement Table displays a definition of each agreement and objective for every element, starting with the children for which the view was created. Its constraints are:

- ♦ **Depth:** The number of element levels to traverse.

Default value is 1. Specify `ALL` to traverse all levels.

Table 4-1 explains the Agreement Table's columns.

*Table 4-1 Agreement Table Columns*

name=	Required In Where=	nullable=	length	JDBC Type=
AGREEMENT	false	true	1024	VARCHAR
CALENDAR	false	true	512	VARCHAR
AGREEMENTDESCRIPTION	false	true	1024	VARCHAR
OBJECTIVE	false	true	1024	VARCHAR
OBJDEFINITION	false	true	1024	VARCHAR
ELEMENT	false	true	1024	VARCHAR
ELEMENT_NAME	false	true	1024	VARCHAR
ELEMENT_ID	false	false	0	INTEGER

## 4.1.2 Alarms Table

The Alarms Table displays a row for each alarm for the element for which the view was created. It includes default columns and additional columns in semicolon delimited format or XML. You cannot configure the columns. The type of alarm is specified by a constraint. The constraints are:

- ♦ **Alarm Type:** The alarm type:
- ♦ **Alarms:** Historical and real-time element alarms.
- ♦ **Audit Events:** Historical and real-time audit alarms.
- ♦ **Outages:** Historical element outages. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Service Level Breaches:** Historical agreement breaches generated by the real-time BSLM engine. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Service Level Metrics:** Real-time agreement metrics. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Change Events:** Alarms indicating a change in the element. For more information, see the [Operations Center 5.6 Version Tracking Guide](#).

- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to define a specific time period for pruning the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

Table 4-2 explains the Alarm Table's columns.

Table 4-2 Alarms Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
START_TIME	false	true	0	TIMESTAMP
END_TIME	false	true	0	TIMESTAMP
ELEMENT	false	true	1024	VARCHAR
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
ID	false	true	0	INTEGER
SEVERITY	false	true	512	VARCHAR
LASTUPDATE	false	true	0	TIMESTAMP
DATA	false	true	0x1000000	LONGVARCHAR
XMLDATA	false	true	0x1000000	LONGVARCHAR

### 4.1.3 AlarmsConstructed Table

The AlarmsConstructed Table displays a row for each alarm for the element for which the view was created. You can define a custom set of columns and add *EMS* (external management system) as a searchable column. For example, to search for alarms generated from an external management system called ALPHA, you would add *EMS* as a column and *ALPHA* as a value and then use the following query:

```
select * from MOSQL.EVE_NAMED_ALARMS where EMS='ALPHA'
```

The type of alarm is specified by a constraint. A constraint determines which columns display. The constraints are:

- ♦ **Columns:** The columns to display. The syntax for identifying columns is:

Name:name, Type:type, Nullable:Yes|No, Size:size\_in\_bytes

For example:

Name:LASTUPDATE, Type:Timestamp, Nullable:false, Size:1024

- ♦ **Alarm Type:** The alarm type:
- ♦ **Alarms:** Historical and real-time element alarms.
- ♦ **Audit Events:** Historical and real-time audit alarms.
- ♦ **Outages:** Historical element outages.
- ♦ **Service Level Breaches:** Historical agreement breaches.
- ♦ **Service Level Metrics:** Real-time agreement metrics.
- ♦ **Change Events:** Alarms indicating a change in the element. For more information, see the [Operations Center 5.6 Version Tracking Guide](#).
- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Setting a *Report Time Period* of *None* only queries real-time alarms. Setting the *Report Time Period* to any other value queries the warehouse alarm history and bounds the query according to the configuration of the warehouse alarm history.

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to define a specific time period for pruning the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

[Table 4-3](#) explains the `AlarmsConstructed` Table's columns.

**Table 4-3** *AlarmsConstructed* Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
DNAME	false	true	1024	VARCHAR
SEVERITY	false	true	512	VARCHAR
ID	false	true	0	INTEGER
Class	false	true	512	VARCHAR

Specific information is available in Operations Center from external applications via adapters. To include this information, you must add the following columns:

**Table 4-4** *Information from External Applications via Adapters*

Column Name	Name=	nullable=	length	JDBC Type=
NAME	NAME	false	1024	VARCHAR
STATUS	Status	false	1024	VARCHAR
CLASS	Class	false	1024	VARCHAR
DESCRIPTION	Description	false	1024	VARCHAR

*NAME* corresponds to the element name displayed in the Operations Center console, and *STATUS*, *CLASS*, and *DESCRIPTION* contain values that originate from external applications.

## 4.1.4 AlarmsNamed Table

The AlarmsNamed Table displays a row for each alarm column for the element for which the view was created. The type of alarm is specified by a constraint. The table contains default columns in addition to *NAME* and *VALUE* columns for specifying additional alarm columns. The *NAME* column is the name of the alarm field. The *VALUE* column is the value of the alarm field. You cannot configure the columns. The constraints are:

- ♦ **Alarm Type:** The alarm type:
- ♦ **Alarms:** Historical and real-time element alarms.
- ♦ **Audit Events:** Historical and real-time audit alarms.
- ♦ **Outages:** Historical element outages. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Service Level Breaches:** Historical agreement breaches generated by the real-time BSLM engine. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Service Level Metrics:** Real-time agreement metrics. For more information, see the [Operations Center 5.6 Service Level Agreement Guide](#).
- ♦ **Change Events:** Alarms indicating a change in the element. For more information, see the [Operations Center 5.6 Version Tracking Guide](#).
- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to define a specific time period for pruning the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

[Table 4-5](#) explains the AlarmsNamed Table's columns.

**Table 4-5** AlarmsNamed Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
START_TIME	false	true	0	TIMESTAMP
END_TIME	false	true	0	TIMESTAMP
ELEMENT	false	true	1024	VARCHAR
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
ID	false	true	0	INTEGER

name=	required In Where=	nullable=	length	JDBC Type=
SEVERITY	false	true	512	VARCHAR
LASTUPDATE	false	true	0	TIMESTAMP
NAME	false	true	1024	VARCHAR
VALUE	false	true	1024	VARCHAR

## 4.1.5 Availability Table

The Availability Table displays a row of data for each time period (such as Minute, Hour, Day, and so on) The row contains historical availability data and outage data. The constraints are:

- ♦ **Calendar:** The calendar used in determining data relevance. The default is Default calendar, which is On 24x7.
- ♦ **Time Categories:** The time categories used in determining data relevance. This is a comma-separated list (such as On, Off, or Peak). The default is On. For example, if the specified calendar includes On and Blackout times, then outages that occur in Blackout times are excluded from the results based on the default setting to include *On* time categories.
- ♦ **Time Zone:** The time zone used in determining the result set. The default is America/New York.
- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to define a specific time period for pruning the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ♦ **Reporting Interval:** The interval or level of granularity to display the data. By default this constraint uses the overall report time period. For example, if the report time period is Last Month and days are specified as the reporting interval, a row is generated for each day in the month.
- ♦ **Display Sub-Elements Values:** Select this option to display a data row for each child element.

Table 4-6 explains the Availability Table's columns.

**Table 4-6** Availability Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
START_TIME	false	true	0	TIMESTAMP

name=	required In Where=	nullable=	length	JDBC Type=
END_TIME	false	true	0	TIMESTAMP
DNAME	false	true	1024	VARCHAR
AVAILABILITY	false	true	0	DOUBLE
DOWNTIME	false	true	0	BIGINT
OUTAGES	false	true	0	INTEGER
OUTAGES_CONTINUING	false	true	0	INTEGER
OUTAGES_INITIATED	false	true	0	INTEGER
RELEVANCE	false	true	0	DOUBLE
DISCONTINUITY	false	true	0	DOUBLE
AGREEMENT	false	true	1024	VARCHAR
OBJECTIVE	false	true	1024	VARCHAR

The following explain the *Downtime*, *Availability*, and *Discontinuity* column values:

- ◆ *Downtime* and *Availability* are determined based on element condition data.
- ◆ *Downtime* is recorded in milliseconds.
- ◆ *Availability* is calculated based on the total time within the report time period. For example, if you request availability for the month of January, the total possible time is the number of milliseconds from Jan 1, 12:00 AM until Feb 1, 12:00 AM. *Availability* is determined by the formula: (total time in period minus total downtime in period) divide by total time in period. The *Availability* value is between 0 and 1, where 1 = 100%. By default, an element is available when its state is anything other than `CRITICAL`. The *Calendar* and *Time Categories* specified are used to determine when system outages are relevant to the calculated *Availability*, *Downtime*, and *Outage* results. Only those system outages that occur during time windows of the *Calendar* that reference the included *Time Categories* are included in the calculated results. For example, outages that occur during a scheduled maintenance period are not included in the results if the *Blackout* time category is not specified as included in the view.

When *Agreement* and *Objective* are specified as part of the *Where* clause in the query, *Availability* is calculated using the SLA and Objective definitions to determine the total time window.

- ◆ *Discontinuity* is the time recorded when the system does not record any condition data. This might occur because of manually stopping an adapter, the Operations Center server, or a profile, or if the Operations Center server or a management system feed goes down unexpectedly. It is not known if the element was available during these times. By default, the BSLM engine calculates availability by assuming that there was no outage during these times.
- ◆ *Agreement* and *Objective* columns are not saved values, but allow Agreement and Objective definitions to be applied in the *Availability* calculation. *Agreement* and *Objective* are displayed as `null` unless defined as part of the query. These columns are optional in the SQL query.

For more detailed information, see the [Operations Center 5.6 Service Level Agreement Guide](#).

## 4.1.6 Breaches Table

The Breaches Table displays a row of data for each breach in the time period (such as Minute, Hour, Day, and so on) The row contains historical breaches. The constraints are:

- ♦ **Calendar:** The calendar used in determining data relevance. The default is Default calendar.
- ♦ **Time Categories:** The time categories used in determining data relevance. This is a comma-separated list (such as On, Off, or Peak). The default is On. For example, if the specified calendar includes On and Blackout times, then outages that occur in Blackout times are excluded from the results based on the default setting to include *On* time categories.
- ♦ **Time Zone:** The time zone used in determining the result set. The default is America/New York.
- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to further prune the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ♦ **Reporting Interval:** The interval or level of granularity to display the data. By default this constraint uses the overall report time period. For example, if the report time period is Last Month and days are specified as the reporting interval, a row is generated for each day in the month.

Table 4-7 explains the Breaches Table's columns.

*Table 4-7 Breaches Table Columns*

name=	required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
AGREEMENT	true	false	1024	VARCHAR
OBJECTIVE	false	true	1024	VARCHAR
START_TIME	false	true	0	TIMESTAMP
END_TIME	false	true	0	TIMESTAMP
DNAME	false	true	1024	VARCHAR
DATE	false	true	0	TIMESTAMP
SEVERITY	false	true	512	VARCHAR
STATUS	false	true	1024	VARCHAR
KEYMETRIC	false	true	0	DOUBLE



name=	required In Where=	nullable=	length	JDBC Type=
APPLIEDAGREEMENT	false	true	1024	VARCHAR
REASON	false	true	1024	VARCHAR
PERSISTENTID	false	true	1024	VARCHAR

This table requires specifying AGREEMENT in the SQL query as part of the where clause. It also optionally accepts OBJECTIVE as part of the where clause.

## 4.1.7 Condition Table

The Condition Table displays historical condition data. Each row represents the condition of the element at the specified data. The constraints are:

- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to further prune the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ♦ **Display Sub-Elements Values:** Select this option to display a data row for each child element.

[Table 4-8](#) explains the Condition Table's columns.

**Table 4-8** Condition Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
DNAME	false	true	1024	VARCHAR
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
TIME	true	true	0	TIMESTAMP
TYPE	false	true	1024	VARCHAR
SVALUE	false	true	1024	VARCHAR
DVALUE	false	true	0	DOUBLE

## 4.1.8 Elements Table

The Elements Table displays a real-time list of all elements, starting at the children of the element for which the view was created. The constraints are:

- ◆ **Depth:** The number of element levels to traverse. Default value is 1. Specify All to traverse all levels.

Table 4-9 explains the Elements Table's columns.

Table 4-9 Elements Table Columns

name=	required In Where=	nullable=	length	JDBC Type=
NAME	true	true	512	VARCHAR
DNAME	false	true	512	VARCHAR
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
CLASSNAME	false	true	512	VARCHAR
CONDITION	false	true	512	VARCHAR
ID	true	true	0	INTEGER
PARENT	false	true	0	INTEGER
LASTUPDATE	false	true	0	TIMESTAMP

## 4.1.9 Health Table

The Health Table displays a row of data for each time period (such as Minute, Hour, Day, and so on) The row contains historical agreement health data. The constraints are:

- ◆ **Calendar:** The calendar used in determining data relevance. The default is Default calendar.
- ◆ **Time Categories:** The time categories used in determining data relevance. This is a comma-separated list (such as On, Off, or Peak). The default is On. For example, if the specified calendar includes On and Blackout times, then outages that occur in Blackout times are excluded from the results based on the default setting to include *On* time categories.
- ◆ **Time Zone:** The time zone used in determining the result set. The default is America/New York.
- ◆ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to further prune the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ♦ **Reporting Interval:** The interval or level of granularity to display the data. By default this constraint uses the overall report time period. For example, if the report time period is Last Month and days are specified as the reporting interval, a row is generated for each day in the month.
- ♦ **Display Sub-Elements Values:** Select this option to display a data row for each child element.
- ♦ **Calculate Health Using Objective Interval:** Select this option to evaluate health and key metric values based on the time intervals defined by the objective definition, and not those selected in the report settings.
- ♦ **Show Key Metric As Percentage:** Select this option to display the inverse value of the key metric.

Table 4-10 explains the Health Table's columns.

**Table 4-10** Health Table Columns

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
AGREEMENT	true	false	1024	VARCHAR
OBJECTIVE	false	true	1024	VARCHAR
DNAME	false	true	1024	VARCHAR
START_TIME	false	true	0	TIMESTAMP
END_TIME	false	true	0	TIMESTAMP
HEALTH	false	false	0	DOUBLE
KEYMETRIC	false	true	0	DOUBLE
GRADE	false	false	256	VARCHAR
RELEVANCE	false	false	0	DOUBLE
BREACHES	false	true	0	INTEGER
DISCONTINUITY	false	false	0	DOUBLE

This table requires specifying AGREEMENT in the SQL query as a where clause. It also accepts OBJECTIVE as a where clause.

## 4.1.10 Outages Table

The Outages Table displays a row of data for outage in each time period (such as Minute, Hour, Day, and so on) The row contains historical outages. The constraints are:

- ♦ **Calendar:** The calendar used in determining data relevance. The default is Default calendar.
- ♦ **Time Categories:** The time categories used in determining data relevance. This is a comma-separated list (such as On, Off, or Peak). The default is On. For example, if the specified calendar includes On and Blackout times, then outages that occur in Blackout times are excluded from the results based on the default setting to include *On* time categories.
- ♦ **Time Zone:** The time zone used in determining the result set. The default is America/New York.

- ♦ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no data exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to further prune the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ♦ **Reporting Interval:** The interval or level of granularity to display the data. By default this constraint uses the overall report time period. For example, if the report time period is Last Month and days are specified as the reporting interval, a row is generated for each day in the month.

Table 4-11 explains the Outages Table's columns.

**Table 4-11** Outages Table Columns

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
DNAME	false	true	1024	VARCHAR
START_TIME	false	true	0	TIMESTAMP
END_TIME	false	true	0	TIMESTAMP
OUTAGE_START	false	true	0	TIMESTAMP
OUTAGE_END	false	true	0	TIMESTAMP
DURATION	false	false	0	DOUBLE
DESCRIPTION	false	true	1024	VARCHAR
PERSISTENTID	false	true	1024	VARCHAR

## 4.1.11 Performance Table

Queries against the Performance table must contain a valid performance Profile name and Expression name defined in the Operations Center server. If the names are not included in the query as part of the where clause, then the query returns an error. For example:

```
select * from PERFORMANCE_VIEW where Profile = 'Router Performance' and Expression = 'Condition Counts'
```

The Performance Table displays a list of profile and expression performance data. The constraints are:

- ◆ **Report Time Period:** For historical tables, enables creating a single view that can be reused on a regular basis to produce a standard interval of data without having to edit the view and specify the start and end dates. The valid values are:

Last Year, Last Quarter, Last Month, Last Week, Yesterday, Last Hour, This Year, This Quarter, This Month, This Week, Today, This Hour, None

Ensure that data exists for the time period queried. If no exists for the time period, no results are returned. Use the *Start\_Time* and *End\_Time* columns to further prune the result set. One of the following time formats must be specified:

yyyy-MM-dd-HH.mm.ss For example: 2012-05-01-00.00.00

yyyy-MM-dd HH:mm:ss For example: 2012-05-01 00:00:00

The first format uses periods and hyphens where the other format uses colons and spaces.

- ◆ **Display Sub-Elements Values:** Select this option to display a data row for each child element.

Table 4-12 explains the Performance Table's columns.

**Table 4-12** Performance Table Columns

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
DNAME	false	true	1024	VARCHAR
PROFILE	true	false	1024	VARCHAR
EXPRESSION	true	false	1024	VARCHAR
TIME	true	false	0	TIMESTAMP
VALUE	false	false	0	DOUBLE
DISCONTINUITY	false	false	0	BIT

## 4.1.12 Properties Table

The Properties Table displays a list of real-time properties for all elements, starting with the children of the element for which the view was created. The constraints are:

- ◆ **Depth:** The number of element levels to traverse. Default value is 1. Specify All to traverse all levels.

Table 4-13 explains the Properties Table's columns.

**Table 4-13** Properties Table Columns

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_NAME	false	true	1024	VARCHAR
DNAME	false	true	1024	VARCHAR
DATA	false	true	0x1000000	LONGVARCHAR
XMLDATA	false	true	0x1000000	LONGVARCHAR

### 4.1.13 PropertiesConstructed Table

The PropertiesConstructed Table displays a list of real-time properties for all elements, starting with the children of the element for which the view was created. This table displays columns based on the table constraint. The constraints are:

- ◆ **Columns:** The columns to display. The syntax for identifying columns is:

Name:*name*, Type:*type*, Nullable:Yes|No, Size:*size\_in\_bytes*

For example:

Name:LASTUPDATE,Type:Timestamp, Nullable:false,Size:1024

- ◆ **Depth:** The number of element levels to traverse. Default value is 1. Specify All to traverse all levels.

The PropertiesConstructed Table's columns are user-defined.

### 4.1.14 PropertiesNamed Table

The PropertiesNamed Table displays a list of real-time properties for all elements, starting with the children of the element for which the view was created. Each property is specified in a single row. The *NAME* column specifies the property name. The *VALUE* column specifies the property value. The constraints are:

- ◆ **Depth:** The number of element levels to traverse. Default value is 1. Specify All to traverse all levels.

Table 4-14 explains the PropertiesNamed Table's columns.

**Table 4-14** PropertiesNamed Table Columns

name=	Required In Where=	nullable=	length	JDBC Type=
ELEMENT_ID	false	false	0	INTEGER
ELEMENT_NAME	false	true	1024	VARCHAR
DNAME	false	true	1024	VARCHAR
NAME	true	true	512	VARCHAR
VALUE	false	true	1024	VARCHAR

## 4.1.15 Relationships Table

The Relationships Table displays a real-time list of all relationships for every element, starting with the children of the element for which the view was created. The constraints are:

- ♦ **Depth:** The number of element levels to traverse. Default value is 1. Specify All to traverse all levels.

[Table 4-15](#) explains the Relationships Table's columns.

*Table 4-15 Relationships Table Columns*

name=	Required In Where=	nullable=	length	JDBC Type=
LEFTID	false	true	0	INTEGER
RIGHTID	false	true	0	INTEGER
NAME	false	true	512	VARCHAR

LEFTID represents the parent and RIGHTID represents the child in the relationship.

## 4.2 Using System Views

SQL Views ships with some predefined views, called system views. System views extract data only one level deep (the element and the child immediately beneath it) in the *Operations Center* hierarchy.

These views can not be modified, but they can be used to create new views. Each view has the following components:

- ♦ **Table:** The database table accessed by the view.
- ♦ **Element:** The element (and its children) where the view applies.
- ♦ **Constraints:** The data in the table that determines data relevance. For example, a specific alarm type (Alarms, Breaches) or time category constraint can affect data query selection. The list of constraints depends on the selected table.

All system views start with `SYSTEM_`. The default values for each system view are listed in [Table 4-16](#).

*Table 4-16 System Views*

View Name	Element	Table	Constraint Name	Constraint Value
ELEMENTS_ALARMS	Alarms	Alarms	Alarm Type Report Time Period	Alarms None
ELEMENTS_ELEMENTS	Elements	Elements	Depth	1
ELEMENTS_PROPERTIES	Elements	Properties	Depth	1
ELEMENTS_RELATIONSHIPS	Elements	Relationships	Depth	1
ENTERPRISE_ELEMENTS	Enterprise	Elements	Depth	1
ENTERPRISE_PROPERTIES	Enterprise	Properties	Depth	1

View Name	Element	Table	Constraint Name	Constraint Value
ENTERPRISE_RELATIONSHIPS	Enterprise	Relationships	Depth	1
SERVICEMODELS_ALARMS	Service Models	Alarms	Alarm Type Report Time Period	Alarms None
SERVICEMODELS_ELEMENTS	Service Models	Elements	Depth	1
SERVICEMODELS_PROPERTIES	Service Models	Properties	Depth	1
SERVICEMODELS_RELATIONSHIPS	Service Models	Relationships	Depth	1
SERVICEMODELS_SLAS	Service Models	Agreement	Depth	1

To manage these views:

- 1 In the *Explorer* pane of the Operations Center console, expand *Administration > SQL Views*.
- 2 To edit the properties of an existing view, right-click the name of the view, then select *Properties*.
- 3 On the Properties page, select *View*.

## 4.3 Creating Views in the Operations Center console

You can create your own views in the Operations Center console that select data from a single table. This view only extracts data only one level deep (the element and the child immediately beneath it) in the *Operations Center* hierarchy.

The Operations Center console contains functionality for viewing and editing existing views, as well as creating, copying, editing, and deleting views.

The iSQL Viewer in the MOSDB utility only allows you to view the data in SQL Views. This utility is not intended for use with SQL Views.


The following sections cover creating and maintaining views:

- ♦ [Section 4.3.1, “Editing a View,” on page 41](#)
- ♦ [Section 4.3.2, “Creating a New View,” on page 41](#)
- ♦ [Section 4.3.3, “Deleting Views,” on page 42](#)



## 4.3.1 Editing a View

- 1 In the Operations Center console, expand *Enterprise > Administration > SQL Views*.
- 2 Right-click the desired view, select *Properties*, then select *View* in the Properties dialog box.



- 3 Edit the view as required.

## 4.3.2 Creating a New View

To create a new view, you have two options:

- ♦ Copy an existing view and modify it.
- ♦ Create a new view from scratch.

You cannot rename or modify system views, such as views that are named *SYSTEM\_*. However, you can copy a system view and rename the copy.


- ♦ [“Copying a View and Renaming It” on page 41](#)
- ♦ [“Creating a New View from Scratch” on page 42](#)

### Copying a View and Renaming It

- 1 Right-click a view, then select *Copy*.  
The view is copied to the Clipboard.
- 2 Right-click the *SQL Views* element, then select *Paste*.  
A copy of the view name is appended with *\_COPY* and placed under the *SQL Views* element.
- 3 Right-click the view, then select *Rename* to open the Rename dialog box.
- 4 Specify the new name, then click *OK*.  
The renamed view displays in the *Explorer* pane.

## Creating a New View from Scratch

- 1 In the *Explorer* pane, right-click *SQL Views*, then select *Create View*:



- 2 Fill in the fields:

**Table:** Select the database table to query.

**Element:** (Required) Click *Browse* to open the *Browse for Element* dialog box, then select the element (and its children) where the view applies.

**Constraints:** Select the *Enabled* check box next to data that should determine data relevance. For example, a specific alarm type (*Alarms*, *Breaches*) or time category can affect data query selection. The list of constraints depends on the selected table. For more information, see [Section 4.1, “Using Tables,” on page 25](#).

- 3 Click *Create*.

A message displays in the *Status* box stating that the view was successfully created. The new view displays under *SQL Views* in the *Operations Center* hierarchy.

### 4.3.3 Deleting Views

You can only delete views that you create. You cannot delete system views, whose names begin with *SYSTEM\_*; these views ship with *Operations Center*. If you delete a view that is referenced by a report, then the report no longer works.

- ♦ [“Deleting a View” on page 42](#)
- ♦ [“Deleting Multiple Views” on page 43](#)

#### Deleting a View

- 1 Right-click a view, then select *Delete View* to display a confirmation dialog box.
- 2 Click *Yes* to delete the view.

## Deleting Multiple Views

- 1 Right-click the *SQL Views* element, then select *Manage Views* to open the Manage Views dialog box.
- 2 Use Shift+click or Ctrl+click to select multiple views.
- 3 Click *Delete* to delete the views.

A message displays in the *Status* dialog box saying that the views were successfully deleted.

## 4.4 Creating Custom Views

Using the *Mossqcli* tool, you can create custom views that use more complex queries to include multiple tables. Views can even be combined to form more complex views. You can then use third-party tools to query just a single view to create reports.

- ♦ [Section 4.4.1, “Testing Mossqcli,” on page 43](#)
- ♦ [Section 4.4.2, “Creating a View using Mossqcli,” on page 44](#)

### 4.4.1 Testing Mossqcli

*Mossqcli* is based on Apache Derby *ij*, a third-party tool, which is installed with SQL Views. For information on how to use Derby *ij* and for a tutorial on the Apache Derby Web site, see [http://db.apache.org/derby/integrate/plugin\\_help/ij\\_toc.html](http://db.apache.org/derby/integrate/plugin_help/ij_toc.html).

The following is a possible test query:

```
select * from MOSQL.SYSTEM_SERVICEMODELS_ELEMENTS;
```

If *mossqcli* has not been installed, you can install it.

- ♦ [“Testing that Mossqcli was Installed Properly” on page 43](#)
- ♦ [“Installing Mossqcli” on page 43](#)

### Testing that Mossqcli was Installed Properly

- 1 Run `mossqcli`.

The following should display:

```
Usage: mossqcli username password [host:port]
The port shown is the port for Managed Object SQL; the default is 1560.
```

- 2 Run the file again with valid arguments.
- 3 Verify a connection to SQL Views.

The Operations Center server and SQL Views must be running.

### Installing Mossqcli

- 1 Install the latest patch bundle from Operations Center.  
For more information, contact [Technical Support](#).
- 2 Run the Operations Center Configuration Manager (such as `customizer`).
- 3 Verify that a new `bin` file called `mossqcli` (Unix) or `mossqcli.bat` (Windows) exists.

## 4.4.2 Creating a View using Mossqcli

You can use mossqcli to create a custom view based on one or more tables. For example, to create a view called `MOSQL_One` containing the data from the system view called `SYSTEM_ELEMENTS_ELEMENTS`, which contains one record, you enter the following code:

```
create view MOSQLONE as select * from MOSQL.SYSTEM_SERVICEMODELS_ELEMENTS;
```

Mossqcli returns the following:

```
0 rows inserted/updated/deteled
```

To see the contents of the view, enter the following code:

```
select * from MOSQLONE;
```

Mossqcli returns the following:

```
NAME
      | DNAME
      | CLASSNAME
      | CONDITION          | ID          | PARENT          | LASTUPDATE
-----|-----|-----|-----|-----
Adapter: NOC Demonstration Adapter
      | demoMgr=Adapter%3A+NOC+Demonstration+Adapter/root=Elements
      | demoMgr
      | CRITICAL          | 1206626208 | 1206624715 | 2008-04-04 14:00:14.102
1 row selected
```

You can use the SQL Views syntax to write more complex queries to create more complex views, also.

## 4.5 Writing Custom Queries

SQL Views uses views to make data accessible for use in reports. Views are used for two reasons:

- ♦ The SQL dialect for SQL Views is slightly different than standard SQL  
The definition of a view causes the altered SQL syntax to be hidden from the third party reporting tool or java application.
- ♦ The definition of a view causes the database metadata to report a view in the database catalog

You can query the tables to either use the results for a custom view or in a report; the query must use SQL Views. The following is a sample query:

```
SELECT
    EL1.NAME AS "Service Name",
    EL1.CLASSNAME AS "Service Type",
    EL1.DNAME AS "Service Address",
    RL.NAME AS "Relationship Name",
    EL2.NAME AS "Component Name",
    EL2.CLASSNAME AS "Component Type",
    EL2.DNAME AS "Component Address"
FROM NEW formula.Elements('root=Elements') AS EL1,
     NEW formula.Elements() AS EL2,
     NEW formula.Relationships() AS RL
WHERE EL1.ID = RL.LEFTID
AND EL1.CLASSNAME = 'computer_workstation'
AND EL2.ID = RL.RIGHTID;
SELECT *
FROM Enterprise_Elements;
SELECT
    EL1.NAME AS "Service Name",
    EL1.CLASSNAME AS "Service Type",
    EL1.DNAME AS "Service Address",
    RL.NAME AS "Relationship Name",
    EL2.NAME AS "Component Name",
    EL2.CLASSNAME AS "Component Type",
    EL2.DNAME AS "Component Address"
FROM NEW formula.Elements('root=Elements') AS EL1,
     NEW formula.Elements() AS EL2,
     NEW formula.Relationships() AS RL
WHERE EL1.ID = RL.LEFTID
AND EL1.CLASSNAME = 'computer_workstation'
AND EL2.ID = RL.RIGHTID;
SELECT *
FROM NEW formula.Properties('root=Elements') AS properties;
SELECT *
FROM NEW formula.Relationships() AS RL
WHERE RL.NAME <> 'NAM';
```



---

# 5 Example Reports

SQL Views can be used to create many different types of reports. The following are five potential uses:

- ◆ Alarms
- ◆ Performance
- ◆ SLA catalog
- ◆ Availability, downtime, and outages based on Service Level Agreements (SLAs) and objectives
- ◆ Service catalog changes

A BSLM license key is required for performance reporting, service level catalog reporting, and availability reporting.

Sample reports ship with SQL Views and can be found in `/OperationsCenter_install_path/database/examples/mosql`.

The following sections contain various types of reports generated using SQL Views:

- ◆ [Section 5.1, “Alarms Reports,” on page 48](#)
- ◆ [Section 5.2, “Performance Reports,” on page 49](#)
- ◆ [Section 5.3, “SLA Catalog Reports,” on page 50](#)
- ◆ [Section 5.4, “SLA Availability Reports,” on page 51](#)
- ◆ [Section 5.5, “Service Catalog Changes Report,” on page 53](#)

# 5.1 Alarms Reports


Using SQL Views, you can create reports that contain historical alarm data. There are two system views that contain alarm data: *system\_elements\_alarms* and *system\_servicemodels\_alarms*. You can use these views to create reports. Two possible reports are events (alarms) by severity (Figure 5-1) and number of incidents by severity (Figure 5-2), as shown in the following examples:

Figure 5-1 Report showing events (alarms) by severity

## Service Model Event Report

3/9/2007 4:15:18PM

### Events by Severity




### Top 10 Most Recent Critical Events

<u>ID</u>	<u>Name</u>	<u>Description</u>	<u>Last Update</u>
38	PATROL	Host linupgs1 (linupgs1) offline status=closed: Retrying on port 3300	3/7/2008 8:48:42PM
41	N	Node Down.	12/12/2005 11:46:40AM
30	N	Node Down.	12/12/2005 11:46:40AM
27	N	Node Down.	12/12/2005 11:46:40AM
1,893	LOGFILE	TEST-CRITICAL-4	12/12/2005 11:46:52AM
31	linupdw4:/STATUS/linupdw2/AgentStatus	Alarm #1 of global parameter AgentStatus triggered on STATUS.linupdw2 . 0 <= 0.00 <= 0	12/8/2005 8:28:27PM
36	linuptm5:/LOGTEMP/var-adm-messagesKernelWarning1/LOGErrorLvl	Alarm #2 of global parameter LOGErrorLvl triggered on LOGTEMP.var-adm-messagesKernelWarning1 . 1 <= 2.00 <= 100	12/8/2005 8:28:28PM
21	linuptm5:/LOGTEMP/var-adm-messagesKernelWarning1/LOGErrorLvl	Alarm #2 of global parameter LOGErrorLvl triggered on LOGTEMP.var-adm-messagesKernelWarning1 . 1 <= 2.00 <= 100	12/8/2005 8:28:28PM
1,897	TEC	KAREN-CRITICAL-TEST	11/11/2005 12:54:58PM
1,896	TEC	ROB-CRITICAL-TEST	10/27/2005 11:43:40AM



Figure 5-2 Report showing the number of incidents by severity



## 5.2 Performance Reports

Historical performance data, such as element properties, alarm properties, performance series data, and severity counts can be captured in Operations Center and is then available in SQL Views in the Performance table.

A BSLM license key is required for performance reporting.

To capture performance data, you must set up element profiles, which apply matching criteria to select elements for which to collect data, and expressions, which identify the type of data saved for these elements. For more information about profiles and expressions, see “[Capturing Alarm and Performance History](#)” in the *Operations Center 5.6 Server Configuration Guide*.

In addition to collecting performance data for elements residing on the local Operations Center server, performance data for elements on remote servers can also be collected. To access data from another server requires an Intercommunication adapter. Data related to the Service Level Manager (such as availability, downtime, SLA/objective health, and SLA/objective key metrics) is not available over an Intercommunication adapter. For more information on the Intercommunication adapter, see the *Operations Center 5.6 Adapter and Integration Guide*.

You can create a report using SQL Views that contains performance data from both the local Operations Center server and remote Operations Center servers.

There are no system views that use the Performance table. So to create a report using performance data, you must create a custom view then use that view in your reporting tool.

To create a performance report for local and remote data:

- 1 Create an InterCommunication adapter.  
For instructions, see the [Operations Center 5.6 Adapter and Integration Guide](#).
- 2 Create and start a profile with expressions that track the desired performance data, such as an element property or an alarm property.  
For example, create a profile that stores the total number of alarms in the *Operations Center server* element or stores the queue size of the *Data Warehouse* element.
- 3 Create a view.  
In creating this view, select an element that has profile information, then select *Performance* as the table.
- 4 Configure SQL Views, if you have not done so already.  
For more information, see [Section 2.1, "Prerequisites," on page 9](#).
- 5 Extract the performance data into Microsoft Excel or Crystal Reports and create a report.  
For more information, see [Chapter 3, "Queries and Reports," on page 17](#).

## 5.3 SLA Catalog Reports

Using SQL Views, you have access to information about Service Level Agreements (SLAs).

A BSLM license key is required for SLA Catalog reporting.

The *system\_servicemodels\_agreement* view contains the following information about Service Level Agreements:

- ♦ Name of the agreement
- ♦ Name of any objectives
- ♦ Definitions of objectives
- ♦ Elements associated with each SLA and objective

You can use this view to create a report that gives you a service level catalog listing the Agreements and Objectives defined in the system. [Figure 5-3](#) illustrates this:

**Figure 5-3** Report showing a SLA catalog

**Service Level Catalog**

---

3/9/2007 4:29:16PM

SLA Name	Objective Name	Element	Definition
Bronze	Availability - On	SLA	During On periods, ensure 90% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Downtime	SLA	During On periods, allow a maximum of 3 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Availability - On	SLA	During On periods, ensure 99% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Outages	SLA	During On periods, allow a maximum of 1 outages of more than 0 seconds over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Availability - On	SLA	During On periods, ensure 95% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Downtime	SLA	During On periods, allow a maximum of 2 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Availability - On	CustomerA	During On periods, ensure 90% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Downtime	CustomerA	During On periods, allow a maximum of 3 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Availability - On	CustomerA	During On periods, ensure 99% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Outages	CustomerA	During On periods, allow a maximum of 1 outages of more than 0 seconds over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Availability - On	CustomerA	During On periods, ensure 95% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Downtime	CustomerA	During On periods, allow a maximum of 2 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Availability - On	CustomerB	During On periods, ensure 90% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Downtime	CustomerB	During On periods, allow a maximum of 3 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Availability - On	CustomerB	During On periods, ensure 99% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Outages	CustomerB	During On periods, allow a maximum of 1 outages of more than 0 seconds over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Availability - On	CustomerB	During On periods, ensure 95% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Downtime	CustomerB	During On periods, allow a maximum of 2 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Availability - On	CustomerC	During On periods, ensure 90% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Bronze	Downtime	CustomerC	During On periods, allow a maximum of 3 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Availability - On	CustomerC	During On periods, ensure 99% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Gold	Outages	CustomerC	During On periods, allow a maximum of 1 outages of more than 0 seconds over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Availability - On	CustomerC	During On periods, ensure 95% availability over 1 hours aligned and threshold condition Critical, Weight = 1
Sliver	Downtime	CustomerC	During On periods, allow a maximum of 2 seconds of downtime, over 1 hours aligned and threshold condition Critical, Weight = 1

## 5.4 SLA Availability Reports

To monitor the status of your Service Level Agreements (SLAs), you can write a report in SQL Views that includes availability, downtime, and breaches on specific elements during a month.

A BSLM license key is required for SLA Availability reporting.

- ◆ [Section 5.4.1, “Understanding Availability and Downtime,” on page 52](#)
- ◆ [Section 5.4.2, “Creating an Availability Report,” on page 53](#)

## 5.4.1 Understanding Availability and Downtime

Availability and downtime are defined as follows:

- ◆ *Downtime* and *Availability* are determined based on element condition data.
- ◆ *Downtime* is recorded in milliseconds.
- ◆ *Availability* is calculated based on the total time within the report time period.

For example, if you request availability for the month of January, the total possible time is the number of milliseconds from Jan 1, 12:00 AM until Feb 1, 12:00 AM.

*Availability* is determined by the formula: (total time in period minus total downtime in period) divided by total time in period.

The *Availability* value is between 0 and 1, where 1 = 100%.

By default, an element is available when its state is anything other than `CRITICAL`.

The *Calendar* and *Time Categories* specified are used to determine when system outages are relevant to the calculated *Availability*, *Downtime*, and *Outage* results. Only those system outages that occur during time windows of the *Calendar* that reference the included *Time Categories* are included in the calculated results. For example, outages that occur during a scheduled maintenance period are not included in the results if the *Blackout* time category is not specified as included in the view.

- ◆ Optionally specify *Agreement* and *Objective* as part of the Where clause in the query, to calculate *Availability* using the SLA and Objective definitions to determine the total time window, versus report time period.

*Agreement* and *Objective* columns are not saved values, but allow Agreement and Objective definitions to be applied to the *Availability* calculation. *Agreement* and *Objective* are displayed as `null` unless defined as part of the query. These columns are optional in the SQL query.

- ◆ *Discontinuity* is the time recorded when the software did not record any condition data. This might occur because of manually stopping an adapter, the Operations Center server, or a profile, or if the Operations Center server or a management system feed goes down unexpectedly.

It is not known by the software if the element was available during these times. By default, the BSLM engine calculates availability by assuming that there was no outage during these times.

Data on availability, outages, and breaches is stored in the availability, outages, and breaches tables. To use this data, you must create views that use these tables.

As an example, [Figure 5-4](#) shows an availability report that was created using data from the Business Metric Demo adapter that is populated via a sample script:

**Figure 5-4** Basic report showing availability, downtime, and outages

<u>START_TIME</u>	<u>END_TIME</u>	<u>ELEMENT_NAME</u>	<u>AVAILABILITY</u>	<u>DOWNTIME</u>	<u>OUTAGES</u>
3/9/2007 7:00:00AM	3/9/2007 8:00:00AM	Customers	0.00	3600000	1
3/9/2007 8:00:00AM	3/9/2007 9:00:00AM	Customers	0.00	3600000	1
3/9/2007 9:00:00AM	3/9/2007 10:00:00AM	Customers	60.61	1418015	1
3/9/2007 10:00:00AM	3/9/2007 11:00:00AM	Customers	51.67	1740000	1
3/9/2007 11:00:00AM	3/9/2007 12:00:00PM	Customers	48.33	1860000	1
3/9/2007 12:00:00PM	3/9/2007 1:00:00PM	Customers	100.00	0	0
3/9/2007 1:00:00PM	3/9/2007 2:00:00PM	Customers	100.00	0	0
3/9/2007 2:00:00PM	3/9/2007 3:00:00PM	Customers	100.00	0	0
3/9/2007 3:00:00PM	3/9/2007 4:00:00PM	Customers	100.00	0	0
3/9/2007 4:00:00PM	3/9/2007 5:00:00PM	Customers	100.00	0	0
3/9/2007 5:00:00PM	3/9/2007 6:00:00PM	Customers	100.00	0	0
3/9/2007 6:00:00PM	3/9/2007 7:00:00PM	Customers	100.00	0	0
3/9/2007 7:00:00PM	3/9/2007 8:00:00PM	Customers	100.00	0	0

This demo adapter and data ship with Operations Center. For more information, see [“Service Level Management Demo”](#) in the [Operations Center 5.6 Service Level Agreement Guide](#).

## 5.4.2 Creating an Availability Report

To create an availability report with demo BSLM data:

- 1 Configure a service model for the data.  
For the example, the service model is called *Customers* and contains one element called *Customer2*.
- 2 Create a new view called *Availability*.
- 3 Select *Customer for Element*.
- 4 Select *Availability for Table*.
- 5 Select a period for which you know there is data for the *Report Time Period* and a corresponding *Report Interval*.
- 6 Configure SQL Views, if you have not done so already.  
For more information, see [Section 2.1, "Prerequisites," on page 9](#).
- 7 Extract the performance data into Microsoft Excel or Crystal Reports and create a report.  
For more information, see [Chapter 3, "Queries and Reports," on page 17](#).

## 5.5 Service Catalog Changes Report

If you use Operations Center as a service catalog, you can create a report that gives you changes in the catalog if you have configured version tracking. The version tracking functionality in Operations Center records all changes to an element. When the following change events occur, they are recorded as alarms:

- ♦ Create, change, or remove an element
- ♦ Add, change, or remove an attribute
- ♦ Add, change, or remove a relationship

For more information about change events and version tracking, see the [Operations Center 5.6 Version Tracking Guide](#).

Your Operations Center server must be configured for version tracking in order to capture and report on change data.

You can use this data to create a report that shows all the changes to elements over a specific amount of time. This report gives you an indication of how your service catalog has changed over time. For an example of a report created with SQL Views, see the [Operations Center 5.6 Version Tracking Guide](#).

